

# Chapter 8,9: Memory

#### Adapted by Vikram Pudi






#### Background

- Program must be brought (from disk) into memory and placed within a process for it to be run
- Main memory and registers are only storage CPU can access directly
- Memory unit only sees a stream of addresses + read requests, or address + data and write requests
- Register access in one CPU clock (or less)
- Main memory can take many cycles
- Cache sits between main memory and CPU registers
- Protection of memory required to ensure correct operation





# Multistep Processing of a User Program



Source code addresses usually symbolic

Compiled code addresses **bind** to relocatable addresses

i.e. "14 bytes from beginning of this module" **Compile time**: If memory location known a priori, **absolute code** can be generated; must recompile code if starting location changes

Linker or loader will bind relocatable addresses to absolute addresses

**Load time**: Must generate **relocatable code** if memory location is not known at compile time

**Execution time**: Binding delayed until run time if the process can be moved during its execution from one memory segment to another



#### Logical vs. Physical Address Space

- The concept of a logical address space that is bound to a separate physical address space is central to proper memory management
  - Logical address generated by the CPU; also referred to as virtual address
  - Physical address address seen by the memory unit
- Logical and physical addresses are the same in compile-time and load-time address-binding schemes;
   logical (virtual) and physical addresses differ in execution-time address-binding scheme
- Logical address space is the set of all logical addresses generated by a program
- Physical address space is the set of all physical addresses generated by a program







#### Memory-Management Unit (мми)

- Hardware device that at run time maps virtual to physical address
- Many methods possible, covered in the rest of this chapter
- To start, consider simple scheme where the value in the relocation register is added to every address generated by a user process at the time it is sent to memory
  - Base register now called relocation register
  - MS-DOS on Intel 80x86 used 4 relocation registers
- The user program deals with *logical* addresses; it never sees the *real* physical addresses
  - Execution-time binding occurs when reference is made to location in memory
  - Logical address bound to physical addresses





# Dynamic relocation using a relocation register








#### **Dynamic Loading**

- Routine is not loaded until it is called
- Better memory-space utilization; unused routine is never loaded
- All routines kept on disk in relocatable load format
- Useful when large amounts of code are needed to handle infrequently occurring cases
- No special support from the operating system is required
  - Implemented through program design
  - OS can help by providing libraries to implement dynamic loading





#### **Dynamic Linking**

- Static linking system libraries and program code combined by the loader into the binary program image
- Dynamic linking –linking postponed until execution time
- Small piece of code, *stub*, used to locate the appropriate memory-resident library routine
- Stub replaces itself with the address of the routine, and executes the routine
- Operating system checks if routine is in processes' memory address
  - If not in address space, add to address space
- Dynamic linking is particularly useful for libraries
- System also known as shared libraries
- Consider applicability to patching system libraries
  - Versioning may be needed






## **Swapping**

- A process can be swapped temporarily out of memory to a backing store, and then brought back into memory for continued execution
  - Total physical memory space of processes can exceed physical memory
- Backing store fast disk large enough to accommodate copies of all memory images for all users; must provide direct access to these memory images
- Roll out, roll in swapping variant used for priority-based scheduling algorithms; lower-priority process is swapped out so higher-priority process can be loaded and executed
- Major part of swap time is transfer time; total transfer time is directly proportional to the amount of memory swapped
- System maintains a ready queue of ready-to-run processes which have memory images on disk
- Does the swapped out process need to swap back in to same physical addresses?
- Depends on address binding method
  - Plus consider pending I/O to / from process memory space
- Modified versions of swapping are found on many systems (i.e., UNIX, Linux, and Windows)
  - Swapping normally disabled
  - Started if more than threshold amount of memory allocated
  - Disabled again once memory demand reduced below threshold





#### Schematic View of Swapping







- If next processes to be put on CPU is not in memory, need to swap out a process and swap in target process
- Context switch time can then be very high
- 100MB process swapping to hard disk with transfer rate of 50MB/sec
  - Plus disk latency of 8 ms
  - Swap out time of 2008 ms
  - Plus swap in of same sized process
  - Total context switch swapping component time of 4016ms (> 4 seconds)
- Can reduce if reduce size of memory swapped by knowing how much memory really being used
  - System calls to inform OS of memory use via request memory and release memory







#### **Contiguous Allocation**

- Main memory usually into two partitions:
  - Resident operating system, usually held in low memory with interrupt vector
  - User processes then held in high memory
  - Each process contained in single contiguous section of memory
- Relocation registers used to protect user processes from each other, and from changing operating-system code and data
  - Base register contains value of smallest physical address
  - Limit register contains range of logical addresses each logical address must be less than the limit register
  - MMU maps logical address dynamically
  - Can then allow actions such as kernel code being transient and kernel changing size





# Hardware Support for Relocation and Limit Registers








## **Contiguous Allocation (Cont.)**


- Multiple-partition allocation
  - Degree of multiprogramming limited by number of partitions
  - Hole block of available memory; holes of various size are scattered throughout memory
  - When a process arrives, it is allocated memory from a hole large enough to accommodate it
  - Process exiting frees its partition, adjacent free partitions combined
  - Operating system maintains information about:
     a) allocated partitions
     b) free partitions (hole)



How to satisfy a request of size *n* from a list of free holes?

- First-fit: Allocate the *first* hole that is big enough
- **Best-fit**: Allocate the *smallest* hole that is big enough; must search entire list, unless ordered by size
  - Produces the smallest leftover hole
- Worst-fit: Allocate the *largest* hole; must also search entire list
  - Produces the largest leftover hole

First-fit and best-fit better than worst-fit in terms of speed and storage utilization



#### Fragmentation

- **External Fragmentation** total memory space exists to satisfy a request, but it is not contiguous
- Internal Fragmentation allocated memory may be slightly larger than requested memory; this size difference is memory internal to a partition, but not being used
- First fit analysis reveals that given *N* blocks allocated, 0.5 *N* blocks lost to fragmentation
  - 1/3 may be unusable -> 50-percent rule





# Fragmentation (Cont.)

- Reduce external fragmentation by compaction
  - Shuffle memory contents to place all free memory together in one large block
  - Compaction is possible only if relocation is dynamic, and is done at execution time
  - I/O problem
    - Latch job in memory while it is involved in I/O
    - Do I/O only into OS buffers
- Now consider that backing store has same fragmentation problems






## **Paging**

- Physical address space of a process can be noncontiguous; process is allocated physical memory whenever the latter is available
- Divide physical memory into fixed-sized blocks called frames
  - Size is power of 2, between 512 bytes and 16 Mbytes
- Divide logical memory into blocks of same size called pages
- Keep track of all free frames
- To run a program of size *N* pages, need to find *N* free frames and load program
- Set up a page table to translate logical to physical addresses
- Backing store likewise split into pages
- Still have Internal fragmentation





#### **Address Translation Scheme**


- Address generated by CPU is divided into:
  - Page number (p) used as an index into a page table which contains base address of each page in physical memory
  - Page offset (d) combined with base address to define the physical memory address that is sent to the memory unit

page number	page offset
p	d
m - n	n

For given logical address space 2<sup>m</sup> and page size 2<sup>n</sup>



#### **Paging Hardware**






#### Paging Model of Logical and Physical Memory

page 0
page 1
page 2
page 3
logical memory

frame number 0 page 0 1 3 page 2 page 1 4 5 6 page 3 physical memory



#### Paging Example



n=2 and m=4 32-byte memory and 4-byte pages






#### Paging (Cont.)

- Calculating internal fragmentation
  - Page size = 2,048 bytes
  - Process size = 72,766 bytes
  - 35 pages + 1,086 bytes
  - Internal fragmentation of 2,048 1,086 = 962 bytes
  - Worst case fragmentation = 1 frame 1 byte
  - On average fragmentation = 1 / 2 frame size
  - So small frame sizes desirable?
  - But each page table entry takes memory to track
  - Page sizes growing over time
    - ▶ Solaris supports two page sizes 8 KB and 4 MB
- Process view and physical memory now very different
- By implementation process can only access its own memory






#### **Free Frames**



Before allocation

After allocation






#### Implementation of Page Table

- Page table is kept in main memory
- Page-table base register (PTBR) points to the page table
- Page-table length register (PTLR) indicates size of the page table
- In this scheme every data/instruction access requires two memory accesses
  - One for the page table and one for the data / instruction
- The two memory access problem can be solved by the use of a special fast-lookup hardware cache called associative memory or translation look-aside buffers (TLBs)
- Some TLBs store address-space identifiers (ASIDs) in each TLB entry uniquely identifies each process to provide address-space protection for that process
  - Otherwise need to flush at every context switch
- TLBs typically small (64 to 1,024 entries)
- On a TLB miss, value is loaded into the TLB for faster access next time
  - Replacement policies must be considered
  - Some entries can be wired down for permanent fast access





#### **Associative Memory**


Associative memory – parallel search

Page #	Frame #

- Address translation (p, d)
  - If p is in associative register, get frame # out
  - Otherwise get frame # from page table in memory



#### **Paging Hardware With TLB**







#### **Effective Access Time**

- Associative Lookup =  $\varepsilon$  time unit
  - Can be < 10% of memory access time</li>
- $\blacksquare$  Hit ratio =  $\alpha$ 
  - Hit ratio percentage of times that a page number is found in the associative registers; ratio related to number of associative registers
- Consider  $\alpha$  = 80%,  $\epsilon$  = 20ns for TLB search, 100ns for memory access
- **■** Effective Access Time (EAT)

EAT = 
$$(1 + \varepsilon) \alpha + (2 + \varepsilon)(1 - \alpha)$$
  
=  $2 + \varepsilon - \alpha$ 

- Consider  $\alpha = 80\%$ ,  $\varepsilon = 20$ ns for TLB search, 100ns for memory access
  - EAT = 0.80 x 120 + 0.20 x 220 = 140ns
- Consider slower memory but better hit ratio ->  $\alpha$  = 98%,  $\epsilon$  = 20ns for TLB search, 140ns for memory access
  - EAT = 0.98 x 160 + 0.02 x 300 = 162.8ns






#### **Memory Protection**

- Memory protection implemented by associating protection bit with each frame to indicate if read-only or read-write access is allowed
  - Can also add more bits to indicate page execute-only, and so on
- Valid-invalid bit attached to each entry in the page table:
  - "valid" indicates that the associated page is in the process' logical address space, and is thus a legal page
  - "invalid" indicates that the page is not in the process' logical address space
  - Or use PTLR
- Any violations result in a trap to the kernel





#### Valid (v) or Invalid (i) Bit In A Page Table





#### **Shared Pages**

#### Shared code

- One copy of read-only (reentrant) code shared among processes (i.e., text editors, compilers, window systems)
- Similar to multiple threads sharing the same process space
- Also useful for interprocess communication if sharing of read-write pages is allowed


#### Private code and data

- Each process keeps a separate copy of the code and data
- The pages for the private code and data can appear anywhere in the logical address space





#### **Shared Pages Example**








#### Structure of the Page Table

- Memory structures for paging can get huge using straight-forward methods
  - Consider a 32-bit logical address space as on modern computers
  - Page size of 4 KB (2<sup>12</sup>)
  - Page table would have 1 million entries (2<sup>32</sup> / 2<sup>12)</sup>
  - If each entry is 4 bytes -> 4 MB of physical address space / memory for page table alone
    - That amount of memory used to cost a lot
    - Don't want to allocate that contiguously in main memory
- Hierarchical Paging
- Hashed Page Tables
- Inverted Page Tables






# **Hierarchical Page Tables**

- Break up the logical address space into multiple page tables
- A simple technique is a two-level page table
- We then page the page table






#### **Two-Level Page-Table Scheme**







# **Two-Level Paging Example**


- A logical address (on 32-bit machine with 1K page size) is divided into:
  - a page number consisting of 22 bits
  - a page offset consisting of 10 bits
- Since the page table is paged, the page number is further divided into:
  - a 12-bit page number
  - a 10-bit page offset
- Thus, a logical address is as follows:

page num	ber	page offset
$p_1$	$\rho_{\scriptscriptstyle 2}$	d
12	10	10

- where  $p_1$  is an index into the outer page table, and  $p_2$  is the displacement within the page of the inner page table
- Known as forward-mapped page table



## **Address-Translation Scheme**








# 64-bit Logical Address Space

- Even two-level paging scheme not sufficient
- If page size is 4 KB (2<sup>12</sup>)
  - Then page table has 2<sup>52</sup> entries
  - If two level scheme, inner page tables could be 2<sup>10</sup> 4-byte entries
  - Address would look like

outer page	inner page	page offset	
$p_1$	$\rho_{\scriptscriptstyle 2}$	d	
42	10	12	

- Outer page table has 2<sup>42</sup> entries or 2<sup>44</sup> bytes
- One solution is to add a 2<sup>nd</sup> outer page table
- But in the following example the 2<sup>™</sup> outer page table is still 2<sup>¾</sup> bytes in size
  - And possibly 4 memory access to get to one physical memory location





# **Three-level Paging Scheme**

outer page	inner page	offset
$p_1$	$p_2$	d
42	10	12

2nd outer page	outer page	inner page	offset
$p_1$	$p_2$	$p_3$	d
32	10	10	12






# Hashed Page Tables

- Common in address spaces > 32 bits
- The virtual page number is hashed into a page table
  - This page table contains a chain of elements hashing to the same location
- Each element contains (1) the virtual page number (2) the value of the mapped page frame (3) a pointer to the next element
- Virtual page numbers are compared in this chain searching for a match
  - If a match is found, the corresponding physical frame is extracted





# **Hashed Page Table**








# **Inverted Page Table**

- Rather than each process having a page table and keeping track of all possible logical pages, track all physical pages
- One entry for each real page of memory
- Entry consists of the virtual address of the page stored in that real memory location, with information about the process that owns that page
- Decreases memory needed to store each page table, but increases time needed to search the table when a page reference occurs
- Use hash table to limit the search to one or at most a few page-table entries
  - TLB can accelerate access
- But how to implement shared memory?
  - One mapping of a virtual address to the shared physical address






# **Inverted Page Table Architecture**






# Segmentation: User's View of a Program







# Segmentation Architecture

Logical address consists of a two tuple:


<segment-number, offset>,

All details like paging, but since segments vary in length, memory allocation is a dynamic storage-allocation problem






# **Segmentation Hardware**





physical memory



# **Virtual Memory**










physical memory



# Page Fault

If there is a reference to a page, first reference to that page will trap to operating system:

#### page fault

- 1. Operating system looks at another table to decide:
  - Invalid reference ⇒ abort
  - Just not in memory
- 2. Get empty frame
- 3. Swap page into frame via scheduled disk operation
- 4. Reset tables to indicate page now in memory Set validation bit = v
- 5. Restart the instruction that caused the page fault






# **Aspects of Demand Paging**


- Extreme case start process with no pages in memory
  - OS sets instruction pointer to first instruction of process, non-memory-resident -> page fault
  - And for every other process pages on first access
  - Pure demand paging
- Actually, a given instruction could access multiple pages -> multiple page faults
  - Pain decreased because of locality of reference
- Hardware support needed for demand paging
  - Page table with valid / invalid bit
  - Secondary memory (swap device with swap space)
  - Instruction restart





### **Instruction Restart**


- Consider an instruction that could access several different locations
  - block move



- auto increment/decrement location
- Restart the whole operation?
  - What if source and destination overlap?



# Steps in Handling a Page Fault






- Page Fault Rate  $0 \le p \le 1$ 
  - if p = 0 no page faults
  - if p = 1, every reference is a fault
- Effective Access Time (EAT)

```
EAT = (1 - p) x memory access
+ p (page fault overhead
+ swap page out
+ swap page in
+ restart overhead
```





# **Demand Paging Example**

- Memory access time = 200 nanoseconds
- Average page-fault service time = 8 milliseconds
- EAT =  $(1 p) \times 200 + p$  (8 milliseconds) =  $(1 - p \times 200 + p \times 8,000,000$ =  $200 + p \times 7,999,800$
- If one access out of 1,000 causes a page fault, then EAT = 8.2 microseconds.


This is a slowdown by a factor of 40!!

- If want performance degradation < 10 percent</p>
  - 220 > 200 + 7,999,800 x p20 > 7,999,800 x p
  - p < .0000025
  - < one page fault in every 400,000 memory accesses</p>





# Page Replacement





## Page and Frame Replacement Algorithms

- **Frame-allocation algorithm** determines
  - How many frames to give each process
  - Which frames to replace
- Page-replacement algorithm
  - Want lowest page-fault rate on both first access and re-access
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
  - String is just page numbers, not full addresses
  - Repeated access to the same page does not cause a page fault
- In all our examples, the reference string is


7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1






# FIFO Page Replacement





page frames





# **Optimal Algorithm**

- Replace page that will not be used for longest period of time
  - 9 is optimal for the example on the next slide
- How do you know this?
  - Can't read the future
- Used for measuring how well your algorithm performs






# Least Recently Used (LRU) Algorithm

- Use past knowledge rather than future
- Replace page that has not been used in the most amount of time
- Associate time of last use with each page

### reference string



page frames





# **Thrashing**

- If a process does not have "enough" pages, the page-fault rate is very high
  - Page fault to get page
  - Replace existing frame
  - But quickly need replaced frame back
  - This leads to:
    - Low CPU utilization
    - Operating system thinking that it needs to increase the degree of multiprogramming
    - Another process added to the system
- Thrashing ≡ a process is busy swapping pages in and out





# **Demand Paging and Thrashing**

- Why does demand paging work?
  Locality model
  - Process migrates from one locality to another
  - Localities may overlap
- Why does thrashing occur?Σ size of locality > total memory size
  - Limit effects by using local or priority page replacement



# End of Chapter 8,9

