## **GIST 7128 ArcGIS 1: Introduction**



Lecture 6 **Editing and Geocoding** 

### Geocoding

- Address list  $\rightarrow$  Point map layer
- Input:
  - Address table or text file
  - Street Segment layer with street names (name/type/direction) and address ranges (L\_F\_Add, L\_T\_Add, R\_F\_Add, R\_T\_Add)
  - Address Locator metadata for above plus rules, tolerances
- Output:
  - Address Points layer interpolated position on correct side
  - saved as a shapefile or in geodatabase
  - New Attributes (optional) X,Y, and match results fields
- Example in Getting to Know ArcGIS, chapter 14

#### **Data Editing**

- Modification (or Creation) of spatial & attribute data
- ArcMap can edit shapefiles and geodatabases
- Using these general toolboxes...





...and other advanced/specialized editing tools


#### **General Editing Steps**





- 2. Open Editor toolbar
- 3. Editor > Start Editing to begin edit session
- 4. Select Tool editing operation
  - e.g. create new feature
- 5. Specify the target layer or feature(s)
- 6. Perform the operation
- 7. Select Editor > Save Edits saves data (not mxd)
  - data are not automatically saved
- 8. Editor > Stop Editing end edit session

























































### **Snapping Toolbox**



- Vector data must be "clean"
  - e.g. lines must connect, be segmented at intersections
  - polygons must close and not overlap adjacent polygons
- Snapping is used while adding or editing spatial data
- Set mode(s) on Snapping toolbox:
  - Point, End, Vertex, Edge (on toolbar)
  - Intersection, Midpoint, Tangent (on menu)
- Multiple modes active at same time
- Features added or edited will follow snapping rules

25

# **Snapping Options and Tips**



- · Set snapping tolerance
- default is 10 pixels
- · Enable Snap Tips
  - appear when near a valid feature
  - shows layer name and snap mode

 Press and hold spacebar to suppress snapping while editing

Parcels: Vertex

26

OK Cancel

#### **Feature Construction Toolbox**





- a.k.a. Sketch Toolbox & Tools to:
- Create features
- To provide input for other tools
  - · e.g. cut polygon, extend lines
- Can reveal the sketch of an existing feature to modify it
  - · Double-click with Edit Tool
  - · Or use Edit Vertices tool
- 11 different CAD-like drawing tools
- Also on Editor Toolbox



27

#### **Feature Construction Toolbox** To Create... Example Tool Straight / (default) digitize vertices of line street centerlines, parcels Segment or polygon features cul-de-sac from underlying air Arc r parametric (true) curve: based on startpoint, midpoint, endpoint photo smoothed curves, with handles Bézier railway to change adjust its shape Direction point or vertex using a distance pole at specified distance -Distance and direction from known from corner of one building and at defined angle from point(s) corner of another building pole based on field measurepoint or vertex at the -Distance intersection of two distances ments: 50 feet from one from two other points building corner and 75 feet from another 28





#### **Map Topology for Editing**

- Designed for easier and more precise editing
- For Shapefile and Geodatabase feature classes
- · Polygon features do not share common borders
  - Instead, each has a unique copy of the border
  - If one adjacent polygon is edited, the other is not changed;
    can cause gaps or overlaps
- Map Topology is for the current map extents and the current editing session only
- Geodatabase Topology is persistent and has built-in integrity rules to detect spatial errors

**Topology Toolbar** 



- 1. Start Editing
- 2. On the topology toolbar, click the Map Topology button
- 3. Check the layers to participate in the topology
- 4. Also set the cluster tolerance
  - · Maximum distance between vertices that will be snapped together
- 5. Click the Topology Edit tool and click the features you want to edit using the map topology
- 6. The map topology is created for:
  - · features visible in the current display extent
  - · the current editing session
- 7. Perform editing operations
  - e.g. move vertex applied to multiple polygons

32

Lecture 6 Page 8

31