

Lecture 3 - Ionic Conductivity

Lecture summary

- Recap of defect types
- Ionic conductivity
- Conduction mechanisms
- Ionic migration paths
- Energetics of conduction

Defect recap

Place these defects on the axes

Drag & drop items on the image, or click on an item then on its position on the image

Change
in Density



Submit

Wooclap Code: SUJNYY

Defect recap results

wooclap



Quiz results will be available here
after the lecture

Conductivity

- Many ionic solids conduct electricity; due to *ionic* and/or *electronic* motion.
- Most ionic solids are electrically insulating/semiconducting (localised electrons)

Conductivity

- Many ionic solids conduct electricity; due to *ionic* and/or *electronic* motion.
- Most ionic solids are electrically insulating/semiconducting (localised electrons)
- Ionic conductors are important!

	
Batteries (Lecture 4)	Sensors
	
Separation Membranes	Fuel Cells (Lecture 6)

Origin of ionic conduction

- Ionic conductivity is dominated by **defects**
 - In an ideal crystal, ions can't easily move
 - vacancies and/or interstitials are the main charge carriers

Origin of ionic conduction


- Ionic conductivity is dominated by **defects**
 - In an ideal crystal, ions can't easily move
 - vacancies and/or interstitials are the main charge carriers
- Conductivity, $\sigma = nq\mu$, where
 - n is number of charge carriers
 - q is charge
 - μ is the mobility of charge carriers

Origin of ionic conduction

- Ionic conductivity is dominated by **defects**
 - In an ideal crystal, ions can't easily move
 - vacancies and/or interstitials are the main charge carriers
- Conductivity, $\sigma = nq\mu$, where
 - n is number of charge carriers
 - q is charge
 - μ is the mobility of charge carriers
- In ionic solids, conductivity covers $10^{-16} \text{ S m}^{-1} - 10^3 \text{ S m}^{-1}$
 - most solids are limited to around 10^{-2} S m^{-1}
 - Liquid electrolytes typically $10^{-1} - 10^3 \text{ S m}^{-1}$

Measuring Conductivity


- For electronic conductors, this is simple:
 - Apply a voltage (V) and measure the resulting current (I)
 - Resistance (in Ω) is found through Ohm's law; $V = IR$
 - Resistivity (in $\Omega \text{ cm}$) of the material calculated from geometry
- Resistivity ρ (in $\Omega \text{ cm}$) =
$$\frac{1}{\text{Conductivity } \sigma \text{ (in } \text{S cm}^{-1}\text{)}}$$



In reality, we normally use two wires for V and two for I


Measuring Ionic Conductivity

- Ions cannot flow round a circuit, so current drops with a constant applied voltage




Measuring Ionic Conductivity

- Ions cannot flow round a circuit, so current drops with a constant applied voltage



- Instead, we use an alternating voltage - this is called Impedance spectroscopy (see [lecture 5](#))




Ion migration mechanisms

Three 'main' mechanisms of ionic migration


1. Vacancy mechanism

Vacancies move throughout the lattice (atoms move into vacancy)



2. Interstitial mechanism

Ions hop between interstitial sites



3. Interstitialcy (knock-on) mechanism

Interstitial ions 'push' into a neighbouring site



Vacancy, Interstitial or Interstitialcy?

**What technique(s) could you use to distinguish
the mechanism?**

Write your answer...

30 remaining

You can answer multiple times

Submit



Suggestions

wooclap

Quiz results will be available here
after the lecture

Migration paths


Ion paths are rarely **direct**, but will take the **lowest energy route**.




Pathways can be complex

- Migration pathways can be calculated and/or experimentally determined


e.g. **NASICON** Na^+ conductor, $\text{Na}_3\text{Zr}_2(\text{SiO}_4)_2(\text{PO}_4)$:



MD density plot



BVEL




MEM/Rietveld

Migration energetics

- Defect mobility (μ) is a thermally-activated process:

$$\mu = \mu_0 \exp\left(-\frac{E_a}{RT}\right)$$

- interstitial sites are higher energy than vacancies, so will be more mobile.



Variation with temperature

As $\sigma = nq\mu$ and μ is thermally-activated,

$$\begin{aligned}\sigma &= nq\mu_0 \exp\left(-\frac{E_a}{RT}\right) \\ &= A \exp\left(-\frac{E_a}{RT}\right)\end{aligned}$$


Variation with temperature

As $\sigma = nq\mu$ and μ is thermally-activated,

$$\begin{aligned}\sigma &= nq\mu_0 \exp\left(-\frac{E_a}{RT}\right) \\ &= A \exp\left(-\frac{E_a}{RT}\right)\end{aligned}$$

Plotting $\ln \sigma$ vs. $\frac{1}{T}$ should give a straight line



- more commonly we plot $\log_{10} \sigma$ vs. $\frac{1000}{T}$ for high temperature measurements
- gradient is $\frac{-E_a}{R}$ (or $\frac{-E_a}{2303R}$ using base 10).



Nasicon conductivity

Defect ordering



More defects increase conductivity, but interaction can form new phases, e.g. $\text{Mo}_{1-x}\text{Cr}_x\text{O}_2$:



Vacancy ordering

Vacancies can order in lines/planes, leading to structural 'collapse'.

Plane-like defects are often described as *shear phases*



Lecture recap

- Defects can give rise to ionic conduction
 - Occurs by three main mechanisms:
 - Vacancy hopping
 - Interstitial hopping
 - interstitialcy (knock-on) cooperation
- Ionic conductivity is thermally-activated
 - shows Arrhenius-like behaviour
- Different defects have different conduction energetics
 - Pathways can sometimes be determined experimentally
- Ordering of defects can sometimes give rise to new crystal phases with different conduction properties

Feedback



What did you like or dislike about lecture 3?

Write your answer...

Submit

A large, semi-transparent rectangular box with rounded corners and a thin gray border. It contains the placeholder text "Write your answer...". Below this box is a long, horizontal, semi-transparent blue bar with a slight gradient, which serves as a background for the "Submit" button.

