

Namespace SimpleRelm

Classes

[RelmHelper](#)

Provides a collection of helper methods and properties for interacting with relational databases.

Class RealmHelper

Namespace: [SimpleRealm](#)

Assembly: SimpleRealm.dll

Provides a collection of helper methods and properties for interacting with relational databases.

```
public class RealmHelper
```

Inheritance

[object](#)  ← RealmHelper

Inherited Members

[object.ToString\(\)](#)  , [object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  ,
[object.ReferenceEquals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  , [object.GetType\(\)](#)  ,
[object.MemberwiseClone\(\)](#) 

Remarks

The [RealmHelper](#) class offers a variety of static methods and properties to simplify database operations, including connection management, query execution, and data retrieval. It also provides utilities for handling execution errors, managing database contexts, and working with relational models. This class is designed to abstract common database operations, making it easier to interact with MySQL databases and manage data access layers in a consistent and reusable manner.

Properties

CurrentContext

Gets or sets the current context for the application.

```
public static IRealmContext CurrentContext { get; set; }
```

Property Value

[IRealmContext](#)

Remarks

This property holds the active context used throughout the application. Ensure that the context is properly initialized before accessing this property.

HasError

Convenience function to check if there's an error cached.

```
public static bool HasError { get; }
```

Property Value

[bool](#) 

LastExecutionError

Convenience function to get the last exception message

```
public static string LastExecutionError { get; }
```

Property Value

[string](#) 

LastExecutionException

Caches the last execution error encountered

```
public static Exception LastExecutionException { get; }
```

Property Value

[Exception](#) 

RootLoggingDirectory

Gets the root directory where logging files are stored.

```
public static string RootLoggingDirectory { get; }
```

Property Value

[string](#) 

Methods

BulkTableWrite<T>(MySQLConnection, IEnumerable<T>, string, MySQLTransaction, Type, int, bool, bool, bool)

Writes a collection of data to a database table in bulk, optimizing for performance.

```
public static int BulkTableWrite<T>(MySQLConnection establishedConnection, IEnumerable<T>
sourceData, string tableName = null, MySQLTransaction sqlTransaction = null, Type forceType
= null, int batchSize = 100, bool allowAutoIncrementColumns = false, bool
allowPrimaryKeyColumns = false, bool allowUniqueColumns = false)
```

Parameters

establishedConnection MySQLConnection

An open `MySQL.Data.MySqlClient.MySqlConnection` to the database where the data will be written. The connection must remain open for the duration of the operation.

sourceData [IEnumerable](#)  <T>

The collection of data to be written to the database table. Each item in the collection represents a row to be inserted.

tableName [string](#) 

The name of the target database table. If `null`, the table name is inferred from the type `T`.

sqlTransaction MySQLTransaction

An optional `MySQL.Data.MySqlClient.MySQLTransaction` to associate with the bulk write operation. If `null`, the operation is performed without a transaction.

forceType [Type](#)

An optional [Type](#) to enforce a specific type mapping for the data being written. If **null**, the type is inferred from **T**.

batchSize [int](#)

The number of rows to write in each batch. Defaults to 100. Larger batch sizes may improve performance but require more memory.

allowAutoIncrementColumns [bool](#)

A value indicating whether columns with auto-increment constraints are included in the bulk write operation. If **true**, auto-increment columns are included; otherwise, they are excluded.

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns are included in the bulk write operation. If **true**, primary key columns are included; otherwise, they are excluded.

allowUniqueColumns [bool](#)

A value indicating whether unique constraint columns are included in the bulk write operation. If **true**, unique columns are included; otherwise, they are excluded.

Returns

[int](#)

The total number of rows successfully written to the database table.

Type Parameters

T

The type of the objects in the **sourceData** collection.

Remarks

This method is designed for high-performance bulk data insertion and should be used when inserting large datasets. Ensure that the **establishedConnection** is open and valid before calling this method. If **tableName** is not provided, the method attempts to infer the table name from the type **T**.

BulkTableWrite<T>(MySqlConnection, T, string, MySqlConnection, Type, int, bool, bool, bool)

Writes a collection of data to a database table in bulk, optimizing for performance.

```
public static int BulkTableWrite<T>(MySqlConnection establishedConnection, T sourceData,
string tableName = null, MySqlConnection sqlTransaction = null, Type forceType = null, int
batchSize = 100, bool allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns =
false, bool allowUniqueColumns = false)
```

Parameters

establishedConnection MySqlConnection

An open MySql.Data.MySqlClient.MySqlConnection to the database where the data will be written. The connection must remain open for the duration of the operation.

sourceData T

The data to be written to the table. This can be a collection of objects or a DataTable.

tableName [string](#)

The name of the target database table. If null, the table name is inferred from the type of **T**.

sqlTransaction MySqlConnection

An optional MySql.Data.MySqlClient.MySqlTransaction to associate with the bulk write operation. If null, the operation is performed outside of a transaction.

forceType [Type](#)

An optional [Type](#) to enforce a specific type for the data being written. If null, the type is inferred from **T**.

batchSize [int](#)

The number of rows to write in each batch. Defaults to 100. Larger batch sizes may improve performance but require more memory.

allowAutoIncrementColumns [bool](#)

Indicates whether auto-increment columns in the target table are allowed to be written. Defaults to [false](#).

`allowPrimaryKeyColumns` [bool](#)

Indicates whether primary key columns in the target table are allowed to be written. Defaults to [false](#).

`allowUniqueColumns` [bool](#)

Indicates whether unique columns in the target table are allowed to be written. Defaults to [false](#).

Returns

[int](#)

The number of rows successfully written to the database table.

Type Parameters

T

The type of the data source. Typically a collection of objects or a DataTable.

Remarks

This method is designed for high-performance bulk data insertion. It is the caller's responsibility to ensure that the data in `sourceData` matches the schema of the target table.

If `allowAutoIncrementColumns`, `allowPrimaryKeyColumns`, or `allowUniqueColumns` are set to [true](#), the caller must ensure that the data does not violate database constraints.

The method does not automatically handle schema mismatches or data validation. Ensure that the data types and column mappings align with the target table.

BulkTableWrite<T>(IRelmContext, IEnumerable<T>, string, Type, int, bool, bool, bool)

Writes a collection of data to a database table in bulk, optimizing for performance.

```
public static int BulkTableWrite<T>(IRelmContext relmContext, IEnumerable<T> sourceData,
string tableName = null, Type forceType = null, int batchSize = 100, bool
allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool
allowUniqueColumns = false)
```

Parameters

realmContext [IRelmContext](#)

The database context used to perform the bulk write operation. Cannot be [null](#).

sourceData [IEnumerable<T>](#)

The collection of data to be written to the table. Cannot be [null](#) or empty.

tableName [string](#)

The name of the target database table. If [null](#), the table name is inferred from the type **T**.

forceType [Type](#)

An optional type to enforce for the table schema. If [null](#), the schema is inferred from **T**.

batchSize [int](#)

The number of records to write in each batch. Must be greater than 0. Defaults to 100.

allowAutoIncrementColumns [bool](#)

A value indicating whether auto-increment columns in the target table are allowed to be explicitly written to. If [false](#), auto-increment columns are ignored during the write operation.

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns in the target table are allowed to be explicitly written to. If [false](#), primary key columns are ignored during the write operation.

allowUniqueColumns [bool](#)

A value indicating whether unique columns in the target table are allowed to be explicitly written to. If [false](#), unique columns are ignored during the write operation.

Returns

[int](#)

The total number of rows successfully written to the database table.

Type Parameters

T

The type of the objects in the `sourceData` collection.

Remarks

This method is designed for high-performance bulk data insertion and may bypass certain database constraints depending on the provided parameters. Use caution when enabling options such as `allowAutoIncrementColumns`, `allowPrimaryKeyColumns`, or `allowUniqueColumns` to avoid violating database integrity.

BulkTableWrite<T>(IRelmContext, T, string, Type, int, bool, bool, bool)

Writes a collection of data to a database table in bulk, optimizing for performance.

```
public static int BulkTableWrite<T>(IRelmContext relmContext, T sourceData, string tableName = null, Type forceType = null, int batchSize = 100, bool allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool allowUniqueColumns = false)
```

Parameters

`relmContext` [IRelmContext](#)

The database context used to perform the bulk write operation. Cannot be [null](#).

`sourceData` `T`

The data to be written to the table. This can be a collection of objects or a single object. Cannot be [null](#).

`tableName` [string](#)

The name of the target database table. If [null](#), the table name is inferred from the type `T`.

`forceType` [Type](#)

An optional type to enforce for the operation. If [null](#), the type is inferred from `T`.

`batchSize` [int](#)

The number of rows to write in each batch. Must be greater than 0. Defaults to 100.

`allowAutoIncrementColumns` [bool](#)

A value indicating whether auto-increment columns are allowed to be included in the bulk write operation. If [false](#), auto-increment columns are excluded.

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns are allowed to be included in the bulk write operation. If [false](#), primary key columns are excluded.

allowUniqueColumns [bool](#)

A value indicating whether unique columns are allowed to be included in the bulk write operation. If [false](#), unique columns are excluded.

Returns

[int](#)

The total number of rows successfully written to the database.

Type Parameters

T

The type of the data to be written. This can be a collection or a single object.

Remarks

This method is designed for high-performance bulk data insertion. It allows fine-grained control over which columns are included in the operation, such as auto-increment, primary key, and unique columns. Use the optional parameters to customize the behavior as needed.

BulkTableWrite<T>(IRelmQuickContext, IEnumerable<T>, string, Type, int, bool, bool, bool)

Writes a collection of data to a database table in bulk, optimizing for performance.

```
public static int BulkTableWrite<T>(IRelmQuickContext relmQuickContext, IEnumerable<T>
sourceData, string tableName = null, Type forceType = null, int batchSize = 100, bool
allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool
allowUniqueColumns = false)
```

Parameters

realmQuickContext [IRelmQuickContext](#)

The database context used to execute the bulk write operation. Cannot be [null](#).

sourceData [IEnumerable](#) <T>

The collection of data to be written to the table. Cannot be [null](#) or empty.

tableName [string](#)

The name of the target database table. If [null](#), the table name is inferred from the type **T**.

forceType [Type](#)

An optional type to enforce for the table schema. If [null](#), the schema is inferred from **T**.

batchSize [int](#)

The number of rows to write in each batch. Must be greater than 0. Defaults to 100.

allowAutoIncrementColumns [bool](#)

A value indicating whether auto-increment columns in the target table are allowed to be written to. If [false](#), auto-increment columns are excluded from the operation.

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns in the target table are allowed to be written to. If [false](#), primary key columns are excluded from the operation.

allowUniqueColumns [bool](#)

A value indicating whether unique columns in the target table are allowed to be written to. If [false](#), unique columns are excluded from the operation.

Returns

[int](#)

The total number of rows successfully written to the database.

Type Parameters

T

The type of the objects in the `sourceData` collection.

Remarks

This method is designed for high-performance bulk insert operations. It is the caller's responsibility to ensure that the data in `sourceData` conforms to the schema of the target table.

BulkTableWrite<T>(IRelmQuickContext, T, string, Type, int, bool, bool, bool)

Writes data in bulk to a database table, with options to customize the operation.

```
public static int BulkTableWrite<T>(IRelmQuickContext relmQuickContext, T sourceData, string
tableName = null, Type forceType = null, int batchSize = 100, bool allowAutoIncrementColumns
= false, bool allowPrimaryKeyColumns = false, bool allowUniqueColumns = false)
```

Parameters

`relmQuickContext` [IRelmQuickContext](#)

The database context used to execute the bulk write operation. Cannot be [null](#).

`sourceData` `T`

The data to be written to the table. This can be a collection or a single object. Cannot be [null](#).

`tableName` [string](#)

The name of the target database table. If [null](#), the table name is inferred from the type `T`.

`forceType` [Type](#)

An optional type to enforce for the operation. If [null](#), the type is inferred from `T`.

`batchSize` [int](#)

The number of rows to write in each batch. Must be greater than 0. Defaults to 100.

`allowAutoIncrementColumns` [bool](#)

A value indicating whether auto-increment columns in the target table are allowed to be explicitly written. If [false](#), auto-increment columns are ignored during the write operation.

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns in the target table are allowed to be explicitly written. If [false](#), primary key columns are ignored during the write operation.

allowUniqueColumns [bool](#)

A value indicating whether unique columns in the target table are allowed to be explicitly written. If [false](#), unique columns are ignored during the write operation.

Returns

[int](#)

The total number of rows successfully written to the database table.

Type Parameters

T

The type of the data source to be written to the table.

Remarks

This method provides a high-performance way to insert or update large amounts of data in a database table. The behavior of the operation can be customized using the optional parameters to control how specific columns (e.g., auto-increment, primary key, or unique columns) are handled.

BulkTableWrite<T>(Enum, IEnumerable<T>, string, Type, int, bool, bool, bool)

Writes a collection of data to a database table in bulk, using the specified connection and options.

```
public static int BulkTableWrite<T>(Enum connectionName, IEnumerable<T> sourceData, string
tableName = null, Type forceType = null, int batchSize = 100, bool allowAutoIncrementColumns
= false, bool allowPrimaryKeyColumns = false, bool allowUniqueColumns = false)
```

Parameters

connectionName [Enum](#)

The name of the database connection to use. This must be an enumeration value representing a valid connection.

sourceData [IEnumerable<T>](#)

The collection of data to write to the database table. Each item in the collection represents a row to be inserted.

tableName [string](#)

The name of the target database table. If [null](#), the table name is inferred from the type **T**.

forceType [Type](#)

An optional type to enforce for the operation. If specified, the operation will treat the data as this type.

batchSize [int](#)

The number of rows to write in each batch. Defaults to 100. Larger batch sizes may improve performance but require more memory.

allowAutoIncrementColumns [bool](#)

A value indicating whether auto-increment columns in the target table are allowed to be explicitly written. Defaults to [false](#).

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns in the target table are allowed to be explicitly written. Defaults to [false](#).

allowUniqueColumns [bool](#)

A value indicating whether unique columns in the target table are allowed to be explicitly written. Defaults to [false](#).

Returns

[int](#)

The total number of rows successfully written to the database.

Type Parameters

T

The type of the objects in the `sourceData` collection.

Remarks

This method provides a high-performance way to insert large amounts of data into a database table. It supports optional configuration for handling auto-increment, primary key, and unique columns.

BulkTableWrite<T>(Enum, T, string, Type, int, bool, bool, bool)

Writes a collection of data to a database table in bulk, optimizing for high performance.

```
public static int BulkTableWrite<T>(Enum connectionName, T sourceData, string tableName = null, Type forceType = null, int batchSize = 100, bool allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool allowUniqueColumns = false)
```

Parameters

`connectionName` [Enum](#)

The name of the database connection to use. This must correspond to a valid connection configuration.

`sourceData` `T`

The data to be written to the table. This can be a collection or a single object, depending on the implementation.

`tableName` [string](#)

The name of the target database table. If [null](#), the table name is inferred from the type `T`.

`forceType` [Type](#)

An optional type to enforce when writing the data. If specified, the data will be treated as this type during the operation.

`batchSize` [int](#)

The number of rows to write in each batch. Defaults to 100. Larger batch sizes may improve performance but require more memory.

`allowAutoIncrementColumns` [bool](#)

A value indicating whether columns with auto-increment constraints are allowed to be written. Defaults to [false](#).

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns are allowed to be written. Defaults to [false](#).

allowUniqueColumns [bool](#)

A value indicating whether unique columns are allowed to be written. Defaults to [false](#).

Returns

[int](#)

The number of rows successfully written to the database.

Type Parameters

T

The type of the data objects to be written to the table.

Remarks

This method is designed for scenarios where large amounts of data need to be inserted into a database efficiently. It uses bulk operations to minimize database round-trips and improve performance. Ensure that the database schema matches the structure of the data being written to avoid runtime errors.

DoDatabaseWork(MySqlConnection, string, Dictionary<string, object>, bool, bool, MySqlConnectionTransaction)

Executes a database query using the provided connection and optional parameters.

```
public static void DoDatabaseWork(MySqlConnection establishedConnection, string query,
Dictionary<string, object> parameters = null, bool throwException = true, bool
useTransaction = false, MySqlConnectionTransaction sqlTransaction = null)
```

Parameters

establishedConnection MySqlConnection

An open and established `MySQL.Data.MySqlClient.MySqlConnection` to the database. The connection must be valid and open before calling this method.

query [string](#)

The SQL query to execute. This must be a valid SQL statement supported by the database.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. If null, no parameters are applied.

throwException [bool](#)

A boolean value indicating whether to throw an exception if an error occurs. If [true](#), exceptions are thrown; otherwise, errors are suppressed.

useTransaction [bool](#)

A boolean value indicating whether to execute the query within a transaction. If [true](#), a transaction is used; otherwise, the query is executed without a transaction.

sqlTransaction `MySQLTransaction`

An optional `MySQL.Data.MySqlClient.MySQLTransaction` to use for the query. If provided, this transaction is used instead of creating a new one. Ignored if **useTransaction** is [false](#).

Remarks

This method delegates the execution to [DoDatabaseWork\(Enum, string, Dictionary<string, object>, bool, bool, MySQLTransaction, bool\)](#). Ensure that the connection is properly managed and disposed of after use.

DoDatabaseWork(MySqlConnection, string, Func<MySQLCommand, object>, bool, bool, MySQLTransaction)

Executes a database operation using the provided connection, query, and callback function.

```
public static void DoDatabaseWork(MySqlConnection establishedConnection, string query,
Func<MySQLCommand, object> actionCallback, bool throwException = true, bool useTransaction =
false, MySQLTransaction sqlTransaction = null)
```

Parameters

establishedConnection MySqlConnection

An open and valid MySql.Data.MySqlClient.MySqlConnection to the database. The connection must be established before calling this method.

query [string](#)

The SQL query to execute. This query is passed to the callback function for processing.

actionCallback [Func](#) <MySqlCommand, [object](#)>

A callback function that processes the MySql.Data.MySqlClient.MySqlCommand created from the query. The function should return an object representing the result of the operation.

throwException [bool](#)

A value indicating whether to throw exceptions if an error occurs during the operation. If [true](#), exceptions will be propagated; otherwise, errors will be suppressed. The default value is [true](#).

useTransaction [bool](#)

A value indicating whether the operation should be executed within a transaction. If [true](#), a transaction will be used unless **sqlTransaction** is provided. The default value is [false](#).

sqlTransaction MySqlTransaction

An optional MySql.Data.MySqlClient.MySqlTransaction to use for the operation. If provided, this transaction will be used instead of creating a new one.

Remarks

This method delegates the database operation to a helper method and provides flexibility for executing queries with or without transactions. Ensure that the connection is open and valid before calling this method. If **useTransaction** is [true](#) and **sqlTransaction** is not provided, a new transaction will be created and committed automatically.

DoDatabaseWork(IRelmContext, string, Dictionary<string, object>, bool, bool)

Executes a database operation using the specified query and parameters.

```
public static void DoDatabaseWork(IRelmContext relmContext, string query, Dictionary<string, object> parameters = null, bool throwException = true, bool useTransaction = false)
```

Parameters

relmContext [IRelmContext](#)

The database context used to execute the operation. Cannot be [null](#).

query [string](#)

The SQL query to execute. Cannot be [null](#) or empty.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. If [null](#), no parameters will be passed.

throwException [bool](#)

A value indicating whether an exception should be thrown if the operation fails. The default value is [true](#).

useTransaction [bool](#)

A value indicating whether the operation should be executed within a transaction. The default value is [false](#).

Remarks

This method delegates the database operation to an internal helper. Ensure that the **relmContext** is properly configured and that the **query** is valid for the target database.

DoDatabaseWork(IRelmContext, string, Func<MySqlCommand, object>, bool, bool)

Executes a database operation using the specified query and callback function.

```
public static void DoDatabaseWork(IRelmContext relmContext, string query, Func<MySqlCommand, object> actionCallback, bool throwException = true, bool useTransaction = false)
```

Parameters

realmContext [IRelmContext](#)

The database context used to establish the connection. Cannot be [null](#).

query [string](#)

The SQL query to be executed. Cannot be [null](#) or empty.

actionCallback [Func](#) <MySQLCommand, [object](#)>

A callback function that processes the `MySQL.Data.MySqlClient.MySqlCommand` object and returns a result. The callback cannot be [null](#).

throwException [bool](#)

A value indicating whether exceptions should be thrown if an error occurs during the operation. The default value is [true](#).

useTransaction [bool](#)

A value indicating whether the operation should be executed within a database transaction. The default value is [false](#).

Remarks

This method delegates the database operation to a helper class. Ensure that the provided **realmContext** is properly configured and that the **query** is valid for the target database.

DoDatabaseWork(IRelmQuickContext, string, Dictionary<string, object>, bool, bool)

Executes a database operation using the specified query and parameters.

```
public static void DoDatabaseWork(IRelmQuickContext realmQuickContext, string query,
Dictionary<string, object> parameters = null, bool throwException = true, bool
useTransaction = false)
```

Parameters

realmQuickContext [IRelmQuickContext](#)

The database context used to execute the operation. This cannot be [null](#).

query [string](#)

The SQL query to execute. This cannot be [null](#) or empty.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. If [null](#), no parameters are applied.

throwException [bool](#)

A value indicating whether an exception should be thrown if the operation fails. The default is [true](#).

useTransaction [bool](#)

A value indicating whether the operation should be executed within a transaction. The default is [false](#).

Remarks

This method delegates the database operation to an internal helper. Ensure that the provided query and parameters are valid for the target database.

DoDatabaseWork(IRelmQuickContext, string, Func<MySqlCommand, object>, bool, bool)

Executes a database operation using the specified query and callback function.

```
public static void DoDatabaseWork(IRelmQuickContext relmQuickContext, string query,
    Func<MySqlCommand, object> actionCallback, bool throwException = true, bool useTransaction
    = false)
```

Parameters

relmQuickContext [IRelmQuickContext](#)

The database context used to establish the connection and manage the operation.

query [string](#)

The SQL query to execute. Must be a valid SQL statement.

actionCallback [Func](#) <MySQLCommand, [object](#)>

A callback function that processes the `MySQL.Data.MySqlClient.MySqlCommand` object and returns a result.

throwException [bool](#)

A value indicating whether to throw an exception if an error occurs during the operation. [true](#) to throw exceptions; otherwise, [false](#).

useTransaction [bool](#)

A value indicating whether the operation should be executed within a database transaction. [true](#) to use a transaction; otherwise, [false](#).

Remarks

This method delegates the database operation to [DoDatabaseWork\(Enum, string, Dictionary<string, object>, bool, bool, MySqlConnection, bool\)](#). Ensure that the `realmQuickContext` is properly configured before calling this method.

DoDatabaseWork(Enum, string, Dictionary<string, object>, bool, bool, MySqlConnection, bool)

Executes a database operation using the specified connection, query, and parameters.

```
public static void DoDatabaseWork(Enum connectionName, string query, Dictionary<string, object> parameters = null, bool throwException = true, bool useTransaction = false, MySqlConnection sqlTransaction = null, bool allowUserVariables = false)
```

Parameters

connectionName [Enum](#)

The name of the database connection to use. This must be a valid value from the specified enumeration.

query [string](#)

The SQL query to execute. The query can include parameter placeholders.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. If null, no parameters will be passed to the query.

throwException [bool](#)

A boolean value indicating whether to throw an exception if an error occurs. If [true](#), exceptions will be thrown; otherwise, errors will be suppressed.

useTransaction [bool](#)

A boolean value indicating whether to execute the query within a transaction. If [true](#), a transaction will be used; otherwise, the query will execute without a transaction.

sqlTransaction [MySqlTransaction](#)

An optional [MySql.Data.MySqlClient.MySqlTransaction](#) object to use for the operation. If provided, the operation will use this transaction; otherwise, a new transaction may be created if **useTransaction** is [true](#).

allowUserVariables [bool](#)

A boolean value indicating whether user-defined variables are allowed in the query. If [true](#), user variables are permitted; otherwise, they are not.

Remarks

This method delegates the database operation to the [DatabaseWorkHelper.DoDatabaseWork](#) method. Ensure that the **connectionName** corresponds to a valid database connection and that the **query** is properly formatted for the target database.

DoDatabaseWork(Enum, string, Func<MySqlCommand, object>, bool, bool, MySqlTransaction, bool)

Executes a database operation using the specified query and callback function.

```
public static void DoDatabaseWork(Enum connectionName, string query, Func<MySqlCommand, object> actionCallback, bool throwException = true, bool useTransaction = false, MySqlTransaction sqlTransaction = null, bool allowUserVariables = false)
```

Parameters

connectionName [Enum](#)

The name of the database connection to use. This must be a valid connection identifier.

query [string](#)

The SQL query to execute. Cannot be null or empty.

actionCallback [Func](#) <MySQLCommand, [object](#)>

A callback function that processes the `MySQL.Data.MySqlClient.MySqlCommand` object and returns a result. Cannot be null.

throwException [bool](#)

Specifies whether to throw an exception if an error occurs. If [true](#), exceptions will be thrown; otherwise, errors will be suppressed.

useTransaction [bool](#)

Specifies whether the operation should be executed within a transaction. If [true](#), a transaction will be used.

sqlTransaction `MySQLTransaction`

An optional `MySQL.Data.MySqlClient.MySqlTransaction` object to use for the operation. If provided, this transaction will be used instead of creating a new one.

allowUserVariables [bool](#)

Specifies whether user-defined variables are allowed in the SQL query. If [true](#), user variables are permitted.

Remarks

This method delegates the database operation to an internal helper and provides flexibility for executing queries with or without transactions. Ensure that the **connectionName** corresponds to a valid database connection and that the **query** is properly formatted.

DoDatabaseWork<T>(MySQLConnection, string, Dictionary<string, object>, bool, bool, MySQLTransaction)

Executes a database query and returns the result as the specified type.

```
public static T DoDatabaseWork<T>( MySqlConnection establishedConnection, string query,
Dictionary<string, object> parameters = null, bool throwException = true, bool
useTransaction = false, MySqlTransaction sqlTransaction = null)
```

Parameters

establishedConnection MySqlConnection

An open and valid MySql.Data.MySqlClient.MySqlConnection to the database.

query [string](#)

The SQL query to execute.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. If null, no parameters are added.

throwException [bool](#)

A boolean value indicating whether to throw an exception if an error occurs. If [true](#), exceptions are thrown; otherwise, errors are suppressed.

useTransaction [bool](#)

A boolean value indicating whether to execute the query within a transaction. If [true](#), a transaction is used.

sqlTransaction MySqlTransaction

An optional MySql.Data.MySqlClient.MySqlTransaction to use for the query. If null, a new transaction is created if **useTransaction** is [true](#).

Returns

T

The result of the query, cast to the specified type **T**.

Type Parameters

T

The type of the result expected from the query.

Remarks

This method is a wrapper for executing database queries with optional parameterization, transaction support, and error handling. Ensure the connection is open before calling this method.

DoDatabaseWork<T>(MySqlConnection, string, Func< MySqlCommand, object>, bool, bool, MySqlTransaction)

Executes a database operation using the provided query and callback function.

```
public static T DoDatabaseWork<T>(MySqlConnection establishedConnection, string query,
Func<MySqlCommand, object> actionCallback, bool throwException = true, bool useTransaction =
false, MySqlTransaction sqlTransaction = null)
```

Parameters

establishedConnection MySqlConnection

An open and valid `MySql.Data.MySqlClient.MySqlConnection` to the database. The connection must already be established.

query [string](#)

The SQL query to be executed. This query is passed to the callback function for execution.

actionCallback [Func](#) <MySqlCommand, [object](#)>

A callback function that defines the operation to perform using the `MySql.Data.MySqlClient.MySqlCommand` created from the query.

throwException [bool](#)

A value indicating whether exceptions should be thrown if an error occurs during the operation. If [true](#), exceptions are propagated to the caller; otherwise, they are suppressed.

useTransaction [bool](#)

A value indicating whether the operation should be executed within a transaction. If [true](#), a transaction is used unless `sqlTransaction` is provided.

sqlTransaction MySqlTransaction

An optional `MySQL.Data.MySqlClient.MySqlTransaction` to use for the operation. If provided, this transaction is used regardless of the value of `useTransaction`.

Returns

`T`

The result of type `T` as returned by the `actionCallback`.

Type Parameters

`T`

The type of the result returned by the callback function.

Remarks

This method provides a flexible way to execute database operations by allowing the caller to define the specific action to perform via the `actionCallback`. If `useTransaction` is `true` and no `sqlTransaction` is provided, a new transaction is created for the operation.

DoDatabaseWork<T>(IRelmContext, string, Dictionary<string, object>, bool, bool)

Executes a database operation using the specified query and parameters, and optionally within a transaction.

```
public static T DoDatabaseWork<T>(IRelmContext relmContext, string query, Dictionary<string, object> parameters = null, bool throwException = true, bool useTransaction = false)
```

Parameters

`relmContext` [IRelmContext](#)

The database context used to execute the operation. Cannot be [null](#).

`query` [string](#)

The SQL query to execute. Cannot be [null](#) or empty.

`parameters` [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. Can be [null](#) if no parameters are required.

throwException [bool](#)

A value indicating whether an exception should be thrown if the operation fails. If [true](#), exceptions will be propagated; otherwise, the method may handle errors internally.

useTransaction [bool](#)

A value indicating whether the operation should be executed within a transaction. If [true](#), the operation will be wrapped in a transaction.

Returns

T

The result of the database operation, of type **T**.

Type Parameters

T

The type of the result returned by the database operation.

Remarks

This method provides a high-level abstraction for executing database operations. The behavior of the operation, including error handling and transaction usage, can be customized using the **throwException** and **useTransaction** parameters.

DoDatabaseWork<T>(IRelmContext, string, Func<MySQLCommand, object>, bool, bool)

Executes a database operation using the specified query and callback function.

```
public static T DoDatabaseWork<T>(IRelmContext relmContext, string query, Func<MySQLCommand, object> actionCallback, bool throwException = true, bool useTransaction = false)
```

Parameters

realmContext [IRelmContext](#)

The database context used to establish the connection and manage the operation. Cannot be [null](#).

query [string](#)

The SQL query to execute. Cannot be [null](#) or empty.

actionCallback [Func](#) <MySQLCommand, [object](#)>

A callback function that defines the operation to perform using the `MySQL.Data.MySqlClient.MySqlCommand` object. Cannot be [null](#).

throwException [bool](#)

A value indicating whether exceptions encountered during the operation should be thrown. If [true](#), exceptions will be propagated to the caller; otherwise, they will be suppressed.

useTransaction [bool](#)

A value indicating whether the operation should be executed within a database transaction. If [true](#), the operation will be wrapped in a transaction.

Returns

T

The result of the database operation, as defined by the **T** type.

Type Parameters

T

The type of the result returned by the database operation.

Remarks

This method provides a flexible way to execute database operations by allowing the caller to specify a query and a callback function that defines the operation to perform. The operation can optionally be executed within a transaction, and exceptions can be suppressed based on the **throwException** parameter.

DoDatabaseWork<T>(IRelmQuickContext, string, Dictionary<string, object>, bool, bool)

Executes a database operation using the specified query and parameters, and optionally within a transaction.

```
public static T DoDatabaseWork<T>(IRelmQuickContext relmQuickContext, string query, Dictionary<string, object> parameters = null, bool throwException = true, bool useTransaction = false)
```

Parameters

relmQuickContext [IRelmQuickContext](#)

The database context used to execute the operation. Cannot be [null](#).

query [string](#)

The SQL query to execute. Cannot be [null](#) or empty.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameters to include in the query. Keys represent parameter names, and values represent their corresponding values. Defaults to [null](#).

throwException [bool](#)

A value indicating whether an exception should be thrown if the operation fails. Defaults to [true](#).

useTransaction [bool](#)

A value indicating whether the operation should be executed within a transaction. Defaults to [false](#).

Returns

T

The result of the database operation, cast to the specified type **T**.

Type Parameters

T

The type of the result expected from the database operation.

DoDatabaseWork<T>(IRelmQuickContext, string, Func<MySQLCommand, object>, bool, bool)

Executes a database operation using the specified query and callback function.

```
public static T DoDatabaseWork<T>(IRelmQuickContext relmQuickContext, string query,
    Func<MySQLCommand, object> actionCallback, bool throwException = true, bool useTransaction
    = false)
```

Parameters

relmQuickContext [IRelmQuickContext](#)

The database context used to establish the connection and manage the operation. Cannot be [null](#).

query [string](#)

The SQL query to be executed. Cannot be [null](#) or empty.

actionCallback [Func](#)<MySQLCommand, [object](#)>

A callback function that defines the operation to perform using the MySQL.Data.MySqlClient.MySqlCommand object. Cannot be [null](#).

throwException [bool](#)

A value indicating whether exceptions should be thrown if an error occurs during the operation. If [true](#), exceptions will be propagated; otherwise, errors will be suppressed.

useTransaction [bool](#)

A value indicating whether the operation should be executed within a database transaction. If [true](#), the operation will be wrapped in a transaction.

Returns

T

The result of the operation, as returned by the **actionCallback**.

Type Parameters

T

The type of the result returned by the callback function.

Remarks

This method provides a flexible way to execute database operations by allowing the caller to specify a query and a custom callback function to process the database command. The caller can optionally enable transaction support and control whether exceptions are thrown or suppressed.

DoDatabaseWork<T>(Enum, string, Dictionary<string, object>, bool, bool, MySqlConnection, bool)

Executes a database operation and returns the result of the specified type.

```
public static T DoDatabaseWork<T>(Enum connectionName, string query, Dictionary<string, object> parameters = null, bool throwException = true, bool useTransaction = false, MySqlConnection sqlTransaction = null, bool allowUserVariables = false)
```

Parameters

connectionName [Enum](#)

The name of the database connection to use. Must be a valid enumeration value representing a configured connection.

query [string](#)

The SQL query to execute. Cannot be null or empty.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameters to include in the query. Keys represent parameter names, and values represent their corresponding values. Can be null if no parameters are needed.

throwException [bool](#)

Indicates whether an exception should be thrown if an error occurs during the operation. If [true](#), exceptions will be propagated; otherwise, errors will be suppressed.

useTransaction [bool](#)

Specifies whether the operation should be executed within a transaction. If [true](#), a transaction will be used unless **sqlTransaction** is provided.

`sqlTransaction` [MySQLTransaction](#)

An optional existing `MySQL.Data.MySqlClient.MySqlTransaction` to use for the operation. If provided, `useTransaction` is ignored.

`allowUserVariables` [bool](#)

Indicates whether user-defined variables are allowed in the query. If [true](#), user variables are permitted; otherwise, they are disallowed.

Returns

`T`

The result of the database operation, cast to the specified type `T`.

Type Parameters

`T`

The type of the result returned by the database operation.

Remarks

This method provides a flexible way to execute database operations, supporting parameterized queries, transactions, and user-defined variables. Ensure that the specified type `T` matches the expected result of the query.

DoDatabaseWork<T>(Enum, string, Func<MySqlCommand, object>, bool, bool, MySQLTransaction, bool)

Executes a database operation using the specified query and callback function.

```
public static T DoDatabaseWork<T>(Enum connectionName, string query, Func<MySqlCommand, object> actionCallback, bool throwException = true, bool useTransaction = false, MySQLTransaction sqlTransaction = null, bool allowUserVariables = false)
```

Parameters

`connectionName` [Enum](#)

The name of the database connection to use. Must be a valid enumeration value representing a configured connection.

query [string](#)

The SQL query to execute. Cannot be null or empty.

actionCallback [Func](#) < MySqlCommand, [object](#) >

A callback function that processes the `MySQL.Data.MySqlClient.MySqlCommand` object and returns a result of type `T`.

throwException [bool](#)

Specifies whether to throw an exception if an error occurs. If [true](#), exceptions will be thrown; otherwise, errors will be suppressed.

useTransaction [bool](#)

Specifies whether the operation should be executed within a database transaction. If [true](#), a transaction will be used.

sqlTransaction `MySqlTransaction`

An optional `MySQL.Data.MySqlClient.MySqlTransaction` object to use for the operation. If provided, the operation will be executed within this transaction.

allowUserVariables [bool](#)

Specifies whether user-defined variables are allowed in the SQL query. If [true](#), user variables are permitted.

Returns

`T`

The result of the operation, as returned by the **actionCallback** function.

Type Parameters

`T`

The type of the result returned by the callback function.

Remarks

This method provides a flexible way to execute database operations by allowing the caller to specify a query and a callback function to process the database command. The operation can optionally be executed within a transaction, and user-defined variables in the query can be enabled if required.

GetBulkTableWriter<T>(MySqlConnection, string, bool, bool, MySqlConnection, bool, bool, bool)

Creates and returns a [BulkTableWriter<T>](#) instance for performing bulk insert operations on a MySQL database table.

```
public static BulkTableWriter<T> GetBulkTableWriter<T>(MySqlConnection
establishedConnection, string insertQuery = null, bool throwException = true, bool
useTransaction = true, MySqlConnection sqlTransaction = null, bool
allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool
allowUniqueColumns = false)
```

Parameters

establishedConnection MySqlConnection

An open and valid `MySQL.Data.MySqlClient.MySqlConnection` to the target database. The connection must remain open for the duration of the bulk operation.

insertQuery [string](#) 

An optional custom SQL insert query to use for the bulk operation. If not provided, a default query will be generated based on the type `T` and the target table schema.

throwException [bool](#) 

A value indicating whether exceptions should be thrown if an error occurs during the bulk operation. If [true](#) , exceptions will be thrown; otherwise, errors will be suppressed.

useTransaction [bool](#) 

A value indicating whether the bulk operation should be performed within a transaction. If [true](#) , a transaction will be used unless `sqlTransaction` is provided.

sqlTransaction MySqlConnection

An optional `MySQL.Data.MySqlClient.MySqlTransaction` to use for the bulk operation. If provided, the operation will use this transaction instead of creating a new one. This parameter is ignored if

`useTransaction` is [false](#).

`allowAutoIncrementColumns` [bool](#)

A value indicating whether auto-increment columns in the target table are allowed to be explicitly written to. If [false](#), auto-increment columns will be excluded from the operation.

`allowPrimaryKeyColumns` [bool](#)

A value indicating whether primary key columns in the target table are allowed to be explicitly written to. If [false](#), primary key columns will be excluded from the operation.

`allowUniqueColumns` [bool](#)

A value indicating whether unique columns in the target table are allowed to be explicitly written to. If [false](#), unique columns will be excluded from the operation.

Returns

[BulkTableWriter](#)<T>

A [BulkTableWriter](#)<T> instance configured for the specified bulk operation.

Type Parameters

T

The type of the objects to be written to the database. Each object represents a row in the target table.

Remarks

This method provides a flexible way to perform high-performance bulk insert operations on a MySQL database table. The behavior of the operation can be customized using the provided parameters.

GetBulkTableWriter<T>(IRelmContext, string, bool, bool, bool, bool, bool)

Creates and returns a [BulkTableWriter](#)<T> instance for performing bulk insert operations on a database table.

```
public static BulkTableWriter<T> GetBulkTableWriter<T>(IRelmContext relmContext, string
insertQuery = null, bool useTransaction = false, bool throwException = true, bool
```



```
allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool  
allowUniqueColumns = false)
```

Parameters

realmContext [IRelmContext](#)

The database context used to manage the connection and operations. This parameter cannot be [null](#).

insertQuery [string](#)

An optional SQL insert query to use for the bulk operation. If [null](#), a default query is generated based on the type **T**.

useTransaction [bool](#)

Indicates whether the bulk operation should be performed within a transaction. If [true](#), the operation is transactional; otherwise, it is not.

throwException [bool](#)

Determines whether exceptions should be thrown during the operation. If [true](#), exceptions are thrown; otherwise, errors are suppressed.

allowAutoIncrementColumns [bool](#)

Specifies whether auto-increment columns are allowed in the bulk operation. If [true](#), auto-increment columns are included; otherwise, they are excluded.

allowPrimaryKeyColumns [bool](#)

Specifies whether primary key columns are allowed in the bulk operation. If [true](#), primary key columns are included; otherwise, they are excluded.

allowUniqueColumns [bool](#)

Specifies whether unique columns are allowed in the bulk operation. If [true](#), unique columns are included; otherwise, they are excluded.

Returns

[BulkTableWriter](#)<T>

A [BulkTableWriter](#)<T> instance configured for the specified bulk operation.

Type Parameters

T

The type representing the table's data model. Each instance of **T** corresponds to a row in the table.

Remarks

This method provides a convenient way to configure and execute bulk insert operations on a database table. The behavior of the operation can be customized using the optional parameters.

GetBulkTableWriter<T>(IRelmQuickContext, string, bool, bool, bool, bool, bool)

Creates and returns a [BulkTableWriter<T>](#) instance for performing bulk insert operations on a database table.

```
public static BulkTableWriter<T> GetBulkTableWriter<T>(IRelmQuickContext relmQuickContext,
string insertQuery = null, bool useTransaction = false, bool throwException = true, bool
allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool
allowUniqueColumns = false)
```

Parameters

relmQuickContext [IRelmQuickContext](#)

The database context used to manage the connection and operations. This parameter cannot be [null](#).

insertQuery [string](#)

An optional SQL insert query to use for the bulk operation. If [null](#), a default query is generated based on the type **T**.

useTransaction [bool](#)

A value indicating whether the bulk operation should be performed within a transaction. The default is [false](#).

throwException [bool](#)

A value indicating whether exceptions should be thrown if an error occurs during the operation. The default is [true](#).

allowAutoIncrementColumns [bool](#)

A value indicating whether auto-increment columns are allowed in the bulk operation. The default is [false](#).

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns are allowed in the bulk operation. The default is [false](#).

allowUniqueColumns [bool](#)

A value indicating whether unique columns are allowed in the bulk operation. The default is [false](#).

Returns

[BulkTableWriter](#)<T>

A [BulkTableWriter](#)<T> instance configured for the specified bulk operation.

Type Parameters

T

The type of the objects to be written to the database table.

Remarks

This method is a wrapper around [GetBulkTableWriter<T>\(Enum, string, bool, bool, bool, bool, bool, bool, bool\)](#) and provides additional configuration options for bulk insert operations. Use this method to efficiently insert large amounts of data into a database table.

GetBulkTableWriter<T>(Enum, string, bool, bool, bool, bool, bool, bool)

Creates and returns a [BulkTableWriter](#)<T> instance for performing bulk insert operations on a database table.

```
public static BulkTableWriter<T> GetBulkTableWriter<T>(Enum connectionName, string
insertQuery = null, bool useTransaction = false, bool throwException = true, bool
```

```
allowUserVariables = false, bool allowAutoIncrementColumns = false, bool  
allowPrimaryKeyColumns = false, bool allowUniqueColumns = false)
```

Parameters

connectionName [Enum](#)

The name of the database connection, represented as an [Enum](#). This specifies which database connection to use.

insertQuery [string](#)

An optional SQL insert query to use for the bulk operation. If not provided, a default query is generated based on the type `T`.

useTransaction [bool](#)

A value indicating whether the bulk operation should be performed within a database transaction. If [true](#), the operation is transactional; otherwise, it is not.

throwException [bool](#)

A value indicating whether exceptions should be thrown if an error occurs during the operation. If [true](#), exceptions are thrown; otherwise, errors are suppressed.

allowUserVariables [bool](#)

A value indicating whether user-defined variables are allowed in the SQL query. If [true](#), user variables are permitted; otherwise, they are not.

allowAutoIncrementColumns [bool](#)

A value indicating whether auto-increment columns are allowed to be included in the bulk operation. If [true](#), auto-increment columns are included; otherwise, they are excluded.

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns are allowed to be included in the bulk operation. If [true](#), primary key columns are included; otherwise, they are excluded.

allowUniqueColumns [bool](#)

A value indicating whether unique columns are allowed to be included in the bulk operation. If [true](#), unique columns are included; otherwise, they are excluded.

Returns

[BulkTableWriter](#)<T>

A [BulkTableWriter](#)<T> instance configured for the specified bulk operation.

Type Parameters

T

The type of the objects to be written to the database. Each object represents a row in the table.

Remarks

This method is designed for scenarios where large amounts of data need to be inserted into a database table efficiently. The behavior of the bulk operation can be customized using the provided parameters.

GetColumnName<T>(Expression<Func<T, object>>)

Retrieves the name of the database column associated with the specified property or field.

```
public static string GetColumnName<T>(Expression<Func<T, object>> predicate) where T : IRealmModel
```

Parameters

predicate [Expression](#)<[Func](#)<T, [object](#)>>

An expression that specifies the property or field for which to retrieve the column name. The expression should be in the form of a lambda, such as `x => x.PropertyName`.

Returns

[string](#)

The name of the database column corresponding to the specified property or field.

Type Parameters

T

The type of the model that implements [IRealmModel](#).

GetConnectionStringBuilderFromConnectionString(string)

Creates and returns a `MySQL.Data.MySqlClient.MySqlConnectionStringBuilder` initialized with the specified connection string.

```
public static MySqlConnectionStringBuilder GetConnectionStringBuilderFromConnectionString(string connectionString)
```

Parameters

`connectionString` [string](#) 

The connection string used to configure the `MySQL.Data.MySqlClient.MySqlConnectionStringBuilder`.

Returns

`MySqlConnectionStringBuilder`

A `MySQL.Data.MySqlClient.MySqlConnectionStringBuilder` instance populated with the settings from the provided connection string.

GetConnectionStringBuilderFromConnectionType(Enum)

Retrieves a `MySQL.Data.MySqlClient.MySqlConnectionStringBuilder` instance configured for the specified connection type.

```
public static MySqlConnectionStringBuilder GetConnectionStringBuilderFromConnectionType(Enum connectionName)
```

Parameters

`connectionName` [Enum](#) 

An enumeration value representing the type of connection to configure. This parameter determines the settings applied to the returned connection string builder.

Returns

`MySqlConnectionStringBuilder`

A `MySQL.Data.MySqlClient.MySqlConnectionStringBuilder` instance configured based on the specified `connectionName`.

Remarks

The method delegates the creation of the connection string builder to the [GetConnectionBuilderFromType\(Enum\)](#) method. Ensure that the provided `connectionName` corresponds to a supported connection type.

GetConnectionBuilderFromName(string)

Retrieves a `MySQL.Data.MySqlClient.MySqlConnectionStringBuilder` instance based on the specified connection name.

```
public static MySqlConnectionStringBuilder GetConnectionBuilderFromName(string  
connectionName)
```

Parameters

`connectionName` [string](#)

The name of the connection to retrieve. This value must correspond to a valid connection name in the application configuration.

Returns

`MySqlConnectionStringBuilder`

A `MySQL.Data.MySqlClient.MySqlConnectionStringBuilder` initialized with the connection string associated with the specified connection name.

GetConnectionFromConnectionString(string, bool, bool, int)

Creates and returns a new `MySQL.Data.MySqlClient.MySqlConnection` instance based on the specified connection string and optional configuration parameters.

```
public static MySqlConnection GetConnectionFromConnectionString(string connectionString,  
bool allowUserVariables = false, bool convertZeroDateTime = false, int  
lockWaitTimeoutSeconds = 0)
```

Parameters

connectionString [string](#)

The connection string used to establish the database connection. This parameter cannot be [null](#) or empty.

allowUserVariables [bool](#)

A value indicating whether user-defined variables are allowed in SQL statements. The default is [false](#).

convertZeroDateTime [bool](#)

A value indicating whether zero date values (e.g., '0000-00-00') in the database should be converted to [MinValue](#). The default is [false](#).

lockWaitTimeoutSeconds [int](#)

The lock wait timeout duration, in seconds, to apply to the connection. A value of 0 indicates that the default timeout will be used.

Returns

MySQLConnection

A `MySQL.Data.MySqlClient.MySqlConnection` instance configured with the specified connection string and options.

Remarks

This method provides a convenient way to create a `MySQL.Data.MySqlClient.MySqlConnection` with additional configuration options such as enabling user-defined variables, converting zero date values, or setting a custom lock wait timeout. Ensure that the connection string is valid and properly formatted for MySQL.

GetConnectionFromName(string, bool, bool, int)

Retrieves a `MySQL.Data.MySqlClient.MySqlConnection` instance based on the specified connection name.

```
public static MySqlConnection GetConnectionFromName(string connectionName, bool
allowUserVariables = false, bool convertZeroDateTime = false, int lockWaitTimeoutSeconds
= 0)
```


Parameters

connectionName [string](#)

The name of the connection to retrieve. This must correspond to a valid connection string defined in the application's configuration.

allowUserVariables [bool](#)

A value indicating whether user-defined variables are allowed in SQL queries. Defaults to [false](#).

convertZeroDateTime [bool](#)

A value indicating whether zero date values (e.g., '0000-00-00') in the database should be converted to [MinValue](#). Defaults to [false](#).

lockWaitTimeoutSeconds [int](#)

The lock wait timeout, in seconds, to apply to the connection. A value of 0 indicates that the default timeout will be used.

Returns

MySqlConnection

A `MySql.Data.MySqlClient.MySqlConnection` instance configured with the specified options.

GetConnectionFromType(Enum, bool, bool, int)

Creates and returns a `MySql.Data.MySqlClient.MySqlConnection` based on the specified connection type and optional configuration settings.

```
public static MySqlConnection GetConnectionFromType(Enum connectionName, bool
allowUserVariables = false, bool convertZeroDateTime = false, int lockWaitTimeoutSeconds
= 0)
```

Parameters

connectionName [Enum](#)

An [Enum](#) representing the type of connection to establish. The specific values and their meanings depend on the application's connection configuration.

allowUserVariables [bool](#)

A boolean value indicating whether user-defined variables are allowed in SQL statements. [true](#) to allow user variables; otherwise, [false](#). Defaults to [false](#).

convertZeroDateTime [bool](#)

A boolean value indicating whether zero date values (e.g., '0000-00-00') should be converted to `DateTime.MinValue`. [true](#) to enable conversion; otherwise, [false](#). Defaults to [false](#).

lockWaitTimeoutSeconds [int](#)

An integer specifying the lock wait timeout duration, in seconds, for the connection. A value of 0 indicates that the default timeout will be used. Defaults to 0.

Returns

MySqlConnection

A `MySql.Data.MySqlClient.MySqlConnection` object configured based on the specified parameters.

Remarks

This method simplifies the creation of MySQL connections. Ensure that the `connectionName` corresponds to a valid configuration in the application's connection settings.

GetDalTable(Type)

Retrieves the name of the database table associated with the specified Data Access Layer (DAL) object type.

```
public static string GetDalTable(Type DalObjectType)
```

Parameters

DalObjectType [Type](#)

The type of the DAL object for which the table name is being retrieved. This parameter cannot be [null](#).

Returns

[string](#)

The name of the database table associated with the specified DAL object type.

GetDalTable<T>()

Retrieves the name of the database table associated with the specified data model type.

```
public static string GetDalTable<T>() where T : IRealmModel, new()
```

Returns

[string](#)

A [string](#) representing the name of the database table associated with the specified data model type.

Type Parameters

T

The type of the data model. Must implement [IRelmModel](#) and have a parameterless constructor.

Remarks

This method is typically used to determine the table name for a given data model type in the context of database operations.

GetDataList<T>(MySQLConnection, string, Dictionary<string, object>, bool, MySQLTransaction)

Executes the specified SQL query and retrieves a list of objects of type **T**.

```
public static IEnumerable<T> GetDataList<T>(MySQLConnection establishedConnection, string query, Dictionary<string, object> parameters = null, bool throwException = true, MySQLTransaction sqlTransaction = null)
```

Parameters

establishedConnection MySQLConnection

An open and valid `MySQL.Data.MySqlClient.MySqlConnection` to use for the query.

query [string](#)

The SQL query to execute. Must be a valid SQL statement.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to include in the query. Can be [null](#) if no parameters are needed.

throwException [bool](#)

A value indicating whether to throw an exception if an error occurs during query execution. If [true](#), exceptions will be thrown; otherwise, errors will be suppressed.

sqlTransaction `MySqlTransaction`

An optional `MySQL.Data.MySqlClient.MySqlTransaction` to associate with the query. Can be [null](#) if no transaction is required.

Returns

[IEnumerable](#) <`T`>

An [IEnumerable<T>](#) containing the results of the query mapped to objects of type `T`. Returns an empty collection if no results are found.

Type Parameters

`T`

The type of objects to map the query results to.

`GetDataList<T>(IRelmContext, string, Dictionary<string, object>, bool)`

Executes a query against the specified Realm context and retrieves a collection of data items.

```
public static IEnumerable<T> GetDataList<T>(IRelmContext relmContext, string query,
Dictionary<string, object> parameters = null, bool throwException = true)
```

Parameters

realmContext [IRelmContext](#)

The Realm context used to execute the query. Cannot be [null](#).

query [string](#)

The query string to execute. Cannot be [null](#) or empty.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameters to include in the query. Can be [null](#) if no parameters are needed.

throwException [bool](#)

A value indicating whether an exception should be thrown if the query fails. If [true](#), an exception is thrown on failure; otherwise, the method returns an empty collection.

Returns

[IEnumerable](#) <[T](#)>

An [IEnumerable<T>](#) containing the data items retrieved by the query. Returns an empty collection if no items are found or if **throwException** is [false](#) and the query fails.

Type Parameters

T

The type of the data items to retrieve.

GetDataList<T>(IRelmQuickContext, string, Dictionary<string, object>, bool)

Executes a query against the specified context and returns a collection of results of the specified type.

```
public static IEnumerable<T> GetDataList<T>(IRelmQuickContext realmContext, string query, Dictionary<string, object> parameters = null, bool throwException = true)
```

Parameters

realmContext [IRelmQuickContext](#)

The context used to execute the query. This parameter cannot be [null](#).

query [string](#)

The query string to execute. This parameter cannot be [null](#) or empty.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameters to be used in the query. Keys represent parameter names, and values represent their corresponding values. Can be [null](#) if no parameters are needed.

throwException [bool](#)

A value indicating whether an exception should be thrown if an error occurs during query execution. If [true](#), an exception will be thrown on error; otherwise, the method will return an empty collection.

Returns

[IEnumerable](#) <[T](#)>

A collection of objects of type [T](#) representing the results of the query. Returns an empty collection if no results are found or if **throwException** is [false](#) and an error occurs.

Type Parameters

T

The type of objects to be returned in the result set.

GetDataList<T>(Enum, string, Dictionary<string, object>, bool, bool)

Executes the specified query and retrieves a collection of data mapped to the specified type.

```
public static IEnumerable<T> GetDataList<T>(Enum connectionName, string query,
Dictionary<string, object> parameters = null, bool throwException = true, bool
allowUserVariables = false)
```

Parameters

connectionName [Enum](#)

The name of the connection to use for executing the query.

query [string](#)

The SQL query to execute.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameters to include in the query. Keys represent parameter names, and values represent their corresponding values.

throwException [bool](#)

A value indicating whether to throw an exception if an error occurs. If [false](#), errors will be suppressed.

allowUserVariables [bool](#)

A value indicating whether user-defined variables are allowed in the query.

Returns

[IEnumerable](#) <[T](#)>

An [IEnumerable<T>](#) containing the results of the query mapped to the specified type. Returns an empty collection if no results are found.

Type Parameters

T

The type to which the query results will be mapped.

Remarks

This method uses the specified connection and query to retrieve data from the database. Ensure that the type **T** has a structure compatible with the query results.

GetDataObject<T>(MySQLConnection, string, Dictionary<string, object>, bool, MySQLTransaction)

Retrieves a single data object of the specified type from the database based on the provided query and parameters.

```
public static T GetDataObject<T>(MySQLConnection establishedConnection, string query,
Dictionary<string, object> parameters = null, bool throwException = true, MySQLTransaction
sqlTransaction = null) where T : IRelmModel, new()
```

Parameters

establishedConnection MySqlConnection

An open MySql.Data.MySqlClient.MySqlConnection to the database. The connection must be valid and already established.

query [string](#)

The SQL query to execute. The query should be structured to return a single row of data.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. Can be [null](#) if no parameters are required.

throwException [bool](#)

A boolean value indicating whether an exception should be thrown if the query does not return a result. If [true](#), an exception is thrown when no data is found; otherwise, [default](#) is returned.

sqlTransaction MySQLTransaction

An optional MySql.Data.MySqlClient.MySQLTransaction to associate with the query. Can be [null](#) if no transaction is needed.

Returns

T

An instance of type **T** populated with the data retrieved from the database. Returns [default](#) if no data is found and **throwException** is [false](#).

Type Parameters

T

The type of the data object to retrieve. Must implement [IRelmModel](#) and have a parameterless constructor.

GetDataObject<T>(IRelmContext, string, Dictionary<string, object>, bool)

Retrieves a single data object of the specified type based on the provided query and parameters.

```
public static T GetDataObject<T>(IRelmContext relmContext, string query, Dictionary<string, object> parameters = null, bool throwException = true) where T : IRelmModel, new()
```

Parameters

relmContext [IRelmContext](#)

The context used to execute the query. This provides the connection and configuration for the data source.

query [string](#)

The query string used to retrieve the data object. The query must be valid for the underlying data source.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameters to be used in the query. Keys represent parameter names, and values represent their corresponding values.

throwException [bool](#)

A boolean value indicating whether an exception should be thrown if the query does not return a result. If [true](#), an exception is thrown when no data is found; otherwise, [null](#) is returned.

Returns

T

An instance of the specified type **T** populated with the data retrieved by the query. Returns [null](#) if no data is found and **throwException** is [false](#).

Type Parameters

T

The type of the data object to retrieve. Must implement [IRelmModel](#) and have a parameterless constructor.

Remarks

This method provides a convenient way to retrieve a single data object. Ensure that the query and parameters are properly constructed to avoid unexpected results.

GetDataObject<T>(IRelmQuickContext, string, Dictionary<string, object>, bool)

Retrieves a single data object of the specified type based on the provided query and parameters.

```
public static T GetDataObject<T>(IRelmQuickContext relmQuickContext, string query,
Dictionary<string, object> parameters = null, bool throwException = true) where T :
IRelmModel, new()
```

Parameters

relmQuickContext [IRelmQuickContext](#)

The context used to execute the query. This provides the necessary connection and configuration for data retrieval.

query [string](#)

The query string used to retrieve the data object. This should be a valid query supported by the context.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameters to be used in the query. Keys represent parameter names, and values represent their corresponding values.

throwException [bool](#)

A boolean value indicating whether an exception should be thrown if the query does not return a result. If [true](#), an exception is thrown when no result is found; otherwise, [null](#) is returned.

Returns

T

An instance of the specified type **T** representing the retrieved data object. Returns [null](#) if no result is found and **throwException** is [false](#).

Type Parameters

T

The type of the data object to retrieve. Must implement [IRelmModel](#) and have a parameterless constructor.

Remarks

This method provides a convenient way to retrieve a single data object. Ensure that the query and parameters are properly constructed to avoid unexpected results.

GetDataObject<T>(Enum, string, Dictionary<string, object>, bool, bool)

Retrieves a single data object of the specified type based on the provided query and parameters.

```
public static T GetDataObject<T>(Enum connectionName, string query, Dictionary<string, object> parameters = null, bool throwException = true, bool allowUserVariables = false)
where T : IRelmModel, new()
```

Parameters

connectionName [Enum](#)

The connection identifier used to determine the data source.

query [string](#)

The query string used to retrieve the data object.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameters to be used in the query. The keys represent parameter names, and the values represent their corresponding values.

throwException [bool](#)

A boolean value indicating whether an exception should be thrown if the query fails or no data is found. If [true](#), an exception is thrown; otherwise, [null](#) is returned.

allowUserVariables [bool](#)

A boolean value indicating whether user-defined variables are allowed in the query. Set to [true](#) to enable user variables; otherwise, [false](#).

Returns

T

An instance of the specified type **T** populated with the data retrieved from the query, or [null](#) if no data is found and **throwException** is [false](#).

Type Parameters

T

The type of the data object to retrieve. Must implement [IRelmModel](#) and have a parameterless constructor.

Remarks

This method is a convenience wrapper for retrieving a single data object. If multiple objects match the query, only the first one is returned.

GetDataObjects<T>(MySQLConnection, string, Dictionary<string, object>, bool, MySQLTransaction)

Retrieves a collection of data objects of the specified type from the database based on the provided query and parameters.

```
public static IEnumerable<T> GetDataObjects<T>(MySQLConnection establishedConnection, string
query, Dictionary<string, object> parameters = null, bool throwException = true,
MySQLTransaction sqlTransaction = null) where T : IRelmModel, new()
```

Parameters

establishedConnection MySQLConnection

An open `MySQL.Data.MySqlClient.MySqlConnection` to the database. The connection must be established and valid.

query [string](#)

The SQL query to execute for retrieving the data objects.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. Can be [null](#) if no parameters are required.

throwException [bool](#)

A value indicating whether an exception should be thrown if an error occurs during query execution. If [true](#), exceptions will be propagated; otherwise, errors will be suppressed.

sqlTransaction `MySqlTransaction`

An optional `MySQL.Data.MySqlClient.MySqlTransaction` to associate with the query execution. Can be [null](#) if no transaction is required.

Returns

[IEnumerable](#) <`T`>

An [IEnumerable<T>](#) containing the data objects retrieved from the database. The collection will be empty if no matching records are found.

Type Parameters

T

The type of the data objects to retrieve. Must implement [IRelmModel](#) and have a parameterless constructor.

Remarks

This method uses the specified SQL query and parameters to retrieve data objects from the database. Ensure that the query matches the structure of the type **T**.

`GetDataObjects<T>(IRelmContext, string, Dictionary<string,`

object>, bool)

Executes a query against the specified Realm context and retrieves a collection of data objects of the specified type.

```
public static IEnumerable<T> GetDataObjects<T>(IRelmContext realmContext, string query,
Dictionary<string, object> parameters = null, bool throwException = true) where T :
IRelmModel, new()
```

Parameters

realmContext [IRelmContext](#)

The Realm context used to execute the query. This context provides the connection and configuration for the database.

query [string](#)

The query string to execute. This should be a valid query supported by the Realm context.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameters to include in the query. The keys represent parameter names, and the values represent their corresponding values.

throwException [bool](#)

A boolean value indicating whether an exception should be thrown if an error occurs during query execution. If [true](#), an exception will be thrown; otherwise, the method will handle the error silently.

Returns

[IEnumerable](#) <T>

An [IEnumerable<T>](#) containing the data objects retrieved by the query. If no data is found, the collection will be empty.

Type Parameters

T

The type of data objects to retrieve. Must implement [IRelmModel](#) and have a parameterless constructor.

Remarks

This method provides a convenient way to execute queries and retrieve data objects. Ensure that the query string and parameters are properly formatted to avoid runtime errors.

GetDataObjects<T>(IRelmQuickContext, string, Dictionary<string, object>, bool)

Executes a query against the specified Relm context and retrieves a collection of data objects of the specified type.

```
public static IEnumerable<T> GetDataObjects<T>(IRelmQuickContext relmContext, string query,
Dictionary<string, object> parameters = null, bool throwException = true) where T :
IRelmModel, new()
```

Parameters

relmContext [IRelmQuickContext](#)

The Relm context used to execute the query. This context provides the connection and configuration for the database.

query [string](#)

The query string to execute. The query must be valid for the underlying database.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameters to include in the query. Keys represent parameter names, and values represent their corresponding values.

throwException [bool](#)

A value indicating whether an exception should be thrown if an error occurs during query execution. If [true](#), exceptions will be thrown; otherwise, errors will be suppressed.

Returns

[IEnumerable](#) <T>

An [IEnumerable<T>](#) containing the data objects retrieved by the query. The collection will be empty if no matching data is found.

Type Parameters

T

The type of data objects to retrieve. Must implement [IRelmModel](#) and have a parameterless constructor.

Remarks

This method provides a convenient way to execute queries and retrieve data objects. Ensure that the query string and parameters are properly formatted to avoid runtime errors.

GetDataObjects<T>(DataTable)

Converts the rows of the specified [DataTable](#) into a collection of objects of type **T**.

```
public static IEnumerable<T> GetDataObjects<T>(DataTable existingData) where T :  
IRelmModel, new()
```

Parameters

existingData [DataTable](#)

The [DataTable](#) containing the data to be converted. Each row in the table is mapped to an object of type **T**.

Returns

[IEnumerable](#)<T>

An [IEnumerable<T>](#) containing the objects created from the rows of the **existingData** table.

Type Parameters

T

The type of objects to create from the data rows. Must implement [IRelmModel](#) and have a parameterless constructor.

Remarks

This method uses the [GetDataObjects<T>\(DataTable\)](#) method to perform the conversion. Ensure that the `existingData` table contains columns that match the properties of type `T`.

GetDataObjects<T>(Enum, string, Dictionary<string, object>, bool, bool)

Retrieves a collection of data objects of the specified type from the database.

```
public static IEnumerable<T> GetDataObjects<T>(Enum connectionName, string query,
Dictionary<string, object> parameters = null, bool throwException = true, bool
allowUserVariables = false) where T : IRelmModel, new()
```

Parameters

`connectionName` [Enum](#)

The name of the database connection to use. This must be an enumeration value representing a valid connection.

`query` [string](#)

The SQL query to execute for retrieving the data objects.

`parameters` [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to include in the query. Can be [null](#) if no parameters are needed.

`throwException` [bool](#)

A value indicating whether an exception should be thrown if an error occurs during query execution. If [true](#), exceptions will be thrown; otherwise, errors will be suppressed.

`allowUserVariables` [bool](#)

A value indicating whether user-defined variables are allowed in the query. Set to [true](#) to enable user variables; otherwise, [false](#).

Returns

[IEnumerable](#) <`T`>

An [IEnumerable<T>](#) containing the data objects retrieved by the query. If no data is found, an empty collection is returned.

Type Parameters

T

The type of data objects to retrieve. Must implement [IRelmModel](#) and have a parameterless constructor.

Remarks

This method provides additional options for query execution. Ensure that the SQL query and parameters are properly constructed to avoid runtime errors.

GetDataRow(MySqlConnection, string, Dictionary<string, object>, bool, MySqlConnectionTransaction)

Executes the specified SQL query and retrieves the first row of the result set as a [DataRow](#).

```
public static DataRow GetDataRow(MySqlConnection establishedConnection, string query,
Dictionary<string, object> parameters = null, bool throwException = true, MySqlConnection
sqlTransaction = null)
```

Parameters

establishedConnection MySqlConnection

An open `MySql.Data.MySqlClient.MySqlConnection` to the database. The connection must be in an open state before calling this method.

query [string](#)

The SQL query to execute. The query must be a valid SQL statement that returns a result set.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. If null, no parameters are applied.

throwException [bool](#)

A boolean value indicating whether to throw an exception if the query fails. [true](#) to throw an exception on failure; otherwise, [false](#).

sqlTransaction MySqlConnection

An optional MySql.Data.MySqlClient.MySqlTransaction to associate with the query. If null, the query is executed without a transaction.

Returns

[DataRow](#)

A [DataRow](#) representing the first row of the result set. Returns [null](#) if the query does not return any rows.

Remarks

This method is a convenience wrapper for retrieving a single row from the result set of a query. If the query returns multiple rows, only the first row is returned. If no rows are returned, the method returns [null](#).

GetDataRow(IRelmContext, string, Dictionary<string, object>, bool)

Executes the specified query and retrieves the first row of the result set as a [DataRow](#).

```
public static DataRow GetDataRow(IRelmContext relmContext, string query, Dictionary<string, object> parameters = null, bool throwException = true)
```

Parameters

relmContext [IRelmContext](#)

The database context used to execute the query. Cannot be [null](#).

query [string](#)

The SQL query to execute. Cannot be [null](#) or empty.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to include in the query. Can be [null](#) if no parameters are required.

throwException [bool](#)

A value indicating whether an exception should be thrown if the query does not return any rows. [true](#) to throw an exception when no rows are returned; otherwise, [false](#).

Returns

[DataRow](#)

A [DataRow](#) representing the first row of the result set. Returns [null](#) if no rows are found and **throwException** is [false](#).

GetDataRow(IRelMQuickContext, string, Dictionary<string, object>, bool)

Executes the specified query and retrieves the first row of the result set as a [DataRow](#).

```
public static DataRow GetDataRow(IRelMQuickContext relmQuickContext, string query,
Dictionary<string, object> parameters = null, bool throwException = true)
```

Parameters

relmQuickContext [IRelMQuickContext](#)

The context used to execute the query. This must not be [null](#).

query [string](#)

The SQL query to execute. This must not be [null](#) or empty.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. If [null](#), no parameters are applied.

throwException [bool](#)

A value indicating whether an exception should be thrown if the query does not return any rows. If [true](#), an exception is thrown when no rows are found; otherwise, [null](#) is returned.

Returns

[DataRow](#)

The first row of the result set as a [DataRow](#), or [null](#) if no rows are found and `throwException` is [false](#).

GetDataRow(Enum, string, Dictionary<string, object>, bool, bool)

Executes the specified query and retrieves the first row of the result set as a [DataRow](#).

```
public static DataRow GetDataRow(Enum connectionName, string query, Dictionary<string, object> parameters = null, bool throwException = true, bool allowUserVariables = false)
```

Parameters

`connectionName` [Enum](#)

An [Enum](#) representing the connection name to use for the database operation.

`query` [string](#)

The SQL query to execute. This query must be a valid SQL statement.

`parameters` [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. If null, no parameters are applied.

`throwException` [bool](#)

A boolean value indicating whether an exception should be thrown if the query fails. [true](#) to throw an exception on failure; otherwise, [false](#).

`allowUserVariables` [bool](#)

A boolean value indicating whether user-defined variables are allowed in the query. [true](#) to allow user variables; otherwise, [false](#).

Returns

[DataRow](#)

A [DataRow](#) representing the first row of the result set. Returns [null](#) if the query does not return any rows.

Remarks

This method uses the connection associated with the specified `connectionName` to execute the query. If `parameters` are provided, they are applied to the query as named parameters.

GetDataTable(MySqlConnection, string, Dictionary<string, object>, bool, MySqlConnectionTransaction)

Executes the specified SQL query and retrieves the results as a [DataTable](#).

```
public static DataTable GetDataTable(MySqlConnection establishedConnection, string query,
Dictionary<string, object> parameters = null, bool throwException = true, MySqlConnection
sqlTransaction = null)
```

Parameters

`establishedConnection` MySqlConnection

An open `MySql.Data.MySqlClient.MySqlConnection` to the database. The connection must be in an open state before calling this method.

`query` [string](#)

The SQL query to execute. The query can include parameter placeholders.

`parameters` [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and their corresponding values to be used in the query. If null, no parameters are applied.

`throwException` [bool](#)

A boolean value indicating whether to throw an exception if an error occurs. If [true](#), exceptions are thrown; otherwise, errors are suppressed.

`sqlTransaction` MySqlConnectionTransaction

An optional `MySQL.Data.MySqlClient.MySqlTransaction` to associate with the query. If null, the query is executed without a transaction.

Returns

[DataTable](#)

A [DataTable](#) containing the results of the query. If the query returns no rows, the [DataTable](#) will be empty.

GetDataTable(IRelmContext, string, Dictionary<string, object>, bool)

Executes the specified query against the provided Relm context and returns the results as a [DataTable](#).

```
public static DataTable GetDataTable(IRelmContext relmContext, string query,
Dictionary<string, object> parameters = null, bool throwException = true)
```

Parameters

relmContext [IRelmContext](#)

The Relm context used to execute the query. This cannot be [null](#).

query [string](#)

The SQL query to execute. This cannot be [null](#) or empty.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. Can be [null](#) if no parameters are required.

throwException [bool](#)

A value indicating whether an exception should be thrown if an error occurs during query execution. If [true](#), exceptions will be thrown; otherwise, errors will be suppressed.

Returns

[DataTable](#)

A [DataTable](#) containing the results of the query. If the query returns no results, the [DataTable](#) will be empty.

GetDataTable(IRelmQuickContext, string, Dictionary<string, object>, bool)

Executes the specified query against the provided RelmQuick context and returns the results as a [DataTable](#).

```
public static DataTable GetDataTable(IRelmQuickContext relmQuickContext, string query,
Dictionary<string, object> parameters = null, bool throwException = true)
```

Parameters

relmQuickContext [IRelmQuickContext](#)

The context used to execute the query. This must not be [null](#).

query [string](#)

The SQL query to execute. This must not be [null](#) or empty.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. If [null](#), no parameters are applied.

throwException [bool](#)

A value indicating whether an exception should be thrown if an error occurs during query execution. If [true](#), exceptions are thrown; otherwise, errors are suppressed.

Returns

[DataTable](#)

A [DataTable](#) containing the results of the query. The table will be empty if the query returns no rows.

Remarks

This method provides a convenient way to execute queries and retrieve results in a tabular format. Ensure that the **relmQuickContext** is properly initialized before calling this method.

GetDataTable(Enum, string, Dictionary<string, object>, bool, bool)

Executes the specified SQL query and returns the results as a [DataTable](#).

```
public static DataTable GetDataTable(Enum connectionName, string query, Dictionary<string, object> parameters = null, bool throwException = true, bool allowUserVariables = false)
```

Parameters

connectionName [Enum](#)

An [Enum](#) representing the name of the database connection to use.

query [string](#)

The SQL query to execute. This query must be a valid SQL statement.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. If null, no parameters are applied.

throwException [bool](#)

A boolean value indicating whether to throw an exception if an error occurs. If [true](#), exceptions are thrown; otherwise, errors are suppressed.

allowUserVariables [bool](#)

A boolean value indicating whether user-defined variables are allowed in the query. If [true](#), user-defined variables are permitted; otherwise, they are not.

Returns

[DataTable](#)

A [DataTable](#) containing the results of the query. The [DataTable](#) will be empty if the query returns no rows.

Remarks

This method establishes a database connection based on the provided **connectionName** and executes the given query. If **parameters** are provided, they are added to the query to prevent SQL injection.

GetIdFromInternalId(IRelmContext, string, string)

Retrieves the ID associated with the specified internal ID from the given table.

```
public static string GetIdFromInternalId(IRelmContext relmContext, string tableName,
string InternalId)
```

Parameters

relmContext [IRelmContext](#)

The database context used to execute the query.

tableName [string](#)

The name of the table to query. Must not be null or empty.

InternalId [string](#)

The internal ID to search for. Must not be null or empty.

Returns

[string](#)

The ID as a string if a matching record is found; otherwise, [null](#).

Remarks

This method executes a SQL query to retrieve the ID corresponding to the provided internal ID. Ensure that the table specified by **tableName** contains columns named "ID" and "InternalId".

GetIdFromInternalId(IRelmQuickContext, string, string)

Retrieves the ID associated with the specified internal ID from the given table.

```
public static string GetIdFromInternalId(IRelmQuickContext relmQuickContext, string
tableName, string InternalId)
```

Parameters

realmQuickContext [IRelmQuickContext](#)

The database quick context used to execute the query.

tableName [string](#)

The name of the table to query. Must not be null or empty.

InternalId [string](#)

The internal ID to search for. Must not be null or empty.

Returns

[string](#)

The ID corresponding to the specified internal ID, or [null](#) if no match is found.

Remarks

This method executes a SQL query to retrieve the external ID from the specified table. Ensure that the table contains a column named "InternalId" and that the query is executed in a secure and valid context.

GetIdFromInternalId(Enum, string, string)

Retrieves the ID associated with the specified internal ID from the given table.

```
public static string GetIdFromInternalId(Enum connectionName, string tableName,
string InternalId)
```

Parameters

connectionName [Enum](#)

The database connection identifier, represented as an enumeration value.

tableName [string](#)

The name of the database table to query. Must not be null or empty.

InternalId [string](#)

The internal ID to search for. Must not be null or empty.

Returns

[string](#)

The ID as a string if a matching record is found; otherwise, [null](#).

Remarks

This method executes a SQL query to retrieve the ID corresponding to the provided internal ID. Ensure that the `connectionName` corresponds to a valid database connection and that the `tableName` exists in the database schema.

GetLastInsertId(IRealmContext)

Retrieves the identifier of the last inserted row in the current database session.

```
public static string GetLastInsertId(IRealmContext realmContext)
```

Parameters

`realmContext` [IRealmContext](#)

The database context used to execute the query. This context must be properly initialized and connected to the database.

Returns

[string](#)

A string containing the identifier of the last inserted row. The value is determined by the database's `LAST_INSERT_ID()` function.

Remarks

This method relies on the database's `LAST_INSERT_ID()` function, which typically returns the most recent auto-increment value generated during the current session. Ensure that the database supports this function and that the session context is consistent with the operation that generated the ID.

GetLastInsertId(IRealmQuickContext)

Retrieves the identifier of the last inserted row in the current database session.

```
public static string GetLastInsertId(IRelmQuickContext relmQuickContext)
```

Parameters

relmQuickContext [IRelmQuickContext](#)

The database quick context used to execute the query. This context must be properly initialized and connected to the database.

Returns

[string](#)

A string representing the identifier of the last inserted row. The value is determined by the database's LAST_INSERT_ID() function.

Remarks

This method relies on the database's LAST_INSERT_ID() function, which typically returns the most recent auto-increment value generated during the current session. Ensure that the database supports this function and that the session context is consistent with the operation that generated the ID.

GetLastInsertId(Enum)

Retrieves the identifier of the last inserted row in the database for the specified connection.

```
public static string GetLastInsertId(Enum connectionName)
```

Parameters

connectionName [Enum](#)

An enumeration value representing the configuration connection string to use for the database query.

Returns

[string](#)

A string containing the identifier of the last inserted row. The value is determined by the database's LAST_INSERT_ID() function.

Remarks

This method relies on the database's LAST_INSERT_ID() function, which typically returns the most recent auto-increment value generated during the current session. Ensure that the database supports this function and that the session context is consistent with the operation that generated the ID.

GetScalar<T>(MySqlConnection, string, Dictionary<string, object>, bool, MySqlConnectionTransaction)

Executes a scalar query on the specified MySQL connection and returns the result as the specified type.

```
public static T GetScalar<T>(MySqlConnection establishedConnection, string query,
Dictionary<string, object> parameters = null, bool throwException = true, MySqlConnection
sqlTransaction = null)
```

Parameters

establishedConnection MySqlConnection

An open MySql.Data.MySqlClient.MySqlConnection to execute the query on. The connection must be valid and open.

query [string](#)

The SQL query string to execute. The query must return a single value.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. If null, no parameters are applied.

throwException [bool](#)

A boolean value indicating whether to throw an exception if an error occurs. If [true](#), exceptions will be thrown; otherwise, errors will be suppressed.

sqlTransaction MySqlConnectionTransaction

An optional `MySQL.Data.MySqlClient.MySqlTransaction` to associate with the query. If null, the query will not be part of a transaction.

Returns

T

The scalar result of the query, converted to the specified type **T**. Returns the default value of **T** if the query result is null.

Type Parameters

T

The type to which the scalar result will be converted.

GetScalar<T>(IRelmContext, string, Dictionary<string, object>, bool)

Executes a scalar query and retrieves the result as the specified type.

```
public static T GetScalar<T>(IRelmContext relmContext, string query, Dictionary<string, object> parameters = null, bool throwException = true)
```

Parameters

relmContext [IRelmContext](#)

The database context used to execute the query. Cannot be [null](#).

query [string](#)

The SQL query string to execute. Cannot be [null](#) or empty.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to include in the query. Can be [null](#) if no parameters are required.

throwException [bool](#)

Indicates whether an exception should be thrown if the query fails. If [true](#), an exception will be thrown on failure; otherwise, the method will return the default value of `T`.

Returns

`T`

The scalar result of the query converted to the specified type `T`. Returns the default value of `T` if the query produces no result or fails and `throwException` is [false](#).

Type Parameters

`T`

The type to which the scalar result will be converted.

GetScalar<T>(IRelmQuickContext, string, Dictionary<string, object>, bool)

Executes a scalar query and retrieves the result as the specified type.

```
public static T GetScalar<T>(IRelmQuickContext relmQuickContext, string query,
Dictionary<string, object> parameters = null, bool throwException = true)
```

Parameters

`relmQuickContext` [IRelmQuickContext](#)

The database context used to execute the query. Cannot be [null](#).

`query` [string](#)

The SQL query string to execute. Cannot be [null](#) or empty.

`parameters` [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameters to include in the query. Keys represent parameter names, and values represent parameter values. Can be [null](#) if no parameters are needed.

`throwException` [bool](#)

Indicates whether an exception should be thrown if the query fails. If [true](#), an exception will be thrown on failure; otherwise, the method will return the default value of `T`.

Returns

`T`

The result of the scalar query, cast to the specified type `T`. Returns the default value of `T` if the query fails and `throwException` is [false](#).

Type Parameters

`T`

The type of the result to be returned.

GetScalar<T>(Enum, string, Dictionary<string, object>, bool, bool)

Executes a scalar query and retrieves the first column of the first row in the result set, cast to the specified type.

```
public static T GetScalar<T>(Enum connectionName, string query, Dictionary<string, object>
parameters = null, bool throwException = true, bool allowUserVariables = false)
```

Parameters

`connectionName` [Enum](#)

The name of the database connection to use. Must be a valid enumeration value representing a configured connection.

`query` [string](#)

The SQL query to execute. The query should return a single value.

`parameters` [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. Can be [null](#) if no parameters are required.

`throwException` [bool](#)

Indicates whether an exception should be thrown if an error occurs during query execution. If [true](#), exceptions will be propagated; otherwise, errors will be suppressed.

allowUserVariables [bool](#)

Indicates whether user-defined variables are allowed in the query. Set to [true](#) to enable user variables; otherwise, [false](#).

Returns

T

The scalar result of the query, cast to the specified type **T**. Returns the default value of **T** if the query returns no result.

Type Parameters

T

The type to which the scalar result will be cast.

Remarks

This method is typically used to retrieve single values, such as counts, sums, or other aggregate results, from a database query.

LoadDataLoaderField<T, R>(IRelmContext, ICollection<T>, Expression<Func<T, R>>)

Loads a specified field for a collection of models using a DataLoader pattern.

```
public static ICollection<T> LoadDataLoaderField<T, R>(IRelmContext relmContext,
    ICollection<T> target, Expression<Func<T, R>> predicate) where T : IRelmModel, new()
```

Parameters

relmContext [IRelmContext](#)

The context used to interact with the data source.

target [ICollection](#)<T>

The collection of models for which the field will be loaded. Cannot be null.

predicate [Expression](#) <[Func](#) <T, R>>

An expression specifying the field to load for each model in the collection. Cannot be null.

Returns

[ICollection](#) <T>

The updated collection of models with the specified field loaded.

Type Parameters

T

The type of the model in the collection. Must implement [IRelmModel](#) and have a parameterless constructor.

R

The type of the field to be loaded.

Remarks

This method uses a DataLoader pattern to efficiently load the specified field for all models in the collection. It is designed to minimize database queries by batching and caching operations.

LoadDataLoaderField<T, R>(IRelmContext, T, Expression<Func<T, R>>)

Loads a specified field of a data model using a DataLoader and returns the first result.

```
public static T LoadDataLoaderField<T, R>(IRelmContext relmContext, T target,
Expression<Func<T, R>> predicate) where T : IRelmModel, new()
```

Parameters

relmContext [IRelmContext](#)

The context used to interact with the data source.

target T

The target data model instance whose field is to be loaded.

predicate [Expression](#) <[Func](#) <T, R>>

An expression specifying the field to load.

Returns

T

The first result of the loaded field, or the default value of **R** if no results are found.

Type Parameters

T

The type of the data model, which must implement [IRealmModel](#) and have a parameterless constructor.

R

The type of the field to be loaded.

Remarks

This method uses a `DataLoader` to load the specified field of the target data model. If multiple results are loaded, only the first result is returned.

LoadDataLoaderField<T, R>(IRealmQuickContext, T, Expression<Func<T, R>>)

Loads a specified field of a data model using a `DataLoader` and returns the first result.

```
public static T LoadDataLoaderField<T, R>(IRealmQuickContext realmQuickContext, T target,
Expression<Func<T, R>> predicate) where T : IRealmModel, new()
```

Parameters

realmQuickContext [IRealmQuickContext](#)

The context used to interact with the data source.

target T

The target data model instance whose field is to be loaded.

predicate [Expression](#) <[Func](#) <T, R>>

An expression specifying the field to load from the data model.

Returns

T

The first result of the loaded field, or the default value of **R** if no results are found.

Type Parameters

T

The type of the data model, which must implement [IRelmModel](#) and have a parameterless constructor.

R

The type of the field to be loaded.

Remarks

This method uses a `DataLoader` to load the specified field of the target data model. If multiple results are loaded, only the first result is returned.

LoadForeignKeyField<T, R>(RelmContextOptionsBuilder, ICollection<T>, Expression<Func<T, ICollection<R>>>)

Loads a foreign key field for a collection of entities, resolving the related entities based on the specified predicate.

```
public static ICollection<T> LoadForeignKeyField<T, R>(RelmContextOptionsBuilder  
    relmContextOptionsBuilder, ICollection<T> target, Expression<Func<T, ICollection<R>>>  
    predicate) where T : IRelmModel, new() where R : IRelmModel, new()
```

Parameters

relmContextOptionsBuilder [RelmContextOptionsBuilder](#)

The options builder used to configure the database context.

target [ICollection](#) <T>

The collection of primary entities for which the foreign key field will be loaded.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R> > >

An expression specifying the foreign key relationship to load.

Returns

[ICollection](#) <T>

A collection of the primary entities with the specified foreign key field loaded.

Type Parameters

T

The type of the primary entity. Must implement [IRelmModel](#).

R

The type of the related entity. Must implement [IRelmModel](#).

Remarks

This method uses the provided **realmContextOptionsBuilder** to configure the database context and resolves the foreign key relationship defined by **predicate** for the given **target** collection.

LoadForeignKeyField<T, R>(RelmContextOptionsBuilder, ICollection<T>, Expression<Func<T, ICollection<R> > >, Expression<Func<R, object> > >)

Loads and populates a foreign key collection field for the specified target entities.

```
public static ICollection<T> LoadForeignKeyField<T, R>(RelmContextOptionsBuilder
realmContextOptionsBuilder, ICollection<T> target, Expression<Func<T, ICollection<R> > >
predicate, Expression<Func<R, object> > > additionalConstraints) where T : IRelmModel, new()
where R : IRelmModel, new()
```

Parameters

`realmContextOptionsBuilder` [RealmContextOptionsBuilder](#)

The options builder used to configure the database context.

`target` [ICollection](#) <T>

The collection of target entities for which the foreign key field will be loaded.

`predicate` [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the foreign key collection property to load.

`additionalConstraints` [Expression](#) <[Func](#) <R, [object](#)>>

An expression defining additional constraints to apply when loading the related entities.

Returns

[ICollection](#) <T>

A collection of the target entities with the specified foreign key field populated.

Type Parameters

T

The type of the target entities that contain the foreign key collection.

R

The type of the related entities in the foreign key collection.

Remarks

This method uses the provided `realmContextOptionsBuilder` to configure the database context and loads the related entities for the specified foreign key field. The `additionalConstraints` parameter can be used to filter or constrain the related entities being loaded.

LoadForeignKeyField<T, R>(RealmContextOptionsBuilder, ICollection<T>, Expression<Func<T, R>>)

Loads and resolves a foreign key field for a collection of entities.

```
public static ICollection<T> LoadForeignKeyField<T, R>(RelmContextOptionsBuilder  
relmContextOptionsBuilder, ICollection<T> target, Expression<Func<T, R>> predicate) where T  
: IRelmModel, new() where R : IRelmModel, new()
```

Parameters

relmContextOptionsBuilder [RelmContextOptionsBuilder](#)

The options builder used to configure the database context.

target [ICollection](#)<T>

The collection of entities for which the foreign key field will be loaded.

predicate [Expression](#)<[Func](#)<T, R>>

An expression specifying the foreign key field to load.

Returns

[ICollection](#)<T>

A collection of entities of type **T** with the specified foreign key field resolved.

Type Parameters

T

The type of the entity in the target collection. Must implement [IRelmModel](#).

R

The type of the related entity being loaded. Must implement [IRelmModel](#).

Remarks

This method uses a SimpleRelm.RelmInternal.Helpers.Utilities.ForeignKeyLoader<T> to load the foreign key field for the specified collection. The **predicate** parameter determines which foreign key field is resolved.

LoadForeignKeyField<T, R>(RelmContextOptionsBuilder,
ICollection<T>, Expression<Func<T, R>>, Expression<Func<R,

object>>)

Loads and resolves a foreign key field for a collection of entities, applying the specified constraints.

```
public static ICollection<T> LoadForeignKeyField<T, R>(RelmContextOptionsBuilder  
    relmContextOptionsBuilder, ICollection<T> target, Expression<Func<T, R>> predicate,  
    Expression<Func<R, object>> additionalConstraints) where T : IRelmModel, new() where R :  
    IRelmModel, new()
```

Parameters

relmContextOptionsBuilder [RelmContextOptionsBuilder](#)

The options builder used to configure the database context for the operation.

target [ICollection](#)<T>

The collection of primary entities for which the foreign key field will be loaded.

predicate [Expression](#)<[Func](#)<T, R>>

An expression specifying the foreign key relationship between the primary and related entities.

additionalConstraints [Expression](#)<[Func](#)<R, [object](#)>>

An optional expression specifying additional constraints to apply when resolving the foreign key field.

Returns

[ICollection](#)<T>

A collection of the primary entities with the foreign key field resolved and loaded.

Type Parameters

T

The type of the primary entity in the collection. Must implement [IRelmModel](#).

R

The type of the related entity referenced by the foreign key. Must implement [IRelmModel](#).

Remarks

This method uses a `SimpleRealm.RelmInternal.Helpers.Utilities.ForeignKeyLoader<T>` to resolve and load the foreign key field for the specified collection of entities. The `predicate` defines the relationship between the primary and related entities, while the `additionalConstraints` can be used to further filter or constrain the related entities.

LoadForeignKeyField<T, R>(RealmContextOptionsBuilder, T, Expression<Func<T, ICollection<R>>>)

Loads a foreign key field for the specified target entity and retrieves the first related entity matching the given predicate.

```
public static T LoadForeignKeyField<T, R>(RealmContextOptionsBuilder
    realmContextOptionsBuilder, T target, Expression<Func<T, ICollection<R>>> predicate) where T
    : IRelmModel, new() where R : IRelmModel, new()
```

Parameters

`realmContextOptionsBuilder` [RealmContextOptionsBuilder](#)

The options builder used to configure the database context.

`target` T

The target entity for which the foreign key field is being loaded.

`predicate` [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the collection navigation property on the target entity that represents the foreign key relationship.

Returns

T

The first related entity matching the specified predicate, or [null](#) if no related entities are found.

Type Parameters

T

The type of the target entity, which must implement [IRelmModel](#).

R

The type of the related entity, which must implement [IRelmModel](#).

Remarks

This method is typically used to load and access a specific related entity in a foreign key relationship. Ensure that the `realmContextOptionsBuilder` is properly configured to access the database context.

LoadForeignKeyField<T, R>(RealmContextOptionsBuilder, T, Expression<Func<T, ICollection<R>>>, Expression<Func<R, object>>)

Loads a foreign key field for the specified target entity, applying the given predicate and additional constraints.

```
public static T LoadForeignKeyField<T, R>(RealmContextOptionsBuilder
realmContextOptionsBuilder, T target, Expression<Func<T, ICollection<R>>> predicate,
Expression<Func<R, object>> additionalConstraints) where T : IRelmModel, new() where R :
IRelmModel, new()
```

Parameters

`realmContextOptionsBuilder` [RealmContextOptionsBuilder](#)

The options builder used to configure the database context.

`target` T

The target entity for which the foreign key field is being loaded.

`predicate` [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the collection navigation property on the target entity.

`additionalConstraints` [Expression](#) <[Func](#) <R, [object](#)>>

An expression specifying additional constraints to apply when loading the related entities.

Returns

T

The first related entity that matches the specified predicate and constraints, or [null](#) if no match is found.

Type Parameters

T

The type of the target entity, which must implement [IRelmModel](#).

R

The type of the related entity, which must implement [IRelmModel](#).

LoadForeignKeyField<T, R>(RelmContextOptionsBuilder, T, Expression<Func<T, R>>)

Loads a foreign key field for the specified target entity using the provided predicate.

```
public static T LoadForeignKeyField<T, R>(RelmContextOptionsBuilder  
    relmContextOptionsBuilder, T target, Expression<Func<T, R>> predicate) where T : IRelmModel,  
    new() where R : IRelmModel, new()
```

Parameters

relmContextOptionsBuilder [RelmContextOptionsBuilder](#)

The options builder used to configure the database context.

target T

The target entity for which the foreign key field is to be loaded.

predicate [Expression](#) <[Func](#) <T, R>>

An expression specifying the foreign key field to load.

Returns

T

The first related entity of type **R** that matches the foreign key field, or [null](#) if no match is found.

Type Parameters

T

The type of the target entity. Must implement [IRelmModel](#) and have a parameterless constructor.

R

The type of the related entity. Must implement [IRelmModel](#) and have a parameterless constructor.

Remarks

This method uses a `SimpleRelm.RelmInternal.Helpers.Utilities.ForeignKeyLoader<T>` to load the foreign key field for the specified target entity.

LoadForeignKeyField<T, R>(RelmContextOptionsBuilder, T, Expression<Func<T, R>>, Expression<Func<R, object>>)

Loads a foreign key field for the specified target model, applying the given predicate and additional constraints.

```
public static T LoadForeignKeyField<T, R>(RelmContextOptionsBuilder  
    relmContextOptionsBuilder, T target, Expression<Func<T, R>> predicate, Expression<Func<R,  
    object>> additionalConstraints) where T : IRelmModel, new() where R : IRelmModel, new()
```

Parameters

relmContextOptionsBuilder [RelmContextOptionsBuilder](#)

The options builder used to configure the database context.

target T

The target model instance for which the foreign key field is being loaded.

predicate [Expression](#) <[Func](#) <T, R>>

An expression specifying the foreign key relationship between the target and related models.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#)>>

An optional expression specifying additional constraints to apply when loading the related model.

Returns

T

The first related model that matches the specified predicate and additional constraints, or [null](#) if no match is found.

Type Parameters

T

The type of the target model. Must implement [IRelmModel](#).

R

The type of the related model. Must implement [IRelmModel](#).

Remarks

This method is typically used to load a related model for a given target model based on a foreign key relationship. The method applies the specified predicate and additional constraints to filter the related models.

LoadForeignKeyField<T, R, S>(RelmContextOptionsBuilder, ICollection<T>, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>)

Loads a foreign key field for a collection of entities, using the specified predicate and custom data loader.

```
public static ICollection<T> LoadForeignKeyField<T, R, S>(RelmContextOptionsBuilder  
    relmContextOptionsBuilder, ICollection<T> target, Expression<Func<T, ICollection<R>>>  
    predicate, IRelmDataLoader<S> customDataLoader) where T : IRelmModel, new() where R :  
    IRelmModel, new() where S : IRelmModel, new()
```

Parameters

relmContextOptionsBuilder [RelmContextOptionsBuilder](#)

The options builder used to configure the database context.

target [ICollection](#) <T>

The collection of primary entities for which the foreign key field will be loaded.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the foreign key field to load for each entity in the collection.

customDataLoader [IRelmDataLoader](#) <S>

A custom data loader used to retrieve the related entities.

Returns

[ICollection](#) <T>

A collection of the primary entities with the specified foreign key field loaded.

Type Parameters

T

The type of the primary entity in the collection. Must implement [IRelmModel](#).

R

The type of the related entity in the foreign key relationship. Must implement [IRelmModel](#).

S

The type of the entity used by the custom data loader. Must implement [IRelmModel](#).

Remarks

This method facilitates the loading of related entities for a collection of primary entities by leveraging a custom data loader. The **predicate** defines the navigation property representing the foreign key relationship, and the **customDataLoader** provides the mechanism for retrieving the related data.

LoadForeignKeyField<T, R, S>(RelmContextOptionsBuilder, [ICollection](#)<T>, [Expression](#)<[Func](#)<T, [ICollection](#)<R>>>, [IRelmDataLoader](#)<S>, [Expression](#)<[Func](#)<R, object>>>)

Loads and populates a foreign key field for a collection of entities, applying optional constraints and using a custom data loader.

```
public static ICollection<T> LoadForeignKeyField<T, R, S>(RelmContextOptionsBuilder  
    relmContextOptionsBuilder, ICollection<T> target, Expression<Func<T, ICollection<R>>>  
    predicate, IRelmDataLoader<S> customDataLoader, Expression<Func<R, object>>  
    additionalConstraints) where T : IRelmModel, new() where R : IRelmModel, new() where S :  
    IRelmModel, new()
```

Parameters

relmContextOptionsBuilder [RelmContextOptionsBuilder](#)

The options builder used to configure the database context for the operation.

target [ICollection](#)<T>

The collection of primary entities for which the foreign key field will be loaded. Cannot be [null](#).

predicate [Expression](#)<[Func](#)<T, [ICollection](#)<R>>>

An expression specifying the foreign key field to load for each entity in the collection.

customDataLoader [IRelmDataLoader](#)<S>

A custom data loader used to retrieve the related entities. Cannot be [null](#).

additionalConstraints [Expression](#)<[Func](#)<R, [object](#)>>

An optional expression specifying additional constraints to apply when loading the related entities.

Returns

[ICollection](#)<T>

A collection of the primary entities with the specified foreign key field populated.

Type Parameters

T

The type of the primary entity in the collection. Must implement [IRelmModel](#).

R

The type of the related entity in the foreign key relationship. Must implement [IRelmModel](#).

S

The type of the entity used by the custom data loader. Must implement [IRelmModel](#).

Remarks

This method is designed to simplify the process of loading related entities for a collection of primary entities. It supports applying additional constraints to filter the related entities and allows the use of a custom data loader for advanced scenarios. The method ensures that the foreign key field specified by `predicate` is populated for each entity in the `target` collection.

LoadForeignKeyField<T, R, S>(RelmContextOptionsBuilder, ICollection<T>, Expression<Func<T, R>>, IRelmDataLoader<S>)

Loads and resolves a foreign key field for a collection of entities, using the specified predicate and data loader.

```
public static ICollection<T> LoadForeignKeyField<T, R, S>(RelmContextOptionsBuilder
    relmContextOptionsBuilder, ICollection<T> target, Expression<Func<T, R>> predicate,
    IRelmDataLoader<S> customDataLoader) where T : IRelmModel, new() where R : IRelmModel, new()
    where S : IRelmModel, new()
```

Parameters

`relmContextOptionsBuilder` [RelmContextOptionsBuilder](#)

The options builder used to configure the database context for loading related data.

`target` [ICollection](#)<T>

The collection of primary entities for which the foreign key field will be loaded.

`predicate` [Expression](#)<[Func](#)<T, R>>

An expression specifying the foreign key relationship to be resolved.

`customDataLoader` [IRelmDataLoader](#)<S>

A custom data loader used to fetch the related entities.

Returns

[ICollection](#)  <T>

A collection of the primary entities with the foreign key field resolved.

Type Parameters

T

The type of the primary entity in the collection. Must implement [IRelmModel](#).

R

The type of the related entity referenced by the foreign key. Must implement [IRelmModel](#).

S

The type of the entity used by the custom data loader. Must implement [IRelmModel](#).

Remarks

This method uses a `SimpleRelm.RelmInternal.Helpers.Utilities.ForeignKeyLoader<T>` to load and resolve the foreign key field for the specified collection of entities. The `customDataLoader` allows for custom logic to be applied when fetching the related entities.

LoadForeignKeyField<T, R, S>(RelmContextOptionsBuilder, ICollection<T>, Expression<Func<T, R>>, IRelmDataLoader<S>, Expression<Func<R, object>>)

Loads and resolves a foreign key field for a collection of entities, applying optional constraints and using a custom data loader.

```
public static ICollection<T> LoadForeignKeyField<T, R, S>(RelmContextOptionsBuilder  
    relmContextOptionsBuilder, ICollection<T> target, Expression<Func<T, R>> predicate,  
    IRelmDataLoader<S> customDataLoader, Expression<Func<R, object>> additionalConstraints)  
    where T : IRelmModel, new() where R : IRelmModel, new() where S : IRelmModel, new()
```

Parameters

`relmContextOptionsBuilder` [RelmContextOptionsBuilder](#)

The options builder used to configure the database context for loading the foreign key field.

target [ICollection](#) <T>

The collection of primary entities for which the foreign key field will be loaded.

predicate [Expression](#) <[Func](#) <T, R>>

An expression specifying the foreign key relationship between the primary entity and the related entity.

customDataLoader [IRelmDataLoader](#) <S>

A custom data loader used to retrieve the related entities.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#)>>

An optional expression specifying additional constraints to apply when resolving the foreign key field.

Returns

[ICollection](#) <T>

A collection of the primary entities with the foreign key field resolved and loaded.

Type Parameters

T

The type of the primary entity in the collection. Must implement [IRelmModel](#).

R

The type of the related entity referenced by the foreign key. Must implement [IRelmModel](#).

S

The type of the entity used by the custom data loader. Must implement [IRelmModel](#).

Remarks

This method is designed to simplify the process of resolving foreign key relationships for a collection of entities. It allows for the use of a custom data loader and additional constraints to tailor the loading process to specific requirements.

LoadForeignKeyField<T, R, S>(RealmContextOptionsBuilder, T, Expression<Func<T, ICollection<R>>>, IRealmDataLoader<S>)

Loads a foreign key field for the specified target entity using the provided predicate and custom data loader.

```
public static T LoadForeignKeyField<T, R, S>(RealmContextOptionsBuilder
realmContextOptionsBuilder, T target, Expression<Func<T, ICollection<R>>> predicate,
IRealmDataLoader<S> customDataLoader) where T : IRealmModel, new() where R : IRealmModel, new()
where S : IRealmModel, new()
```

Parameters

realmContextOptionsBuilder [RealmContextOptionsBuilder](#)

The options builder used to configure the database context.

target T

The target entity for which the foreign key field is being loaded.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the collection navigation property on the target entity.

customDataLoader [IRealmDataLoader](#) <S>

A custom data loader used to retrieve the related data.

Returns

T

The first related entity from the loaded foreign key collection, or [null](#) if no related entities are found.

Type Parameters

T

The type of the target entity. Must implement [IRealmModel](#).

R

The type of the related entity in the collection. Must implement [IRealmModel](#).

The type of the entity used by the custom data loader. Must implement [IRelmModel](#).

Remarks

This method uses a custom data loader to retrieve the related entities for the specified foreign key field. The first entity in the resulting collection is returned. If the collection is empty, the method returns [null](#).

LoadForeignKeyField<T, R, S>(RelmContextOptionsBuilder, T, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>, Expression<Func<R, object>>)

Loads a foreign key field for the specified target model, applying the given predicate, custom data loader, and additional constraints.

```
public static T LoadForeignKeyField<T, R, S>(RelmContextOptionsBuilder
    relmContextOptionsBuilder, T target, Expression<Func<T, ICollection<R>>> predicate,
    IRelmDataLoader<S> customDataLoader, Expression<Func<R, object>> additionalConstraints)
    where T : IRelmModel, new() where R : IRelmModel, new() where S : IRelmModel, new()
```

Parameters

relmContextOptionsBuilder [RelmContextOptionsBuilder](#)

The options builder used to configure the database context for the operation.

target T

The target model instance for which the foreign key field will be loaded.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the foreign key field to load as a collection of related entities.

customDataLoader [IRelmDataLoader](#) <S>

A custom data loader used to retrieve the related entities.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#)>>

An expression specifying additional constraints to apply when loading the related entities.

Returns

T

The first related entity that matches the specified predicate and constraints, or [null](#) if no match is found.

Type Parameters

T

The type of the target model that contains the foreign key field. Must implement [IRelmModel](#).

R

The type of the related model in the foreign key relationship. Must implement [IRelmModel](#).

S

The type of the model used by the custom data loader. Must implement [IRelmModel](#).

Remarks

This method is typically used to load a foreign key field for a model in scenarios where additional constraints or a custom data loader are required.

LoadForeignKeyField<T, R, S>(RelmContextOptionsBuilder, T, Expression<Func<T, R>>, IRelmDataLoader<S>)

Loads a foreign key field for the specified target model using the provided predicate and data loader.

```
public static T LoadForeignKeyField<T, R, S>(RelmContextOptionsBuilder  
    relmContextOptionsBuilder, T target, Expression<Func<T, R>> predicate, IRelmDataLoader<S>  
    customDataLoader) where T : IRelmModel, new() where R : IRelmModel, new() where S :  
    IRelmModel, new()
```

Parameters

relmContextOptionsBuilder [RelmContextOptionsBuilder](#)

The options builder used to configure the database context.

target T

The target model instance for which the foreign key field is being loaded.

predicate [Expression](#) <[Func](#) <T, R> >

An expression specifying the foreign key property to load.

customDataLoader [IRelmDataLoader](#) <S>

A custom data loader used to retrieve the related data.

Returns

T

The first related model of type **R** that matches the foreign key, or [null](#) if no match is found.

Type Parameters

T

The type of the target model. Must implement [IRelmModel](#) and have a parameterless constructor.

R

The type of the related model referenced by the foreign key. Must implement [IRelmModel](#) and have a parameterless constructor.

S

The type of the model used by the custom data loader. Must implement [IRelmModel](#) and have a parameterless constructor.

Remarks

This method uses a `SimpleRelm.RelmInternal.Helpers.Utilities.ForeignKeyLoader<T>` to load the foreign key field for the specified target model. Ensure that the provided **predicate** correctly identifies the foreign key property to be loaded.

```
LoadForeignKeyField<T, R, S>(RelmContextOptionsBuilder, T,  
Expression<Func<T, R>>, IRelmDataLoader<S>,  
Expression<Func<R, object>>)
```

Loads a foreign key field for the specified target model using the provided predicate and optional constraints.

```
public static T LoadForeignKeyField<T, R, S>(RealmContextOptionsBuilder
realmContextOptionsBuilder, T target, Expression<Func<T, R>> predicate, IRealmDataLoader<S>
customDataLoader, Expression<Func<R, object>> additionalConstraints) where T : IRealmModel,
new() where R : IRealmModel, new() where S : IRealmModel, new()
```

Parameters

realmContextOptionsBuilder [RealmContextOptionsBuilder](#)

The options builder used to configure the database context.

target T

The target model instance for which the foreign key field is being loaded.

predicate [Expression](#) <[Func](#) <T, R>>

An expression specifying the foreign key property on the target model.

customDataLoader [IRealmDataLoader](#)<S>

An optional custom data loader to retrieve the related data.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#)>>

An optional expression specifying additional constraints to apply when loading the foreign key field.

Returns

T

The first related model that matches the specified predicate and constraints, or [null](#) if no match is found.

Type Parameters

T

The type of the target model. Must implement [IRealmModel](#).

R

The type of the related model representing the foreign key. Must implement [IRelmModel](#).

S

The type of the model used by the custom data loader. Must implement [IRelmModel](#).

Remarks

This method is typically used to load a foreign key relationship for a model instance, optionally applying additional constraints or using a custom data loader to retrieve the related data.

StandardConnectionWrapper(Enum, Action<MySQLConnection, MySQLTransaction>, Action<Exception, string>)

Provides a standardized wrapper for executing database operations within a connection and transaction context.

```
public static void StandardConnectionWrapper(Enum connectionName, Action<MySQLConnection,
MySQLTransaction> actionWrapper, Action<Exception, string> exceptionHandler = null)
```

Parameters

connectionName [Enum](#)

The type of database connection to use, represented as an enumeration value.

actionWrapper [Action](#) <MySQLConnection, MySQLTransaction>

A delegate that defines the operations to perform using the provided `MySQL.Data.MySqlClient.MySqlConnection` and `MySQL.Data.MySqlClient.MySqlTransaction`. The connection and transaction are managed by the wrapper.

exceptionHandler [Action](#) <[Exception](#), [string](#)>

An optional delegate to handle exceptions that occur during the execution of **actionWrapper**. The delegate receives the exception and an error message as parameters. If not provided, exceptions will propagate to the caller.

Remarks

This method ensures that the database connection and transaction are properly managed, including opening, committing, rolling back, and disposing of resources as necessary. Use this wrapper to simplify

error handling and resource management for database operations.

StandardConnectionWrapper<T>(Enum, Func< MySqlConnection, MySqlConnection, T>, Action<Exception, string>)

Executes a database operation within a standard connection and transaction context.

```
public static T StandardConnectionWrapper<T>(Enum connectionName, Func<MySqlConnection, MySqlConnection, T> actionWrapper, Action<Exception, string> exceptionHandler = null)
```

Parameters

connectionName [Enum](#)

The name of the database connection, represented as an [Enum](#).

actionWrapper [Func](#) <MySqlConnection, MySqlConnection, T>

A delegate that defines the operation to execute. The delegate receives a `MySql.Data.MySqlClient.MySqlConnection` and a `MySql.Data.MySqlClient.MySqlTransaction` as parameters and returns a result of type `T`.

exceptionHandler [Action](#) <[Exception](#), [string](#)>

An optional delegate to handle exceptions that occur during the operation. The delegate receives the exception and a string message describing the context of the error.

Returns

T

The result of the operation, as defined by the **actionWrapper** delegate.

Type Parameters

T

The type of the result returned by the operation.

Remarks

This method provides a standardized way to execute database operations, ensuring that the connection and transaction are properly managed. If an exception occurs and an `exceptionHandler` is provided, the exception will be passed to the handler for custom processing.

WriteToDatabase(IRelmContext, IRelmModel, int, bool, bool, bool, bool)

Writes the specified model to the database using the provided context and configuration options.

```
public static int WriteToDatabase(IRelmContext relmContext, IRelmModel relmModel, int batchSize = 100, bool allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool allowUniqueColumns = false, bool allowAutoDateColumns = false)
```

Parameters

`relmContext` [IRelmContext](#)

The database context used to perform the write operation.

`relmModel` [IRelmModel](#)

The model to be written to the database.

`batchSize` [int](#)

The number of records to process in a single batch. Defaults to 100. Must be a positive integer.

`allowAutoIncrementColumns` [bool](#)

A value indicating whether columns with auto-increment constraints are allowed to be written. Defaults to [false](#).

`allowPrimaryKeyColumns` [bool](#)

A value indicating whether primary key columns are allowed to be written. Defaults to [false](#).

`allowUniqueColumns` [bool](#)

A value indicating whether columns with unique constraints are allowed to be written. Defaults to [false](#).

`allowAutoDateColumns` [bool](#)

A value indicating whether columns with automatic date generation are allowed to be written. Defaults to [false](#).

Returns

[int](#)

The number of records successfully written to the database.

Remarks

This method delegates the write operation to the `realmModel` implementation, which performs the actual database interaction. The behavior of the write operation is influenced by the provided configuration flags.

WriteToDatabase(IRelmContext, IEnumerable<IRelmModel>, int, bool, bool, bool, bool)

Writes a collection of models to the specified database context in batches.

```
public static int WriteToDatabase(IRelmContext realmContext, IEnumerable<IRelmModel>
realmModels, int batchSize = 100, bool allowAutoIncrementColumns = false, bool
allowPrimaryKeyColumns = false, bool allowUniqueColumns = false, bool allowAutoDateColumns
= false)
```

Parameters

`realmContext` [IRelmContext](#)

The database context to which the models will be written. This parameter cannot be [null](#).

`realmModels` [IEnumerable](#) <[IRelmModel](#)>

The collection of models to write to the database. This parameter cannot be [null](#) or empty.

`batchSize` [int](#)

The number of models to include in each batch. Must be a positive integer. The default value is 100.

`allowAutoIncrementColumns` [bool](#)

A value indicating whether auto-increment columns are allowed to be written. If [true](#), auto-increment columns will be included; otherwise, they will be excluded. The default value is [false](#).

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns are allowed to be written. If [true](#), primary key columns will be included; otherwise, they will be excluded. The default value is [false](#).

allowUniqueColumns [bool](#)

A value indicating whether unique columns are allowed to be written. If [true](#), unique columns will be included; otherwise, they will be excluded. The default value is [false](#).

allowAutoDateColumns [bool](#)

A value indicating whether auto-generated date columns are allowed to be written. If [true](#), auto-generated date columns will be included; otherwise, they will be excluded. The default value is [false](#).

Returns

[int](#)

The total number of models successfully written to the database.

Remarks

This method writes the provided models to the database in batches to optimize performance. The behavior of the write operation can be customized using the optional parameters to control whether specific column types (e.g., auto-increment, primary key, unique, or auto-generated date columns) are included in the operation.

WriteToDatabase(IRelmQuickContext, IRelmModel, int, bool, bool, bool, bool)

Writes the specified model to the database using the provided context and configuration options.

```
public static int WriteToDatabase(IRelmQuickContext relmQuickContext, IRelmModel relmModel,
int batchSize = 100, bool allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns =
false, bool allowUniqueColumns = false, bool allowAutoDateColumns = false)
```

Parameters

realmQuickContext [IRelmQuickContext](#)

The database context used to manage the connection and transaction for the operation.

realmModel [IRelmModel](#)

The model to be written to the database. This model must conform to the expected schema.

batchSize [int](#)

The number of records to process in a single batch. Defaults to 100. Must be a positive integer.

allowAutoIncrementColumns [bool](#)

A value indicating whether columns with auto-increment constraints are allowed to be written. If [true](#), auto-increment columns will be included in the operation; otherwise, they will be excluded.

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns are allowed to be written. If [true](#), primary key columns will be included in the operation; otherwise, they will be excluded.

allowUniqueColumns [bool](#)

A value indicating whether unique columns are allowed to be written. If [true](#), unique columns will be included in the operation; otherwise, they will be excluded.

allowAutoDateColumns [bool](#)

A value indicating whether columns with automatic date generation constraints are allowed to be written. If [true](#), auto-date columns will be included in the operation; otherwise, they will be excluded.

Returns

[int](#)

The number of records successfully written to the database.

Remarks

This method provides fine-grained control over which types of columns are included in the database write operation. Use the configuration options to tailor the behavior to your specific requirements.

WriteToDatabase(IRelmQuickContext, IEnumerable<IRelmModel>, int, bool, bool, bool, bool)

Writes a collection of Relm models to the database using the specified context and configuration options.

```
public static int WriteToDatabase(IRelmQuickContext relmQuickContext,
IEnumerable<IRelmModel> relmModels, int batchSize = 100, bool allowAutoIncrementColumns =
false, bool allowPrimaryKeyColumns = false, bool allowUniqueColumns = false, bool
allowAutoDateColumns = false)
```

Parameters

relmQuickContext [IRelmQuickContext](#)

The database context used to manage the connection and transaction for the operation.

relmModels [IEnumerable](#) <[IRelmModel](#)>

The collection of models to be written to the database. Each model represents a row to be inserted or updated.

batchSize [int](#)

The number of models to process in a single batch. Defaults to 100. Larger batch sizes may improve performance but require more memory.

allowAutoIncrementColumns [bool](#)

A value indicating whether columns marked as auto-increment are allowed to be written. Defaults to [false](#).

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns are allowed to be written. Defaults to [false](#).

allowUniqueColumns [bool](#)

A value indicating whether columns with unique constraints are allowed to be written. Defaults to [false](#).

allowAutoDateColumns [bool](#)

A value indicating whether columns with automatic date generation (e.g., timestamps) are allowed to be written. Defaults to [false](#).

Returns

[int](#)

The total number of rows successfully written to the database.

Remarks

This method provides fine-grained control over how data is written to the database by allowing the caller to specify whether certain types of columns (e.g., auto-increment, primary key, unique, or auto-date columns) are included in the operation. Use caution when enabling these options, as they may violate database constraints or lead to unexpected behavior.

Namespace SimpleRealm.Attributes

Classes

[RealmColumn](#)

Specifies metadata for a database column, including its name, size, constraints, and other properties.

[RealmDataLoader](#)

Specifies metadata for associating a data loader with a property, struct, or class.

[RealmDatabase](#)

Specifies that a class or struct represents a database entity and associates it with a database name.

[RealmDto](#)

Specifies that the associated property or struct is part of a Data Transfer Object (DTO) used for communication between application layers or services.

[RealmForeignKey](#)

Specifies a foreign key relationship for a property or struct in a data model.

[RealmKey](#)

Specifies that the associated property or struct is a key used for identifying or referencing entities.

[RealmTable](#)

Specifies that a class or struct represents a table in a relational database and provides the name of the table.

Class RealmColumn

Namespace: [SimpleRealm.Attributes](#)

Assembly: SimpleRealm.dll

Specifies metadata for a database column, including its name, size, constraints, and other properties.

```
[AttributeUsage(AttributeTargets.Struct|AttributeTargets.Property)]  
public sealed class RealmColumn : Attribute, _Attribute
```

Inheritance

[object](#)  ← [Attribute](#)  ← RealmColumn

Implements

[_Attribute](#) 

Inherited Members

[Attribute.GetCustomAttributes\(MemberInfo, Type\)](#)  ,
[Attribute.GetCustomAttributes\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(MemberInfo\)](#)  , [Attribute.GetCustomAttributes\(MemberInfo, bool\)](#)  ,
[Attribute.IsDefined\(MemberInfo, Type\)](#)  , [Attribute.IsDefined\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttribute\(MemberInfo, Type\)](#)  ,
[Attribute.GetCustomAttribute\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo\)](#)  , [Attribute.GetCustomAttributes\(ParameterInfo, Type\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo, bool\)](#)  , [Attribute.IsDefined\(ParameterInfo, Type\)](#)  ,
[Attribute.IsDefined\(ParameterInfo, Type, bool\)](#)  , [Attribute.GetCustomAttribute\(ParameterInfo, Type\)](#)  ,
[Attribute.GetCustomAttribute\(ParameterInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(Module, Type\)](#)  , [Attribute.GetCustomAttributes\(Module\)](#)  ,
[Attribute.GetCustomAttributes\(Module, bool\)](#)  , [Attribute.GetCustomAttributes\(Module, Type, bool\)](#)  ,
[Attribute.IsDefined\(Module, Type\)](#)  , [Attribute.IsDefined\(Module, Type, bool\)](#)  ,
[Attribute.GetCustomAttribute\(Module, Type\)](#)  , [Attribute.GetCustomAttribute\(Module, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, Type\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, Type, bool\)](#)  , [Attribute.GetCustomAttributes\(Assembly\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, bool\)](#)  , [Attribute.IsDefined\(Assembly, Type\)](#)  ,
[Attribute.IsDefined\(Assembly, Type, bool\)](#)  , [Attribute.GetCustomAttribute\(Assembly, Type\)](#)  ,
[Attribute.GetCustomAttribute\(Assembly, Type, bool\)](#)  , [Attribute.Equals\(object\)](#)  ,
[Attribute.GetHashCode\(\)](#)  , [Attribute.Match\(object\)](#)  , [Attribute.IsDefaultAttribute\(\)](#)  ,
[Attribute.TypeId](#)  , [object.ToString\(\)](#)  , [object.Equals\(object, object\)](#)  ,
[object.ReferenceEquals\(object, object\)](#)  , [object.GetType\(\)](#) 

Remarks

This attribute is used to annotate properties or structs that represent database columns. It provides detailed configuration options such as column name, size, nullability, uniqueness, default values, and indexing. The attribute can be applied to define primary keys, auto-incrementing columns, and virtual columns, among other features. When applied, the annotated property or struct is treated as a database column with the specified characteristics. This attribute is commonly used in object-relational mapping (ORM) scenarios to define the schema of a database table.

Constructors

`RelmColumn(string, int, int[], bool, bool, bool, bool, string, string, bool, bool, bool)`

Initializes a new instance of the [RelmColumn](#) class, representing a column definition with various configuration options for database schema design.

```
public RelmColumn(string columnName = null, int columnSize = -1, int[] compoundColumnSize = null, bool isNullable = true, bool primaryKey = false, bool autonumber = false, bool unique = false, string defaultValue = null, string index = null, bool indexDescending = false, bool allowDataTruncation = false, bool isVirtual = false)
```

Parameters

`columnName` [string](#)

The name of the column. If [null](#) or empty, the column will use the property's underscore name.

`columnSize` [int](#)

The size of the column, typically used for fixed-length data types (e.g., strings). A value of -1 indicates that the size is unspecified.

`compoundColumnSize` [int](#)[]

An array specifying the sizes of compound columns, if applicable. Can be [null](#) if the column is not part of a compound structure.

`isNullable` [bool](#)

A value indicating whether the column allows [null](#) values. The default is [true](#).

primaryKey [bool](#)

A value indicating whether the column is part of the primary key. The default is [false](#).

autonumber [bool](#)

A value indicating whether the column is an auto-incrementing identity column. The default is [false](#).

unique [bool](#)

A value indicating whether the column enforces uniqueness. The default is [false](#).

defaultValue [string](#)

The default value for the column, represented as a string. Can be [null](#) if no default value is specified.

index [string](#)

The name of the index associated with the column, if any. Can be [null](#) if the column is not indexed.

indexDescending [bool](#)

A value indicating whether the index on the column is sorted in descending order. The default is [false](#).

allowDataTruncation [bool](#)

A value indicating whether data truncation is allowed for this column. The default is [false](#).

isVirtual [bool](#)

A value indicating whether the column is a virtual column (i.e., its value is computed rather than stored). The default is [false](#).

Properties

AllowDataTruncation

Gets a value indicating whether data truncation is allowed during processing.

```
public bool AllowDataTruncation { get; }
```

Property Value

[bool](#)↗

Autonumber

Gets a value indicating whether the entity is configured to automatically generate unique identifiers.

```
public bool Autonumber { get; }
```

Property Value

[bool](#)↗

ColumnName

Gets the name of the database column associated with this instance. If not specified, the underscore version of the property or struct name is used as the column name.

```
public string ColumnName { get; }
```

Property Value

[string](#)↗

ColumnSize

Gets the size of the column, typically representing the maximum number of characters or bytes that the column can hold.

```
public int ColumnSize { get; }
```

Property Value

[int](#)↗

CompoundColumnSize

Gets the sizes of the compound columns, such as decimal.

```
public int[] CompoundColumnSize { get; }
```

Property Value

[int](#)  []

DefaultValue

Gets the default value associated with this column.

```
public string DefaultValue { get; }
```

Property Value

[string](#) 

Index

Gets the value indicating which index this property is attached to.

```
public string Index { get; }
```

Property Value

[string](#) 

IndexDescending

Gets a value indicating whether the index is sorted in descending order.

```
public bool IndexDescending { get; }
```

Property Value

[bool](#)

IsNullale

Gets a value indicating whether the associated entity or value can be null.

```
public bool IsNullale { get; }
```

Property Value

[bool](#)

PrimaryKey

Gets a value indicating whether this property is the primary key of the entity.

```
public bool PrimaryKey { get; }
```

Property Value

[bool](#)

Unique

Gets a value indicating whether the column can only hold unique values.

```
public bool Unique { get; }
```

Property Value

[bool](#)

Virtual

Gets a value indicating whether the object is virtual.

```
public bool Virtual { get; }
```

Property Value

[bool](#)

Class RealmDataLoader

Namespace: [SimpleRealm.Attributes](#)

Assembly: SimpleRealm.dll

Specifies metadata for associating a data loader with a property, struct, or class.

```
[AttributeUsage(AttributeTargets.Class|AttributeTargets.Struct|AttributeTargets.Property,  
AllowMultiple = true)]  
public class RealmDataLoader : Attribute, _Attribute
```

Inheritance

[object](#)  ← [Attribute](#)  ← RealmDataLoader

Implements

[_Attribute](#) 

Inherited Members

[Attribute.GetCustomAttributes\(MemberInfo, Type\)](#)  ,
[Attribute.GetCustomAttributes\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(MemberInfo\)](#)  , [Attribute.GetCustomAttributes\(MemberInfo, bool\)](#)  ,
[Attribute.IsDefined\(MemberInfo, Type\)](#)  , [Attribute.IsDefined\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttribute\(MemberInfo, Type\)](#)  ,
[Attribute.GetCustomAttribute\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo\)](#)  , [Attribute.GetCustomAttributes\(ParameterInfo, Type\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo, bool\)](#)  , [Attribute.IsDefined\(ParameterInfo, Type\)](#)  ,
[Attribute.IsDefined\(ParameterInfo, Type, bool\)](#)  , [Attribute.GetCustomAttribute\(ParameterInfo, Type\)](#)  ,
[Attribute.GetCustomAttribute\(ParameterInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(Module, Type\)](#)  , [Attribute.GetCustomAttributes\(Module\)](#)  ,
[Attribute.GetCustomAttributes\(Module, bool\)](#)  , [Attribute.GetCustomAttributes\(Module, Type, bool\)](#)  ,
[Attribute.IsDefined\(Module, Type\)](#)  , [Attribute.IsDefined\(Module, Type, bool\)](#)  ,
[Attribute.GetCustomAttribute\(Module, Type\)](#)  , [Attribute.GetCustomAttribute\(Module, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, Type\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, Type, bool\)](#)  , [Attribute.GetCustomAttributes\(Assembly\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, bool\)](#)  , [Attribute.IsDefined\(Assembly, Type\)](#)  ,
[Attribute.IsDefined\(Assembly, Type, bool\)](#)  , [Attribute.GetCustomAttribute\(Assembly, Type\)](#)  ,
[Attribute.GetCustomAttribute\(Assembly, Type, bool\)](#)  , [Attribute.Equals\(object\)](#)  ,
[Attribute.GetHashCode\(\)](#)  , [Attribute.Match\(object\)](#)  , [Attribute.IsDefaultAttribute\(\)](#)  ,

[Attribute.TypeId](#) , [object.ToString\(\)](#) , [object.Equals\(object, object\)](#) ,
[object.ReferenceEquals\(object, object\)](#) , [object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#)

Remarks

This attribute is used to define the type of a data loader and the key fields that the loader uses to identify or retrieve data. It can be applied to properties, structs, or classes, and supports multiple usages on the same target.

Constructors

RelmDataLoader(Type)

Initializes a new instance of the [RelmDataLoader](#) class with the specified loader type.

```
public RelmDataLoader(Type loaderType)
```

Parameters

loaderType [Type](#)

The type of the loader to be used. This parameter cannot be [null](#).

RelmDataLoader(Type, string)

Initializes a new instance of the [RelmDataLoader](#) class with the specified loader type and key field.

```
public RelmDataLoader(Type loaderType, string keyField)
```

Parameters

loaderType [Type](#)

The type of the loader used to process data. This parameter cannot be [null](#).

keyField [string](#)

The name of the key field used to identify data. If not [null](#), it will be added as the sole key field.

Remarks

If `keyField` is [null](#), the [KeyFields](#) property will remain uninitialized.

RelmDataLoader(Type, string[])

Initializes a new instance of the [RelmDataLoader](#) class with the specified loader type and key fields.

```
public RelmDataLoader(Type loaderType, string[] keyFields)
```

Parameters

`loaderType` [Type](#)

The type of the loader used to process the data. This must be a valid [Type](#) representing the loader implementation.

`keyFields` [string](#)[]

An array of strings representing the key fields used to identify or process the data. This array cannot be null and must contain at least one element.

Properties

KeyFields

Gets or sets the collection of key field names used to uniquely identify an entity.

```
public string[] KeyFields { get; set; }
```

Property Value

[string](#)[]

Remarks

Key fields are typically used to identify unique records in a dataset or entity. Ensure that the field names provided correspond to valid and unique identifiers within the context of the entity.

LoaderType

Gets or sets the type of the loader used to process data or resources.

```
public Type LoaderType { get; set; }
```

Property Value

[Type](#)

Remarks

The specified type is expected to define the behavior for loading data or resources. Ensure that the type is compatible with the intended usage context.

Class RealmDatabase

Namespace: [SimpleRealm.Attributes](#)

Assembly: SimpleRealm.dll

Specifies that a class or struct represents a database entity and associates it with a database name.

```
[AttributeUsage(AttributeTargets.Class|AttributeTargets.Struct)]  
public sealed class RealmDatabase : Attribute, _Attribute
```

Inheritance

[object](#)  ← [Attribute](#)  ← RealmDatabase

Implements

[_Attribute](#) 

Inherited Members

[Attribute.GetCustomAttributes\(MemberInfo, Type\)](#)  ,
[Attribute.GetCustomAttributes\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(MemberInfo\)](#)  , [Attribute.GetCustomAttributes\(MemberInfo, bool\)](#)  ,
[Attribute.IsDefined\(MemberInfo, Type\)](#)  , [Attribute.IsDefined\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttribute\(MemberInfo, Type\)](#)  ,
[Attribute.GetCustomAttribute\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo\)](#)  , [Attribute.GetCustomAttributes\(ParameterInfo, Type\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo, bool\)](#)  , [Attribute.IsDefined\(ParameterInfo, Type\)](#)  ,
[Attribute.IsDefined\(ParameterInfo, Type, bool\)](#)  , [Attribute.GetCustomAttribute\(ParameterInfo, Type\)](#)  ,
[Attribute.GetCustomAttribute\(ParameterInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(Module, Type\)](#)  , [Attribute.GetCustomAttributes\(Module\)](#)  ,
[Attribute.GetCustomAttributes\(Module, bool\)](#)  , [Attribute.GetCustomAttributes\(Module, Type, bool\)](#)  ,
[Attribute.IsDefined\(Module, Type\)](#)  , [Attribute.IsDefined\(Module, Type, bool\)](#)  ,
[Attribute.GetCustomAttribute\(Module, Type\)](#)  , [Attribute.GetCustomAttribute\(Module, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, Type\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, Type, bool\)](#)  , [Attribute.GetCustomAttributes\(Assembly\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, bool\)](#)  , [Attribute.IsDefined\(Assembly, Type\)](#)  ,
[Attribute.IsDefined\(Assembly, Type, bool\)](#)  , [Attribute.GetCustomAttribute\(Assembly, Type\)](#)  ,
[Attribute.GetCustomAttribute\(Assembly, Type, bool\)](#)  , [Attribute.Equals\(object\)](#)  ,
[Attribute.GetHashCode\(\)](#)  , [Attribute.Match\(object\)](#)  , [Attribute.IsDefaultAttribute\(\)](#)  ,
[Attribute.TypeId](#)  , [object.ToString\(\)](#)  , [object.Equals\(object, object\)](#)  ,
[object.ReferenceEquals\(object, object\)](#)  , [object.GetType\(\)](#) 

Remarks

This attribute is used to annotate classes or structs that correspond to database entities. The [Database Name](#) property specifies the name of the database associated with the entity.

Constructors

RealmDatabase(string)

Initializes a new instance of the [RealmDatabase](#) class with the specified database name.

```
public RealmDatabase(string databaseName)
```

Parameters

databaseName [string](#) 

The name of the database. This value cannot be null, empty, or consist only of white-space characters.

Exceptions

[ArgumentNullException](#) 

Thrown if **databaseName** is null, empty, or consists only of white-space characters.

Properties

DatabaseName

Gets or sets the name of the database.

```
public string DatabaseName { get; }
```

Property Value

[string](#) 

Class RelmDto

Namespace: [SimpleRelm.Attributes](#)

Assembly: SimpleRelm.dll

Specifies that the associated property or struct is part of a Data Transfer Object (DTO) used for communication between application layers or services.

```
[AttributeUsage(AttributeTargets.Struct|AttributeTargets.Property)]  
public sealed class RelmDto : Attribute, _Attribute
```

Inheritance

[object](#)  ← [Attribute](#)  ← RelmDto

Implements

[_Attribute](#) 

Inherited Members

[Attribute.GetCustomAttributes\(MemberInfo, Type\)](#)  ,
[Attribute.GetCustomAttributes\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(MemberInfo\)](#)  , [Attribute.GetCustomAttributes\(MemberInfo, bool\)](#)  ,
[Attribute.IsDefined\(MemberInfo, Type\)](#)  , [Attribute.IsDefined\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttribute\(MemberInfo, Type\)](#)  ,
[Attribute.GetCustomAttribute\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo\)](#)  , [Attribute.GetCustomAttributes\(ParameterInfo, Type\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo, bool\)](#)  , [Attribute.IsDefined\(ParameterInfo, Type\)](#)  ,
[Attribute.IsDefined\(ParameterInfo, Type, bool\)](#)  , [Attribute.GetCustomAttribute\(ParameterInfo, Type\)](#)  ,
[Attribute.GetCustomAttribute\(ParameterInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(Module, Type\)](#)  , [Attribute.GetCustomAttributes\(Module\)](#)  ,
[Attribute.GetCustomAttributes\(Module, bool\)](#)  , [Attribute.GetCustomAttributes\(Module, Type, bool\)](#)  ,
[Attribute.IsDefined\(Module, Type\)](#)  , [Attribute.IsDefined\(Module, Type, bool\)](#)  ,
[Attribute.GetCustomAttribute\(Module, Type\)](#)  , [Attribute.GetCustomAttribute\(Module, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, Type\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, Type, bool\)](#)  , [Attribute.GetCustomAttributes\(Assembly\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, bool\)](#)  , [Attribute.IsDefined\(Assembly, Type\)](#)  ,
[Attribute.IsDefined\(Assembly, Type, bool\)](#)  , [Attribute.GetCustomAttribute\(Assembly, Type\)](#)  ,
[Attribute.GetCustomAttribute\(Assembly, Type, bool\)](#)  , [Attribute.Equals\(object\)](#)  ,
[Attribute.GetHashCode\(\)](#)  , [Attribute.Match\(object\)](#)  , [Attribute.IsDefaultAttribute\(\)](#)  ,

[Attribute.TypeId](#) , [object.ToString\(\)](#) , [object.Equals\(object, object\)](#) ,
[object.ReferenceEquals\(object, object\)](#) , [object.GetType\(\)](#)

Remarks

This attribute is intended to annotate properties or structs that are part of a DTO, providing metadata for tools or frameworks that process or validate DTOs. It can be applied to properties or structs to indicate their role in data transfer scenarios.

Class RealmForeignKey

Namespace: [SimpleRealm.Attributes](#)

Assembly: SimpleRealm.dll

Specifies a foreign key relationship for a property or struct in a data model.

```
[AttributeUsage(AttributeTargets.Struct|AttributeTargets.Property)]  
public sealed class RealmForeignKey : Attribute, _Attribute
```

Inheritance

[object](#)  ← [Attribute](#)  ← RealmForeignKey

Implements

[_Attribute](#) 

Inherited Members

[Attribute.GetCustomAttributes\(MemberInfo, Type\)](#)  ,
[Attribute.GetCustomAttributes\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(MemberInfo\)](#)  , [Attribute.GetCustomAttributes\(MemberInfo, bool\)](#)  ,
[Attribute.IsDefined\(MemberInfo, Type\)](#)  , [Attribute.IsDefined\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttribute\(MemberInfo, Type\)](#)  ,
[Attribute.GetCustomAttribute\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo\)](#)  , [Attribute.GetCustomAttributes\(ParameterInfo, Type\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo, bool\)](#)  , [Attribute.IsDefined\(ParameterInfo, Type\)](#)  ,
[Attribute.IsDefined\(ParameterInfo, Type, bool\)](#)  , [Attribute.GetCustomAttribute\(ParameterInfo, Type\)](#)  ,
[Attribute.GetCustomAttribute\(ParameterInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(Module, Type\)](#)  , [Attribute.GetCustomAttributes\(Module\)](#)  ,
[Attribute.GetCustomAttributes\(Module, bool\)](#)  , [Attribute.GetCustomAttributes\(Module, Type, bool\)](#)  ,
[Attribute.IsDefined\(Module, Type\)](#)  , [Attribute.IsDefined\(Module, Type, bool\)](#)  ,
[Attribute.GetCustomAttribute\(Module, Type\)](#)  , [Attribute.GetCustomAttribute\(Module, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, Type\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, Type, bool\)](#)  , [Attribute.GetCustomAttributes\(Assembly\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, bool\)](#)  , [Attribute.IsDefined\(Assembly, Type\)](#)  ,
[Attribute.IsDefined\(Assembly, Type, bool\)](#)  , [Attribute.GetCustomAttribute\(Assembly, Type\)](#)  ,
[Attribute.GetCustomAttribute\(Assembly, Type, bool\)](#)  , [Attribute.Equals\(object\)](#)  ,
[Attribute.GetHashCode\(\)](#)  , [Attribute.Match\(object\)](#)  , [Attribute.IsDefaultAttribute\(\)](#)  ,
[Attribute.TypeId](#)  , [object.ToString\(\)](#)  , [object.Equals\(object, object\)](#)  ,
[object.ReferenceEquals\(object, object\)](#)  , [object.GetType\(\)](#) 

Remarks

This attribute is used to define the mapping between local keys and foreign keys in a relational context. It can also specify an optional ordering for the related data. The attribute can be applied to properties or structs, and supports both single and multiple key mappings.

Constructors

RelmForeignKey(string, string, string)

Initializes a new instance of the [RelmForeignKey](#) class with optional foreign key, local key, and order-by values.

```
public RelmForeignKey(string foreignKey = null, string localKey = null, string orderBy = null)
```

Parameters

foreignKey [string](#) 

An optional foreign key used to establish the relationship. If provided, it will be stored as a single-element array in the [ForeignKeys](#) property.

localKey [string](#) 

An optional local key used to establish the relationship. If provided, it will be stored as a single-element array in the [LocalKeys](#) property.

orderBy [string](#) 

An optional order-by clause used to define the sorting of the relationship. If provided, it will be stored as a single-element array in the [OrderBy](#) property.

RelmForeignKey(string[], string[], string[])

Initializes a new instance of the [RelmForeignKey](#) class, specifying the foreign keys, local keys, and optional ordering criteria.

```
public RelmForeignKey(string[] foreignKeys = null, string[] localKeys = null, string[]
```

```
orderBy = null)
```

Parameters

foreignKeys [string](#)[]

An array of strings representing the foreign key columns in the related table. Can be [null](#) if no foreign keys are specified.

localKeys [string](#)[]

An array of strings representing the local key columns in the current table that map to the foreign keys. Can be [null](#) if no local keys are specified.

orderBy [string](#)[]

An array of strings specifying the ordering criteria for the related data. Each string represents a column name, optionally followed by a direction (e.g., "ColumnName ASC" or "ColumnName DESC"). Can be [null](#) if no ordering is required.

Properties

ForeignKeys

Gets the collection of foreign key names associated with the entity.

```
public string[] ForeignKeys { get; }
```

Property Value

[string](#)[]

LocalKeys

Gets the collection of local keys associated with the entity.

```
public string[] LocalKeys { get; }
```

Property Value

[string](#)  []

OrderBy

Gets the list of fields used to determine the order of items.

```
public string[] OrderBy { get; }
```

Property Value

[string](#)  []

Class RelmKey

Namespace: [SimpleRelm.Attributes](#)

Assembly: SimpleRelm.dll

Specifies that the associated property or struct is a key used for identifying or referencing entities.

```
[AttributeUsage(AttributeTargets.Struct|AttributeTargets.Property)]  
public sealed class RelmKey : Attribute, _Attribute
```

Inheritance

[object](#)  ← [Attribute](#)  ← RelmKey

Implements

[_Attribute](#) 

Inherited Members

[Attribute.GetCustomAttributes\(MemberInfo, Type\)](#)  ,
[Attribute.GetCustomAttributes\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(MemberInfo\)](#)  , [Attribute.GetCustomAttributes\(MemberInfo, bool\)](#)  ,
[Attribute.IsDefined\(MemberInfo, Type\)](#)  , [Attribute.IsDefined\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttribute\(MemberInfo, Type\)](#)  ,
[Attribute.GetCustomAttribute\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo\)](#)  , [Attribute.GetCustomAttributes\(ParameterInfo, Type\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo, bool\)](#)  , [Attribute.IsDefined\(ParameterInfo, Type\)](#)  ,
[Attribute.IsDefined\(ParameterInfo, Type, bool\)](#)  , [Attribute.GetCustomAttribute\(ParameterInfo, Type\)](#)  ,
[Attribute.GetCustomAttribute\(ParameterInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(Module, Type\)](#)  , [Attribute.GetCustomAttributes\(Module\)](#)  ,
[Attribute.GetCustomAttributes\(Module, bool\)](#)  , [Attribute.GetCustomAttributes\(Module, Type, bool\)](#)  ,
[Attribute.IsDefined\(Module, Type\)](#)  , [Attribute.IsDefined\(Module, Type, bool\)](#)  ,
[Attribute.GetCustomAttribute\(Module, Type\)](#)  , [Attribute.GetCustomAttribute\(Module, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, Type\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, Type, bool\)](#)  , [Attribute.GetCustomAttributes\(Assembly\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, bool\)](#)  , [Attribute.IsDefined\(Assembly, Type\)](#)  ,
[Attribute.IsDefined\(Assembly, Type, bool\)](#)  , [Attribute.GetCustomAttribute\(Assembly, Type\)](#)  ,
[Attribute.GetCustomAttribute\(Assembly, Type, bool\)](#)  , [Attribute.Equals\(object\)](#)  ,
[Attribute.GetHashCode\(\)](#)  , [Attribute.Match\(object\)](#)  , [Attribute.IsDefaultAttribute\(\)](#)  ,
[Attribute.TypeId](#)  , [object.ToString\(\)](#)  , [object.Equals\(object, object\)](#)  ,
[object.ReferenceEquals\(object, object\)](#)  , [object.GetType\(\)](#) 

Remarks

This attribute can be applied to properties or structs to indicate their role as a key in a relational or entity-based context. It is primarily used for metadata purposes and does not enforce any behavior at runtime.

Class RelmTable

Namespace: [SimpleRelm.Attributes](#)

Assembly: SimpleRelm.dll

Specifies that a class or struct represents a table in a relational database and provides the name of the table.

```
[AttributeUsage(AttributeTargets.Class|AttributeTargets.Struct)]  
public class RelmTable : Attribute, _Attribute
```

Inheritance

[object](#)  ← [Attribute](#)  ← RelmTable

Implements

[_Attribute](#) 

Inherited Members

[Attribute.GetCustomAttributes\(MemberInfo, Type\)](#)  ,
[Attribute.GetCustomAttributes\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(MemberInfo\)](#)  , [Attribute.GetCustomAttributes\(MemberInfo, bool\)](#)  ,
[Attribute.IsDefined\(MemberInfo, Type\)](#)  , [Attribute.IsDefined\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttribute\(MemberInfo, Type\)](#)  ,
[Attribute.GetCustomAttribute\(MemberInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo\)](#)  , [Attribute.GetCustomAttributes\(ParameterInfo, Type\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(ParameterInfo, bool\)](#)  , [Attribute.IsDefined\(ParameterInfo, Type\)](#)  ,
[Attribute.IsDefined\(ParameterInfo, Type, bool\)](#)  , [Attribute.GetCustomAttribute\(ParameterInfo, Type\)](#)  ,
[Attribute.GetCustomAttribute\(ParameterInfo, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(Module, Type\)](#)  , [Attribute.GetCustomAttributes\(Module\)](#)  ,
[Attribute.GetCustomAttributes\(Module, bool\)](#)  , [Attribute.GetCustomAttributes\(Module, Type, bool\)](#)  ,
[Attribute.IsDefined\(Module, Type\)](#)  , [Attribute.IsDefined\(Module, Type, bool\)](#)  ,
[Attribute.GetCustomAttribute\(Module, Type\)](#)  , [Attribute.GetCustomAttribute\(Module, Type, bool\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, Type\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, Type, bool\)](#)  , [Attribute.GetCustomAttributes\(Assembly\)](#)  ,
[Attribute.GetCustomAttributes\(Assembly, bool\)](#)  , [Attribute.IsDefined\(Assembly, Type\)](#)  ,
[Attribute.IsDefined\(Assembly, Type, bool\)](#)  , [Attribute.GetCustomAttribute\(Assembly, Type\)](#)  ,
[Attribute.GetCustomAttribute\(Assembly, Type, bool\)](#)  , [Attribute.Equals\(object\)](#)  ,
[Attribute.GetHashCode\(\)](#)  , [Attribute.Match\(object\)](#)  , [Attribute.IsDefaultAttribute\(\)](#)  ,

[Attribute.TypeId](#) , [object.ToString\(\)](#) , [object.Equals\(object, object\)](#) ,
[object.ReferenceEquals\(object, object\)](#) , [object.GetType\(\)](#) , [object.MemberwiseClone\(\)](#)

Remarks

This attribute is used to associate a class or struct with a specific table name in a relational database. The table name is specified via the [TableName](#) property.

Constructors

RelmTable(string)

Initializes a new instance of the [RelmTable](#) class with the specified table name.

```
public RelmTable(string tableName)
```

Parameters

tableName [string](#)

The name of the table. This value cannot be null, empty, or consist only of white-space characters.

Exceptions

[ArgumentNullException](#)

Thrown if **tableName** is null, empty, or consists only of white-space characters.

Properties

TableName

Gets or sets the name of the database table associated with this instance.

```
public string TableName { get; }
```

Property Value

[string](#)

Namespace SimpleRealm.Enums

Classes

[Commands](#)

Represents a collection of commands that can be used to define and manipulate query operations.

[Triggers](#)

Represents a collection of database trigger types that define actions to be executed before or after specific data modification operations.

Enums

[Commands.Command](#)

Represents the set of commands that can be used to define and manipulate query operations.

[Triggers.TriggerTypes](#)

Specifies the types of triggers that can be executed in response to database operations.

Class Commands

Namespace: [SimpleRealm.Enums](#)

Assembly: SimpleRealm.dll

Represents a collection of commands that can be used to define and manipulate query operations.

```
public class Commands
```

Inheritance

[object](#)  ← Commands

Inherited Members

[object.ToString\(\)](#)  , [object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  ,
[object.ReferenceEquals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  , [object.GetType\(\)](#)  ,
[object.MemberwiseClone\(\)](#) 

Remarks

The [Commands.Command](#) enumeration provides a set of predefined commands commonly used in query construction, such as filtering, ordering, grouping, and limiting results. These commands can be used to specify the behavior of a query in a structured and consistent manner.

Enum Commands.Command

Namespace: [SimpleRealm.Enums](#)

Assembly: SimpleRealm.dll

Represents the set of commands that can be used to define and manipulate query operations.

```
public enum Commands.Command
```

Fields

Count = 9

Gets the number of elements contained in the collection.

DistinctBy = 8

Returns a collection of distinct elements from the input sequence based on a specified key selector.

This method uses deferred execution. The distinctness of elements is determined by comparing the keys returned by **keySelector**. The order of the elements in the returned collection is preserved based on their first occurrence in the source sequence.

GroupBy = 6

Groups the elements of a sequence according to a specified key selector function.

This method uses deferred execution. The query is not executed until the resulting collection is enumerated.

Limit = 7

Gets or sets the maximum allowable limit result for the operation.

OrderBy = 2

Sorts the elements of a sequence in ascending order according to a specified key.

This method performs a stable sort, meaning that if two elements have the same key, their original order in the sequence is preserved. To perform a descending sort, use the [OrderByDescending<TSource, TKey>\(IEnumerable<TSource>, Func<TSource, TKey>\)](#) method.

OrderByDescending = 3

Sorts the elements of a sequence in descending order according to a specified key.

This method performs a stable sort; that is, if two elements have the same key, their original order is preserved in the returned sequence. To perform subsequent ordering operations, use `IOrderedEnumerable<TElement>.ThenByDescending`.

Reference = 1

Represents a reference to an object or entity.

This class is typically used to store and manage references to other objects or entities. It may include additional metadata or functionality depending on the specific implementation.

Set = 4

Sets the value of the specified property or field.

This method allows dynamic assignment of values to properties or fields by name. Ensure that the property or field exists and is accessible in the current context.

SetPostfix = 5

Sets the postfix string that will be appended to the output of the operation.

Where = 0

Filters a sequence of values based on a predicate.

This method uses deferred execution. The query represented by this method is not executed until the resulting sequence is enumerated.

Remarks

This enumeration provides a collection of commands commonly used in query-building scenarios, such as filtering, sorting, grouping, and limiting results. Each command corresponds to a specific operation that can be applied to a query.

Class Triggers

Namespace: [SimpleRealm.Enums](#)

Assembly: SimpleRealm.dll

Represents a collection of database trigger types that define actions to be executed before or after specific data modification operations.

```
public class Triggers
```

Inheritance

[object](#)  ← Triggers

Inherited Members

[object.ToString\(\)](#)  , [object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  ,
[object.ReferenceEquals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  , [object.GetType\(\)](#)  ,
[object.MemberwiseClone\(\)](#) 

Remarks

The [Triggers.TriggerTypes](#) enumeration provides values for common database triggers, including those that occur before or after insert, update, or delete operations. These trigger types can be used to specify the timing and context of database actions.

Enum Triggers.TriggerTypes

Namespace: [SimpleRealm.Enums](#)

Assembly: SimpleRealm.dll

Specifies the types of triggers that can be executed in response to database operations.

```
public enum Triggers.TriggerTypes
```

Fields

AfterDelete = 5

Occurs after an item has been deleted.

This event is triggered once the deletion process is completed successfully. Subscribers can use this event to perform any post-deletion operations, such as cleanup or logging.

AfterInsert = 1

Occurs after an item has been inserted into the collection or data store.

This event allows subscribers to perform additional actions or processing after an item has been successfully inserted.

AfterUpdate = 3

Occurs after an update operation has been completed.

This event is triggered once the update process finishes successfully. Subscribers can use this event to perform any post-update actions, such as refreshing data or logging.

BeforeDelete = 4

Occurs before an item is deleted.

This event allows subscribers to perform any necessary actions or validations prior to the deletion of the item. If the operation should be canceled, subscribers can throw an exception or use a specific cancellation mechanism provided by the implementation.

BeforeInsert = 0

Occurs before an item is inserted into the collection.

This event allows subscribers to perform custom logic or validation before an item is added to the collection. If the operation should be canceled, the event handler can throw an exception or modify the state as needed.

BeforeUpdate = 2

Occurs before an update operation is performed.

This event allows subscribers to execute custom logic or validate data prior to the update operation. If the operation should be canceled, subscribers can throw an exception or modify the state as needed.

Remarks

This enumeration defines trigger types that correspond to specific stages of database operations, such as inserts, updates, and deletes. Triggers can be executed either before or after the operation.

Namespace SimpleReIm.Extensions

Classes

[DbContextExtensions](#)

Provides extension methods for configuring and interacting with database contexts.

[ListExtensions](#)

Provides a set of extension methods for performing database operations, loading related data, and manipulating collections in the context of relational models.

[ModelExtensions](#)

Class DbContextExtensions

Namespace: [SimpleRealm.Extensions](#)

Assembly: SimpleRealm.dll

Provides extension methods for configuring and interacting with database contexts.

```
public static class DbContextExtensions
```

Inheritance

[object](#)  ← DbContextExtensions

Inherited Members

[object.ToString\(\)](#)  , [object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  ,
[object.ReferenceEquals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  , [object.GetType\(\)](#)  ,
[object.MemberwiseClone\(\)](#) 

Remarks

This class contains utility methods that extend the functionality of database contexts, such as setting session-specific database parameters. These methods are designed to simplify common database operations and enhance developer productivity when working with database contexts.

Methods

SetLockWaitTimeout(IRelmContext, int)

Sets the InnoDB lock wait timeout for the current database session.

```
public static void SetLockWaitTimeout(this IRelmContext context, int seconds = 300)
```

Parameters

context [IRelmContext](#)

The database context. This parameter cannot be [null](#) .

seconds [int](#) 

The lock wait timeout, in seconds. The default value is 300 seconds (5 minutes).

Remarks

This method executes a SQL command to set the InnoDB lock wait timeout for the current session. The timeout determines how long a transaction will wait for a lock before timing out.

Exceptions

[ArgumentNullException](#) 

Thrown if `context` is [null](#) .

Class ListExtensions

Namespace: [SimpleReIm.Extensions](#)

Assembly: SimpleReIm.dll

Provides a set of extension methods for performing database operations, loading related data, and manipulating collections in the context of relational models.

```
public static class ListExtensions
```

Inheritance

[object](#) ← ListExtensions

Inherited Members

[object.ToString\(\)](#), [object.Equals\(object\)](#), [object.Equals\(object, object\)](#), [object.ReferenceEquals\(object, object\)](#), [object.GetHashCode\(\)](#), [object.GetType\(\)](#), [object.MemberwiseClone\(\)](#)

Remarks

The [ListExtensions](#) class includes methods for bulk writing data to a database, loading foreign key fields, flattening hierarchical data structures, generating DTOs, and retrieving dictionary entries. These methods are designed to work with relational models that implement the [IReImModel](#) interface and are optimized for scenarios involving database interactions and data transformation. Many methods in this class support advanced customization through optional parameters, such as specifying table names, batch sizes, and constraints for foreign key loading. Additionally, the methods are designed to be used with dependency injection and context-based database operations.

Methods

FlattenTreeObject<T>(IEnumerable<T>, Func<T, ICollection<T>>)

Flattens a hierarchical structure of objects into a single collection.

```
public static ICollection<T> FlattenTreeObject<T>(this IEnumerable<T> enumerableList,  
Func<T, ICollection<T>> getChildrenFunction)
```

Parameters

enumerableList [IEnumerable](#) <T>

The top-level collection of objects to flatten.

getChildrenFunction [Func](#) <T, [ICollection](#) <T>>

A function that retrieves the child objects of a given object. The function should return an [ICollection<T>](#) of child objects, or [null](#) if there are no children.

Returns

[ICollection](#) <T>

A flattened [ICollection<T>](#) containing all objects in the hierarchy, including the top-level objects and their descendants.

Type Parameters

T

The type of the objects in the hierarchy.

Remarks

This method recursively traverses the hierarchy defined by the **getChildrenFunction** and combines all objects into a single collection. If an object has no children, it is included as-is.

GenerateDTO<T>(IEnumerable<T>, ICollection<string>, ICollection<string>, string, Func<IRelmModel, Dictionary<string, object>>)

Generates a collection of dynamic objects (DTOs) from the specified collection of base objects, including or excluding specific properties as needed.

```
public static ICollection<dynamic> GenerateDTO<T>(this IEnumerable<T> baseObjects,
ICollection<string> includeProperties = null, ICollection<string> excludeProperties = null,
string sourceObjectName = null, Func<IRelmModel, Dictionary<string, object>>
getAdditionalObjectProperties = null) where T : IRelmModel
```

Parameters

baseObjects [IEnumerable](#) <T>

The collection of base objects to generate DTOs from. This parameter cannot be [null](#).

includeProperties [ICollection](#) <[string](#)>

An optional collection of property names to include in the generated DTOs. If [null](#), all properties are included by default unless explicitly excluded.

excludeProperties [ICollection](#) <[string](#)>

An optional collection of property names to exclude from the generated DTOs. If [null](#), no properties are excluded unless explicitly specified in **includeProperties**.

sourceObjectName [string](#)

An optional name of the source object to include in the DTOs for identification purposes. If [null](#), the source object name is not included.

getAdditionalObjectProperties [Func](#) <[IRelmModel](#), [Dictionary](#) <[string](#), [object](#)>>

An optional function that takes an [IRelmModel](#) object and returns a dictionary of additional properties to include in the generated DTOs. If [null](#), no additional properties are added.

Returns

[ICollection](#) <dynamic>

A collection of dynamic objects (DTOs) generated from the specified base objects. Each DTO includes the properties specified in **includeProperties** and excludes those in **excludeProperties**, along with any additional properties provided by **getAdditionalObjectProperties**.

Type Parameters

T

The type of the base objects, which must implement the [IRelmModel](#) interface.

Remarks

This method is an extension method for collections of objects implementing the [IRelmModel](#) interface. It allows for flexible generation of DTOs by specifying properties to include or exclude, and by adding custom properties through the **getAdditionalObjectProperties** function.

GetEntry<TKey, TValue>(IDictionary<TKey, TValue>, TKey)

Retrieves the key-value pair associated with the specified key in the dictionary.

```
public static KeyValuePair<TKey, TValue> GetEntry<TKey, TValue>(this IDictionary<TKey, TValue> dictionary, TKey key)
```

Parameters

dictionary [IDictionary](#)<TKey, TValue>

The dictionary from which to retrieve the key-value pair. Cannot be [null](#).

key TKey

The key whose associated key-value pair is to be retrieved. Must exist in the dictionary.

Returns

[KeyValuePair](#)<TKey, TValue>

A [KeyValuePair<TKey, TValue>](#) containing the specified key and its associated value.

Type Parameters

TKey

The type of the keys in the dictionary.

TValue

The type of the values in the dictionary.

LoadDataLoaderField<T, R>(ICollection<T>, IRealmContext, Expression<Func<T, R>>)

Loads and initializes a specific field for a collection of models using a data loader.

```
public static ICollection<T> LoadDataLoaderField<T, R>(this ICollection<T> modelData, IRealmContext realmContext, Expression<Func<T, R>> predicate) where T : IRealmModel, new()
```

Parameters

modelData [ICollection](#)<T>

The collection of models for which the field will be loaded. Cannot be [null](#).

realmContext [IRelmContext](#)

The context used to access the data loader. Cannot be [null](#).

predicate [Expression](#)<[Func](#)<T, R>>

An expression specifying the field to be loaded. Cannot be [null](#).

Returns

[ICollection](#)<T>

The original collection of models with the specified field loaded.

Type Parameters

T

The type of the model in the collection. Must implement [IRelmModel](#).

R

The type of the field to be loaded.

Remarks

This method uses a data loader to populate the specified field for each model in the collection. The field to be loaded is determined by the provided **predicate** expression.

LoadDataLoaderField<T, R>(ICollection<T>, IRelmQuickContext, Expression<Func<T, R>>)

Loads and populates a specified field for a collection of models using a data loader.

```
public static ICollection<T> LoadDataLoaderField<T, R>(this ICollection<T> modelData,
IRelmQuickContext realmQuickContext, Expression<Func<T, R>> predicate) where T :
IRelmModel, new()
```


Parameters

modelData [ICollection](#)<T>

The collection of models for which the field will be loaded.

realmQuickContext [IRelmQuickContext](#)

The context used to facilitate data loading operations.

predicate [Expression](#)<[Func](#)<T, R>>

An expression specifying the field to be loaded for each model in the collection.

Returns

[ICollection](#)<T>

The original collection of models with the specified field loaded.

Type Parameters

T

The type of the model in the collection. Must implement [IRelmModel](#).

R

The type of the field to be loaded.

Remarks

This method uses a data loader to populate the specified field for each model in the collection. The **predicate** parameter determines which field is loaded.

LoadDataLoaderField<T, R>(ICollection<T>, RelmContextOptionsBuilder, Expression<Func<T, R>>)

Loads and populates a specified field for a collection of models using a data loader.

```
public static ICollection<T> LoadDataLoaderField<T, R>(this ICollection<T> modelData,
    RelmContextOptionsBuilder relmContextOptionsBuilder, Expression<Func<T, R>> predicate) where
    T : IRelmModel, new()
```

Parameters

modelData [ICollection](#)<T>

The collection of models to be updated with the loaded field data.

realmContextOptionsBuilder [RealmContextOptionsBuilder](#)

The options builder used to configure the database context for loading the field.

predicate [Expression](#)<[Func](#)<T, R>>

An expression specifying the field to be loaded for each model in the collection.

Returns

[ICollection](#)<T>

The updated collection of models with the specified field populated.

Type Parameters

T

The type of the model in the collection. Must implement [IRelmModel](#) and have a parameterless constructor.

R

The type of the field to be loaded, as specified by the predicate.

Remarks

This method uses a data loader to populate the specified field in the provided collection of models. Ensure that the **realmContextOptionsBuilder** is properly configured to access the required data source.

LoadForeignKeyField<T, R>(ICollection<T>, IRealmContext, Expression<Func<T, ICollection<R>>>)

Loads and populates a foreign key collection field for a collection of models.

```
public static ICollection<T> LoadForeignKeyField<T, R>(this ICollection<T> modelData,
    IRealmContext realmContext, Expression<Func<T, ICollection<R>>> predicate) where T :
```

`IRealmModel, new() where R : IRealmModel, new()`

Parameters

modelData [ICollection](#) <T>

The collection of primary models for which the foreign key field will be loaded.

realmContext [IRelContext](#)

The context used to access the data source and resolve the foreign key relationships.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the foreign key collection property to load for each model in **modelData**.

Returns

[ICollection](#) <T>

The original collection of primary models with the specified foreign key field populated for each model.

Type Parameters

T

The type of the primary model in the collection. Must implement [IRelModel](#).

R

The type of the related model in the foreign key collection. Must implement [IRelModel](#).

Remarks

This method uses the provided **realmContext** to resolve and populate the foreign key collection specified by the **predicate** for each model in the **modelData** collection.

`LoadForeignKeyField<T, R>(ICollection<T>, IRelContext, Expression<Func<T, ICollection<R>>>, Expression<Func<R, object>>)`

Loads and populates a foreign key collection field for a collection of models.

```
public static ICollection<T> LoadForeignKeyField<T, R>(this ICollection<T> modelData,
IRelmContext relmContext, Expression<Func<T, ICollection<R>>> predicate, Expression<Func<R,
object>> additionalConstraints) where T : IRelmModel, new() where R : IRelmModel, new()
```

Parameters

modelData [ICollection](#) <T>

The collection of primary models for which the foreign key field will be loaded.

relmContext [IRelmContext](#)

The context used to access the data source and resolve the foreign key relationships.

predicate [Expression](#) <Func <T, ICollection <R>>>

An expression specifying the foreign key field to populate in the primary model.

additionalConstraints [Expression](#) <Func <R, object>>

An optional expression specifying additional constraints to apply when loading the related models.

Returns

[ICollection](#) <T>

A collection of the primary models with the specified foreign key field populated.

Type Parameters

T

The type of the primary model in the collection. Must implement [IRelmModel](#).

R

The type of the related model representing the foreign key. Must implement [IRelmModel](#).

Remarks

This method is an extension method that simplifies the process of loading related data for a collection of models. It uses the provided **relmContext** to resolve the foreign key relationships and applies any

additional constraints specified by `additionalConstraints`.

LoadForeignKeyField<T, R>(ICollection<T>, IRealmContext, Expression<Func<T, R>>)

Loads and resolves a foreign key field for a collection of models.

```
public static ICollection<T> LoadForeignKeyField<T, R>(this ICollection<T> modelData,
    IRealmContext realmContext, Expression<Func<T, R>> predicate) where T : IRealmModel, new()
    where R : IRealmModel, new()
```

Parameters

modelData [ICollection](#)<T>

The collection of models for which the foreign key field will be loaded.

realmContext [IRealmContext](#)

The context used to resolve the foreign key relationships.

predicate [Expression](#)<[Func](#)<T, R>>

An expression specifying the foreign key field to load.

Returns

[ICollection](#)<T>

A collection of models with the specified foreign key field resolved.

Type Parameters

T

The type of the model in the collection. Must implement [IRealmModel](#).

R

The type of the related model to be loaded. Must implement [IRealmModel](#).

Remarks

This method uses the provided `realmContext` to resolve the foreign key relationships for the specified field in the collection of models. The `predicate` determines which foreign key field to load.

LoadForeignKeyField<T, R>(ICollection<T>, IRealmContext, Expression<Func<T, R>>, Expression<Func<R, object>>)

Loads and resolves a foreign key field for a collection of models, applying the specified predicate and additional constraints.

```
public static ICollection<T> LoadForeignKeyField<T, R>(this ICollection<T> modelData,
    IRealmContext realmContext, Expression<Func<T, R>> predicate, Expression<Func<R, object>>
    additionalConstraints) where T : IRealmModel, new() where R : IRealmModel, new()
```

Parameters

`modelData` [ICollection](#)<T>

The collection of primary models for which the foreign key field will be loaded.

`realmContext` [IRealmContext](#)

The context used to resolve the foreign key relationships.

`predicate` [Expression](#)<[Func](#)<T, R>>

An expression specifying the foreign key relationship between the primary and related models.

`additionalConstraints` [Expression](#)<[Func](#)<R, [object](#)>>

An optional expression specifying additional constraints to apply when resolving the foreign key field.

Returns

[ICollection](#)<T>

A collection of the primary models with the foreign key field resolved based on the specified predicate and constraints.

Type Parameters

T

The type of the primary model in the collection. Must implement [IRelmModel](#).

R

The type of the related model to be loaded. Must implement [IRelmModel](#).

Remarks

This method is an extension method that simplifies the process of resolving foreign key relationships for a collection of models. It uses the provided `relmContext` to perform the resolution and applies the specified `predicate` to define the relationship. Additional constraints can be applied using the `additionalConstraints` parameter.

LoadForeignKeyField<T, R>(ICollection<T>, IRelmQuickContext, Expression<Func<T, ICollection<R>>>)

Loads and populates a foreign key collection field for each entity in the specified model data collection.

```
public static ICollection<T> LoadForeignKeyField<T, R>(this ICollection<T> modelData,
IRelmQuickContext relmQuickContext, Expression<Func<T, ICollection<R>>> predicate) where T :
IRelmModel, new() where R : IRelmModel, new()
```

Parameters

`modelData` [ICollection](#)<T>

The collection of primary model entities for which the foreign key field will be loaded.

`relmQuickContext` [IRelmQuickContext](#)

The database context used to query and load the related entities.

`predicate` [Expression](#)<[Func](#)<T, [ICollection](#)<R>>>

An expression specifying the foreign key collection property to populate for each entity in `modelData`.

Returns

[ICollection](#)<T>

The original `modelData` collection with the specified foreign key field populated for each entity.

Type Parameters

T

The type of the primary model entities in the collection. Must implement [IRelmModel](#).

R

The type of the related entities in the foreign key collection. Must implement [IRelmModel](#).

Remarks

This method uses the provided `relmQuickContext` to query and load the related entities for the specified foreign key collection property. The foreign key field is populated for each entity in the `modelData` collection based on the provided `predicate`.

LoadForeignKeyField<T, R>(ICollection<T>, IRelmQuickContext, Expression<Func<T, ICollection<R>>>, Expression<Func<R, object>>>)

Loads and populates a foreign key collection field for a collection of model entities.

```
public static ICollection<T> LoadForeignKeyField<T, R>(this ICollection<T> modelData,
IRelmQuickContext relmQuickContext, Expression<Func<T, ICollection<R>>> predicate,
Expression<Func<R, object>> additionalConstraints) where T : IRelmModel, new() where R :
IRelmModel, new()
```

Parameters

modelData [ICollection](#)<T>

The collection of primary model entities for which the foreign key field will be loaded.

relmQuickContext [IRelmQuickContext](#)

The database context used to query and load the related entities.

predicate [Expression](#)<[Func](#)<T, [ICollection](#)<R>>>

An expression specifying the foreign key field to populate in the primary model entities.

additionalConstraints [Expression](#)<[Func](#)<R, [object](#)>>

An expression specifying additional constraints to apply when querying the related entities.

Returns

[ICollection](#)  <T>

A collection of the primary model entities with the specified foreign key field populated.

Type Parameters

T

The type of the primary model entities in the collection. Must implement [IRelmModel](#).

R

The type of the related entities referenced by the foreign key. Must implement [IRelmModel](#).

Remarks

This method is an extension method that facilitates the loading of related entities for a collection of primary model entities. It uses the specified database context and constraints to query and populate the foreign key field.

LoadForeignKeyField<T, R>(ICollection<T>, IRelmQuickContext, Expression<Func<T, R>>)

Loads and resolves a foreign key field for the specified collection of models.

```
public static ICollection<T> LoadForeignKeyField<T, R>(this ICollection<T> modelData,
IRelmQuickContext relmQuickContext, Expression<Func<T, R>> predicate) where T : IRelmModel,
new() where R : IRelmModel, new()
```

Parameters

modelData [ICollection](#)  <T>

The collection of models for which the foreign key field will be loaded.

relmQuickContext [IRelmQuickContext](#)

The database context used to resolve the foreign key relationships.

predicate [Expression](#) <[Func](#) <T, R>>

An expression specifying the foreign key field to load.

Returns

[ICollection](#) <T>

The original collection of models with the specified foreign key field resolved and loaded.

Type Parameters

T

The type of the model in the collection. Must implement [IRelmModel](#).

R

The type of the related model to be loaded. Must implement [IRelmModel](#).

Remarks

This method uses the provided **relmQuickContext** to resolve the foreign key relationships for the specified field in the collection of models. The foreign key field is loaded based on the **predicate** expression.

LoadForeignKeyField<T, R>(ICollection<T>, IRelmQuickContext, Expression<Func<T, R>>, Expression<Func<R, object>>)

Loads and resolves a foreign key field for a collection of models, applying the specified constraints.

```
public static ICollection<T> LoadForeignKeyField<T, R>(this ICollection<T> modelData,
IRelmQuickContext relmQuickContext, Expression<Func<T, R>> predicate, Expression<Func<R,
object>> additionalConstraints) where T : IRelmModel, new() where R : IRelmModel, new()
```

Parameters

modelData [ICollection](#) <T>

The collection of primary models for which the foreign key field will be loaded.

relmQuickContext [IRelmQuickContext](#)

The database context used to resolve the foreign key relationships.

predicate [Expression](#) <[Func](#) <T, R>>

An expression specifying the foreign key relationship between the primary model and the related model.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#)>>

An optional expression specifying additional constraints to apply when resolving the foreign key field.

Returns

[ICollection](#) <T>

A collection of the primary models with the foreign key field resolved and populated.

Type Parameters

T

The type of the primary model in the collection. Must implement [IRelmModel](#).

R

The type of the related model representing the foreign key. Must implement [IRelmModel](#).

Remarks

This method is an extension method designed to simplify the process of resolving foreign key relationships for a collection of models. It uses the provided database context and expressions to load the related data efficiently. The additional constraints can be used to filter or customize the resolution process.

LoadForeignKeyField<T, R>(ICollection<T>, RelmContextOptionsBuilder, Expression<Func<T, ICollection<R>>>)

Loads and populates a foreign key collection field for the specified collection of model data.

```
public static ICollection<T> LoadForeignKeyField<T, R>(this ICollection<T> modelData,
    RelmContextOptionsBuilder relmContextOptionsBuilder, Expression<Func<T, ICollection<R>>>
```

predicate) `where T : IRealmModel, new() where R : IRealmModel, new()`

Parameters

`modelData` [ICollection](#) <T>

The collection of primary model data for which the foreign key field will be loaded.

`realmContextOptionsBuilder` [RealmContextOptionsBuilder](#)

The context options builder used to configure the data loading process.

`predicate` [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the foreign key field to load, represented as a navigation property.

Returns

[ICollection](#) <T>

A collection of the primary model data with the specified foreign key field populated.

Type Parameters

T

The type of the primary model in the collection. Must implement [IRealmModel](#).

R

The type of the related model representing the foreign key. Must implement [IRealmModel](#).

Remarks

This method uses the provided `realmContextOptionsBuilder` to configure the loading process and populates the foreign key field specified by the `predicate` for each item in the `modelData` collection.

LoadForeignKeyField<T, R>(ICollection<T>, RealmContextOptionsBuilder, Expression<Func<T, ICollection<R>>>, Expression<Func<R, object>>)

Loads and populates a foreign key collection field for the specified model data.

```
public static ICollection<T> LoadForeignKeyField<T, R>(this ICollection<T> modelData,
    RealmContextOptionsBuilder realmContextOptionsBuilder, Expression<Func<T, ICollection<R>>>
    predicate, Expression<Func<R, object>> additionalConstraints) where T : IRealmModel, new()
    where R : IRealmModel, new()
```

Parameters

modelData [ICollection](#) <T>

The collection of primary model instances for which the foreign key field will be loaded.

realmContextOptionsBuilder [RealmContextOptionsBuilder](#)

The options builder used to configure the database context for the operation.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the foreign key collection property to populate.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#)>>

An optional expression defining additional constraints to apply when loading the related data.

Returns

[ICollection](#) <T>

A collection of the primary model instances with the specified foreign key field populated.

Type Parameters

T

The type of the primary model, which must implement [IRealmModel](#).

R

The type of the related model, which must implement [IRealmModel](#).

Remarks

This method uses the provided **realmContextOptionsBuilder** to configure the database context and loads the related data for the specified foreign key field. The **additionalConstraints** parameter can be used to filter the related data further, if needed.

LoadForeignKeyField<T, R>(ICollection<T>, RealmContextOptionsBuilder, Expression<Func<T, R>>)

Loads and resolves a foreign key field for the specified model data collection.

```
public static ICollection<T> LoadForeignKeyField<T, R>(this ICollection<T> modelData,
    RealmContextOptionsBuilder realmContextOptionsBuilder, Expression<Func<T, R>> predicate) where
    T : IRealmModel, new() where R : IRealmModel, new()
```

Parameters

modelData [ICollection](#)<T>

The collection of models for which the foreign key field will be loaded.

realmContextOptionsBuilder [RealmContextOptionsBuilder](#)

The context options builder used to configure the loading process.

predicate [Expression](#)<[Func](#)<T, R>>

An expression specifying the foreign key field to load.

Returns

[ICollection](#)<T>

A collection of models with the specified foreign key field resolved.

Type Parameters

T

The type of the model in the collection. Must implement [IRealmModel](#).

R

The type of the related model to be loaded. Must implement [IRealmModel](#).

Remarks

This method uses a `SimpleRealm.RealmInternal.Helpers.Utilities.ForeignKeyLoader<T>` to load the foreign key field specified by the **predicate**. The foreign key field is resolved based on the provided context

options and the relationship defined in the model.

LoadForeignKeyField<T, R>(ICollection<T>, RelmContextOptionsBuilder, Expression<Func<T, R>>, Expression<Func<R, object>>)

Loads and populates a foreign key field for a collection of models based on the specified predicate and additional constraints.

```
public static ICollection<T> LoadForeignKeyField<T, R>(this ICollection<T> modelData,
    RelmContextOptionsBuilder relmContextOptionsBuilder, Expression<Func<T, R>> predicate,
    Expression<Func<R, object>> additionalConstraints) where T : IRelmModel, new() where R :
    IRelmModel, new()
```

Parameters

modelData [ICollection](#)<T>

The collection of primary models for which the foreign key field will be loaded.

relmContextOptionsBuilder [RelmContextOptionsBuilder](#)

The options builder used to configure the database context for loading the foreign key data.

predicate [Expression](#)<[Func](#)<T, R>>

An expression specifying the foreign key relationship between the primary model and the related model.

additionalConstraints [Expression](#)<[Func](#)<R, [object](#)>>

An optional expression specifying additional constraints to apply when loading the foreign key data.

Returns

[ICollection](#)<T>

A collection of primary models with the specified foreign key field populated.

Type Parameters

T

The type of the primary model in the collection. Must implement [IRelmModel](#).

R

The type of the related model representing the foreign key. Must implement [IRelmModel](#).

Remarks

This method uses the provided `relmContextOptionsBuilder` to configure the database context and load the related data. The `predicate` defines the relationship between the primary and related models, while the `additionalConstraints` can be used to further filter the related data being loaded.

LoadForeignKeyField<T, R, S>(ICollection<T>, IRelmContext, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>)

Loads and populates a foreign key collection field for a collection of models using the specified predicate and data loader.

```
public static ICollection<T> LoadForeignKeyField<T, R, S>(this ICollection<T> modelData,
IRelmContext relmContext, Expression<Func<T, ICollection<R>>> predicate, IRelmDataLoader<S>
customDataLoader) where T : IRelmModel, new() where R : IRelmModel, new() where S :
IRelmModel, new()
```

Parameters

`modelData` [ICollection](#)<T>

The collection of primary models for which the foreign key field will be loaded.

`relmContext` [IRelmContext](#)

The context used to interact with the data source.

`predicate` [Expression](#)<[Func](#)<T, [ICollection](#)<R>>>

An expression specifying the foreign key field to be loaded.

`customDataLoader` [IRelmDataLoader](#)<S>

A custom data loader used to retrieve the related data.

Returns

[ICollection](#) <T>

A collection of primary models with the specified foreign key field populated.

Type Parameters

T

The type of the primary model in the collection.

R

The type of the related model representing the foreign key field.

S

The type of the model used by the custom data loader.

Remarks

This method uses the provided `customDataLoader` to load the related data for the foreign key field specified by `predicate`. The method is an extension method and operates on the collection of primary models (`modelData`).

LoadForeignKeyField<T, R, S>(ICollection<T>, IRelmContext, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>, Expression<Func<R, object>>)

Loads and populates a foreign key collection field for a collection of models using the specified data loader and constraints.

```
public static ICollection<T> LoadForeignKeyField<T, R, S>(this ICollection<T> modelData,
IRelmContext relmContext, Expression<Func<T, ICollection<R>>> predicate, IRelmDataLoader<S>
customDataLoader, Expression<Func<R, object>> additionalConstraints) where T : IRelmModel,
new() where R : IRelmModel, new() where S : IRelmModel, new()
```

Parameters

`modelData` [ICollection](#) <T>

The collection of primary models for which the foreign key field will be loaded.

realmContext [IRelmContext](#)

The context used to manage the data loading operation.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R> > >

An expression specifying the foreign key field to populate in the primary model.

customDataLoader [IRelmDataLoader](#) <S>

A custom data loader used to retrieve the related data.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#) > >

An expression specifying additional constraints to apply when loading the related data.

Returns

[ICollection](#) <T>

A collection of the primary models with the specified foreign key field populated.

Type Parameters

T

The type of the primary model in the collection.

R

The type of the related model representing the foreign key field.

S

The type of the model used by the custom data loader.

Remarks

This method uses a custom data loader and optional constraints to populate a foreign key field in the primary models. It is designed to work with models that implement the [IRelmModel](#) interface.

LoadForeignKeyField<T, R, S>(ICollection<T>, IRelmContext, Expression<Func<T, R> >, IRelmDataLoader<S>)

Loads and resolves a foreign key field for a collection of models, using the specified predicate and custom data loader.

```
public static ICollection<T> LoadForeignKeyField<T, R, S>(this ICollection<T> modelData,
IRelmContext relmContext, Expression<Func<T, R>> predicate, IRelmDataLoader<S>
customDataLoader) where T : IRelmModel, new() where R : IRelmModel, new() where S :
IRelmModel, new()
```

Parameters

modelData [ICollection](#)<T>

The collection of models for which the foreign key field will be loaded.

relmContext [IRelmContext](#)

The context used to interact with the data source.

predicate [Expression](#)<[Func](#)<T, R>>

An expression specifying the foreign key field to load.

customDataLoader [IRelmDataLoader](#)<S>

A custom data loader used to retrieve the related data.

Returns

[ICollection](#)<T>

The original collection of models with the specified foreign key field resolved.

Type Parameters

T

The type of the model in the collection. Must implement [IRelmModel](#).

R

The type of the related model being loaded. Must implement [IRelmModel](#).

S

The type of the model used by the custom data loader. Must implement [IRelmModel](#).

Remarks

This method is an extension method that facilitates the resolution of foreign key relationships for a collection of models. The `customDataLoader` allows for custom logic to be applied when loading the related data.

LoadForeignKeyField<T, R, S>(ICollection<T>, IRelmContext, Expression<Func<T, R>>, IRelmDataLoader<S>, Expression<Func<R, object>>)

Loads and resolves a foreign key field for a collection of models, applying optional constraints and using a custom data loader.

```
public static ICollection<T> LoadForeignKeyField<T, R, S>(this ICollection<T> modelData,
IRelmContext relmContext, Expression<Func<T, R>> predicate, IRelmDataLoader<S>
customDataLoader, Expression<Func<R, object>> additionalConstraints) where T : IRelmModel,
new() where R : IRelmModel, new() where S : IRelmModel, new()
```

Parameters

`modelData` [ICollection](#)<T>

The collection of primary models for which the foreign key field will be loaded.

`relmContext` [IRelmContext](#)

The context used to interact with the data source.

`predicate` [Expression](#)<[Func](#)<T, R>>

An expression specifying the foreign key field to load in the primary model.

`customDataLoader` [IRelmDataLoader](#)<S>

A custom data loader used to retrieve the related data for the foreign key field.

`additionalConstraints` [Expression](#)<[Func](#)<R, [object](#)>>>

An optional expression specifying additional constraints to apply when resolving the foreign key field.

Returns

[ICollection](#)  <T>

A collection of the primary models with the specified foreign key field resolved and populated.

Type Parameters

T

The type of the primary model in the collection. Must implement [IRelmModel](#).

R

The type of the related model representing the foreign key. Must implement [IRelmModel](#).

S

The type of the model used by the custom data loader. Must implement [IRelmModel](#).

Remarks

This method is an extension method designed to simplify the process of resolving foreign key relationships in a collection of models. It allows for the use of a custom data loader and additional constraints to tailor the loading process to specific requirements.

LoadForeignKeyField<T, R, S>(ICollection<T>, IRelmQuickContext, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>)

Loads and populates a foreign key collection field for a collection of models.

```
public static ICollection<T> LoadForeignKeyField<T, R, S>(this ICollection<T> modelData,
IRelmQuickContext relmQuickContext, Expression<Func<T, ICollection<R>>> predicate,
IRelmDataLoader<S> customDataLoader) where T : IRelmModel, new() where R : IRelmModel, new()
where S : IRelmModel, new()
```

Parameters

modelData [ICollection](#)  <T>

The collection of primary models for which the foreign key field will be loaded.

realmQuickContext [IRelmQuickContext](#)

The context used to manage data loading operations.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the foreign key collection property to populate.

customDataLoader [IRelmDataLoader](#) <S>

A custom data loader used to retrieve the related data.

Returns

[ICollection](#) <T>

The original collection of primary models with the specified foreign key field populated.

Type Parameters

T

The type of the primary model in the collection.

R

The type of the related model in the foreign key collection.

S

The type of the model used by the custom data loader.

Remarks

This method uses a `SimpleRelm.RelmInternal.Helpers.Utilities.ForeignKeyLoader<T>` to load the foreign key collection field for each model in the provided collection. The **customDataLoader** allows for custom logic to retrieve the related data, which is then used to populate the specified foreign key field.

```
LoadForeignKeyField<T, R, S>(ICollection<T>,
IRelmQuickContext, Expression<Func<T, ICollection<R>>>,
IRelmDataLoader<S>, Expression<Func<R, object>>)
```

Loads and populates a foreign key collection field for a collection of models using the specified data loader and constraints.

```
public static ICollection<T> LoadForeignKeyField<T, R, S>(this ICollection<T> modelData,
IRelmQuickContext relmQuickContext, Expression<Func<T, ICollection<R>>> predicate,
IRelmDataLoader<S> customDataLoader, Expression<Func<R, object>> additionalConstraints)
where T : IRelmModel, new() where R : IRelmModel, new() where S : IRelmModel, new()
```

Parameters

modelData [ICollection](#) <T>

The collection of primary models for which the foreign key field will be loaded.

relmQuickContext [IRelmQuickContext](#)

The context used to manage data loading operations.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the foreign key field to be loaded for each primary model.

customDataLoader [IRelmDataLoader](#) <S>

A custom data loader used to retrieve the related data.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#)>>

An expression specifying additional constraints to apply when loading the related data.

Returns

[ICollection](#) <T>

A collection of primary models with the specified foreign key field populated.

Type Parameters

T

The type of the primary model in the collection.

R

The type of the related model representing the foreign key field.

S

The type of the model used by the custom data loader.

Remarks

This method uses a `SimpleRelm.RelmInternal.Helpers.Utilities.ForeignKeyLoader<T>` to load the foreign key field for the provided collection of models. The `customDataLoader` allows for custom logic to retrieve the related data, and the `additionalConstraints` parameter can be used to further refine the data loading process.

LoadForeignKeyField<T, R, S>(ICollection<T>, IRelmQuickContext, Expression<Func<T, R>>, IRelmDataLoader<S>)

Loads and resolves a foreign key field for a collection of models, using the specified predicate and custom data loader.

```
public static ICollection<T> LoadForeignKeyField<T, R, S>(this ICollection<T> modelData,
IRelmQuickContext relmQuickContext, Expression<Func<T, R>> predicate, IRelmDataLoader<S>
customDataLoader) where T : IRelmModel, new() where R : IRelmModel, new() where S :
IRelmModel, new()
```

Parameters

modelData [ICollection](#)<T>

The collection of primary models for which the foreign key field will be loaded.

relmQuickContext [IRelmQuickContext](#)

The context used to manage data loading operations.

predicate [Expression](#)<[Func](#)<T, R>>

An expression that specifies the foreign key field to be loaded.

customDataLoader [IRelmDataLoader](#)<S>

A custom data loader used to retrieve the related data.

Returns

[ICollection](#)  <T>

A collection of the primary models with the specified foreign key field resolved.

Type Parameters

T

The type of the primary model in the collection. Must implement [IRelmModel](#).

R

The type of the related model being loaded. Must implement [IRelmModel](#).

S

The type of the model used by the custom data loader. Must implement [IRelmModel](#).

Remarks

This method is an extension method that simplifies the process of resolving foreign key relationships for a collection of models. The `customDataLoader` allows for custom logic to be applied when retrieving the related data.

`LoadForeignKeyField<T, R, S>(ICollection<T>, IRelmQuickContext, Expression<Func<T, R>>, IRelmDataLoader<S>, Expression<Func<R, object>>)`

Loads and resolves a foreign key field for a collection of models, applying additional constraints if specified.

```
public static ICollection<T> LoadForeignKeyField<T, R, S>(this ICollection<T> modelData,
IRelmQuickContext relmQuickContext, Expression<Func<T, R>> predicate, IRelmDataLoader<S>
customDataLoader, Expression<Func<R, object>> additionalConstraints) where T : IRelmModel,
new() where R : IRelmModel, new() where S : IRelmModel, new()
```

Parameters

`modelData` [ICollection](#)  <T>

The collection of primary models for which the foreign key field will be loaded.

realmQuickContext [IRelmQuickContext](#)

The context used to manage data loading operations.

predicate [Expression](#) <[Func](#) <T, R>>

An expression specifying the foreign key relationship between the primary model and the related model.

customDataLoader [IRelmDataLoader](#)<S>

A custom data loader used to retrieve the related models.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#)>>>

An expression specifying additional constraints to apply when resolving the foreign key field.

Returns

[ICollection](#) <T>

A collection of the primary models with the foreign key field resolved and populated.

Type Parameters

T

The type of the primary model in the collection.

R

The type of the related model referenced by the foreign key.

S

The type of the model used by the custom data loader.

LoadForeignKeyField<T, R, S>(ICollection<T>, RelmContextOptionsBuilder, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>)

Loads and populates a foreign key collection field for the specified model data.

```
public static ICollection<T> LoadForeignKeyField<T, R, S>(this ICollection<T> modelData,
    RealmContextOptionsBuilder realmContextOptionsBuilder, Expression<Func<T, ICollection<R>>>
    predicate, IRealmDataLoader<S> customDataLoader) where T : IRealmModel, new() where R :
    IRealmModel, new() where S : IRealmModel, new()
```

Parameters

modelData [ICollection](#) <T>

The collection of primary model instances for which the foreign key field will be loaded.

realmContextOptionsBuilder [RealmContextOptionsBuilder](#)

The options builder used to configure the data loading context.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the foreign key collection property to populate.

customDataLoader [IRealmDataLoader](#) <S>

A custom data loader used to retrieve the related data.

Returns

[ICollection](#) <T>

The original collection of primary model instances with the specified foreign key field populated.

Type Parameters

T

The type of the primary model in the collection.

R

The type of the related model in the foreign key collection.

S

The type of the model used by the custom data loader.

Remarks

This method uses a `SimpleRelm.RelmInternal.Helpers.Utilities.ForeignKeyLoader<T>` to load the foreign key collection field for each model instance in the provided `modelData` collection. The `customDataLoader` is used to retrieve the related data, and the `predicate` specifies the foreign key collection property to populate.

LoadForeignKeyField<T, R, S>(ICollection<T>, RelmContextOptionsBuilder, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>, Expression<Func<R, object>>)

Loads and populates a foreign key collection field for a collection of model data.

```
public static ICollection<T> LoadForeignKeyField<T, R, S>(this ICollection<T> modelData,
    RelmContextOptionsBuilder relmContextOptionsBuilder, Expression<Func<T, ICollection<R>>>
    predicate, IRelmDataLoader<S> customDataLoader, Expression<Func<R, object>>
    additionalConstraints) where T : IRelmModel, new() where R : IRelmModel, new() where S :
    IRelmModel, new()
```

Parameters

`modelData` [ICollection](#)<T>

The collection of primary model data for which the foreign key field will be loaded.

`relmContextOptionsBuilder` [RelmContextOptionsBuilder](#)

The options builder used to configure the data loading context.

`predicate` [Expression](#)<[Func](#)<T, [ICollection](#)<R>>>

An expression specifying the foreign key field to be loaded.

`customDataLoader` [IRelmDataLoader](#)<S>

A custom data loader used to retrieve the related data.

`additionalConstraints` [Expression](#)<[Func](#)<R, [object](#)>>

An expression specifying additional constraints to apply when loading the foreign key field.

Returns

[ICollection](#) [↗] <T>

A collection of the primary model data with the specified foreign key field populated.

Type Parameters

T

The type of the primary model in the collection.

R

The type of the related model representing the foreign key field.

S

The type of the model used by the custom data loader.

Remarks

This method uses a foreign key loader to populate the specified foreign key field for the provided collection of model data. The `customDataLoader` allows for custom logic to retrieve the related data, and the `additionalConstraints` parameter can be used to apply additional filtering or constraints.

LoadForeignKeyField<T, R, S>(ICollection<T>, RelmContextOptionsBuilder, Expression<Func<T, R>>, IRelmDataLoader<S>)

Loads and resolves a foreign key field for a collection of models, using the specified predicate and custom data loader.

```
public static ICollection<T> LoadForeignKeyField<T, R, S>(this ICollection<T> modelData,
    RelmContextOptionsBuilder relmContextOptionsBuilder, Expression<Func<T, R>> predicate,
    IRelmDataLoader<S> customDataLoader) where T : IRelmModel, new() where R : IRelmModel, new()
    where S : IRelmModel, new()
```

Parameters

modelData [ICollection](#) [↗] <T>

The collection of primary models for which the foreign key field will be loaded.

`realmContextOptionsBuilder` [RealmContextOptionsBuilder](#)

The options builder used to configure the data loading context.

`predicate` [Expression](#) [Func](#) <T, R> >

An expression specifying the foreign key relationship to resolve.

`customDataLoader` [IRelmDataLoader](#) <S>

A custom data loader used to fetch the related data.

Returns

[ICollection](#) <T>

A collection of the primary models with the specified foreign key field resolved.

Type Parameters

T

The type of the primary model in the collection. Must implement [IRelmModel](#).

R

The type of the related model being resolved. Must implement [IRelmModel](#).

S

The type of the model used by the custom data loader. Must implement [IRelmModel](#).

Remarks

This method uses a foreign key loader to resolve the specified relationship for the provided collection of models. The `customDataLoader` allows for custom logic to be applied when loading the related data.

LoadForeignKeyField <T, R, S> (ICollection <T>, RealmContextOptionsBuilder, Expression <Func <T, R> >, IRelmDataLoader <S>, Expression <Func <R, object> >)

Loads and resolves a foreign key field for a collection of models, applying additional constraints if specified.

```
public static ICollection<T> LoadForeignKeyField<T, R, S>(this ICollection<T> modelData,
    RealmContextOptionsBuilder realmContextOptionsBuilder, Expression<Func<T, R>> predicate,
    IRealmDataLoader<S> customDataLoader, Expression<Func<R, object>> additionalConstraints)
    where T : IRealmModel, new() where R : IRealmModel, new() where S : IRealmModel, new()
```

Parameters

modelData [ICollection](#)<T>

The collection of primary models for which the foreign key field will be loaded.

realmContextOptionsBuilder [RealmContextOptionsBuilder](#)

The options builder used to configure the data loading context.

predicate [Expression](#)<[Func](#)<T, R>>

An expression specifying the foreign key relationship between the primary model and the related model.

customDataLoader [IRealmDataLoader](#)<S>

A custom data loader used to fetch the related data.

additionalConstraints [Expression](#)<[Func](#)<R, [object](#)>>

An optional expression specifying additional constraints to apply when resolving the foreign key field.

Returns

[ICollection](#)<T>

A collection of the primary models with the foreign key field resolved and loaded.

Type Parameters

T

The type of the primary model in the collection. Must implement [IRealmModel](#).

R

The type of the related model representing the foreign key. Must implement [IRealmModel](#).

The type of the model used by the custom data loader. Must implement [IRelmModel](#).

WriteToDatabase<T>(IEnumerable<T>, MySqlConnection, MySqlTransaction, string, Type, int, string, bool, bool, bool, bool)

Writes a collection of model data to a database table in bulk.

```
public static int WriteToDatabase<T>(this IEnumerable<T> modelData, MySqlConnection
existingConnection, MySqlTransaction sqlTransaction = null, string tableName = null, Type
forceType = null, int batchSize = 100, string databaseName = null, bool
allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool
allowUniqueColumns = false, bool allowAutoDateColumns = false) where T : IRelmModel
```

Parameters

modelData [IEnumerable](#)<T>

The collection of model data to write to the database.

existingConnection MySqlConnection

An open MySql.Data.MySqlClient.MySqlConnection to the database where the data will be written.

sqlTransaction MySqlTransaction

An optional MySql.Data.MySqlClient.MySqlTransaction to use for the operation. If null, no transaction is used.

tableName [string](#)

The name of the database table to write to. If null, the table name is inferred from the model type.

forceType [Type](#)

An optional [Type](#) to enforce a specific model type for the operation. If null, the type of **T** is used.

batchSize [int](#)

The number of rows to write in each batch. Defaults to 100.

databaseName [string](#)

The name of the database to write to. If null, the default database for the connection is used.

`allowAutoIncrementColumns` [bool](#)

Indicates whether auto-increment columns are allowed to be written. Defaults to [false](#).

`allowPrimaryKeyColumns` [bool](#)

Indicates whether primary key columns are allowed to be written. Defaults to [false](#).

`allowUniqueColumns` [bool](#)

Indicates whether unique columns are allowed to be written. Defaults to [false](#).

`allowAutoDateColumns` [bool](#)

Indicates whether auto-generated date columns are allowed to be written. Defaults to [false](#).

Returns

[int](#)

The number of rows successfully written to the database.

Type Parameters

T

The type of the model data, which must implement [IRelmModel](#).

Remarks

This method performs a bulk write operation, which is optimized for inserting large amounts of data efficiently. The caller is responsible for ensuring that the `existingConnection` is open and valid before calling this method. If `sqlTransaction` is provided, the operation will be part of the specified transaction.

WriteToDatabase<T>(IEnumerable<T>, IRelmContext, string, Type, int, string, bool, bool, bool, bool)

Writes the specified collection of data to a database table in bulk.

```
public static int WriteToDatabase<T>(this IEnumerable<T> modelData, IRelmContext  
    relmContext, string tableName = null, Type forceType = null, int batchSize = 100, string
```

```
databaseName = null, bool allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool allowUniqueColumns = false, bool allowAutoDateColumns = false)
```

Parameters

modelData [IEnumerable](#) <T>

The collection of data objects to write to the database. Cannot be null or empty.

realmContext [IRelmContext](#)

The database context used to perform the write operation. Cannot be null.

tableName [string](#)

The name of the database table to write to. If null, the table name is inferred from the type **T**.

forceType [Type](#)

An optional type to enforce for the database table schema. If null, the schema is inferred from **T**.

batchSize [int](#)

The number of records to write in each batch. Defaults to 100. Must be greater than zero.

databaseName [string](#)

The name of the database to write to. If null, the default database is used.

allowAutoIncrementColumns [bool](#)

Indicates whether auto-increment columns are allowed in the table. Defaults to [false](#).

allowPrimaryKeyColumns [bool](#)

Indicates whether primary key columns are allowed in the table. Defaults to [false](#).

allowUniqueColumns [bool](#)

Indicates whether unique columns are allowed in the table. Defaults to [false](#).

allowAutoDateColumns [bool](#)

Indicates whether auto-generated date columns are allowed in the table. Defaults to [false](#).

Returns

[int](#)

The number of records successfully written to the database.

Type Parameters

T

The type of the data objects to be written to the database.

Remarks

This method performs a bulk write operation, which is optimized for performance when inserting large amounts of data. The table schema is inferred from the type **T** unless a specific schema is enforced using the **forceType** parameter.

WriteToDatabase<T>(IEnumerable<T>, IRealmQuickContext, string, Type, int, string, bool, bool, bool, bool)

Writes the specified collection of data to a database table in bulk.

```
public static int WriteToDatabase<T>(this IEnumerable<T> modelData, IRealmQuickContext
realmContext, string tableName = null, Type forceType = null, int batchSize = 100, string
databaseName = null, bool allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns =
false, bool allowUniqueColumns = false, bool allowAutoDateColumns = false)
```

Parameters

modelData [IEnumerable](#) <T>

The collection of data objects to write to the database. Cannot be null or empty.

realmContext [IRealmQuickContext](#)

The database context used to perform the write operation. Cannot be null.

tableName [string](#)

The name of the database table to write to. If null, the table name is inferred from the type **T**.

forceType [Type](#)

An optional type to enforce for the database table schema. If null, the schema is inferred from the type `T`.

`batchSize` [int](#)

The number of records to write in each batch. Defaults to 100. Must be greater than zero.

`databaseName` [string](#)

The name of the database to write to. If null, the default database associated with `realmContext` is used.

`allowAutoIncrementColumns` [bool](#)

A value indicating whether columns with auto-increment constraints are allowed to be written. Defaults to [false](#).

`allowPrimaryKeyColumns` [bool](#)

A value indicating whether primary key columns are allowed to be written. Defaults to [false](#).

`allowUniqueColumns` [bool](#)

A value indicating whether columns with unique constraints are allowed to be written. Defaults to [false](#).

`allowAutoDateColumns` [bool](#)

A value indicating whether columns with automatic date constraints are allowed to be written. Defaults to [false](#).

Returns

[int](#)

The total number of records successfully written to the database.

Type Parameters

`T`

The type of the data objects to be written to the database.

Remarks

This method performs a bulk write operation, which is optimized for performance when inserting large amounts of data. The behavior of the write operation can be customized using the optional parameters.

WriteToDatabase<T>(IEnumerable<T>, Enum, string, Type, bool, int, string, bool, bool, bool, bool)

Writes a collection of model data to a database table in bulk.

```
public static int WriteToDatabase<T>(this IEnumerable<T> modelData, Enum connectionName,
string tableName = null, Type forceType = null, bool allowUserVariables = false, int
batchSize = 100, string databaseName = null, bool allowAutoIncrementColumns = false, bool
allowPrimaryKeyColumns = false, bool allowUniqueColumns = false, bool allowAutoDateColumns =
false) where T : IRelmModel
```

Parameters

modelData [IEnumerable<T>](#)

The collection of model data to be written to the database.

connectionName [Enum](#)

The database connection identifier, represented as an enumeration value.

tableName [string](#)

The name of the database table to write to. If [null](#), the default table name for the model type **T** is used.

forceType [Type](#)

An optional type to enforce during the write operation. If [null](#), the type of **T** is used.

allowUserVariables [bool](#)

A value indicating whether user-defined variables are allowed in the database operation. The default is [false](#).

batchSize [int](#)

The number of records to write in each batch. The default is 100.

databaseName [string](#)

The name of the database to write to. If [null](#), the default database for the connection is used.

allowAutoIncrementColumns [bool](#)

A value indicating whether auto-increment columns are allowed to be written. The default is [false](#).

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns are allowed to be written. The default is [false](#).

allowUniqueColumns [bool](#)

A value indicating whether unique columns are allowed to be written. The default is [false](#).

allowAutoDateColumns [bool](#)

A value indicating whether auto-generated date columns are allowed to be written. The default is [false](#).

Returns

[int](#)

The number of records successfully written to the database.

Type Parameters

T

The type of the model data, which must implement [IRelmModel](#).

Remarks

This method performs a bulk write operation, which is optimized for high performance when inserting large amounts of data. Ensure that the database schema matches the structure of the model data to avoid runtime errors.

Class ModelExtensions

Namespace: [SimpleRelm.Extensions](#)

Assembly: SimpleRelm.dll

```
public static class ModelExtensions
```

Inheritance

[object](#)  ← ModelExtensions

Inherited Members

[object.ToString\(\)](#) , [object.Equals\(object\)](#) , [object.Equals\(object, object\)](#) ,
[object.ReferenceEquals\(object, object\)](#) , [object.GetHashCode\(\)](#) , [object.GetType\(\)](#) ,
[object.MemberwiseClone\(\)](#) 

Methods

LoadDataLoaderField<T, S>(T, IRelmContext, Expression<Func<T, S>>)

Loads a related data field for the specified model using the provided predicate.

```
public static T LoadDataLoaderField<T, S>(this T inputModel, IRelmContext reImContext,  
Expression<Func<T, S>> predicate) where T : IRelmModel, new() where S : IRelmModel, new()
```

Parameters

inputModel T

The model instance for which the related data field is to be loaded.

reImContext [IRelmContext](#)

The context used to access the data source.

predicate [Expression](#)  <[Func](#)  <T, S>>

An expression specifying the related data field to load.

Returns

T

The input model with the specified related data field loaded.

Type Parameters

T

The type of the input model, which must implement [IRelmModel](#).

S

The type of the related data field, which must implement [IRelmModel](#).

Remarks

This method is an extension method that facilitates loading a specific related data field for a model. The `predicate` parameter is used to identify the field to be loaded.

LoadDataLoaderField<T, S>(T, IRelmQuickContext, Expression<Func<T, S>>)

Loads a related data loader field for the specified model using the provided context and predicate.

```
public static T LoadDataLoaderField<T, S>(this T inputModel, IRelmQuickContext  
    relmQuickContext, Expression<Func<T, S>> predicate) where T : IRelmModel, new() where S :  
    IRelmModel, new()
```

Parameters

`inputModel` T

The model instance for which the data loader field is to be loaded.

`relmQuickContext` [IRelmQuickContext](#)

The context used to resolve the data loader field.

`predicate` [Expression](#) <[Func](#) <T, S>>

An expression specifying the property of the input model that represents the related data loader field.

Returns

T

The input model with the specified data loader field loaded.

Type Parameters

T

The type of the input model, which must implement [IRelmModel](#) and have a parameterless constructor.

S

The type of the related model, which must implement [IRelmModel](#) and have a parameterless constructor.

Remarks

This method is an extension method that facilitates the loading of related data fields in a model. It uses the provided predicate to identify the field to be loaded and the context to resolve the data.

LoadDataLoaderField<T, S>(T, RelmContextOptionsBuilder, Expression<Func<T, S>>)

Loads a related data loader field for the specified input model using the provided context options and predicate.

```
public static T LoadDataLoaderField<T, S>(this T inputModel, RelmContextOptionsBuilder  
    relmContextOptionsBuilder, Expression<Func<T, S>> predicate) where T : IRelmModel, new()  
    where S : IRelmModel, new()
```

Parameters

inputModel T

The input model instance for which the related data loader field is to be loaded.

relmContextOptionsBuilder [RelmContextOptionsBuilder](#)

The options builder used to configure the [RelmContext](#) for the operation.

predicate [Expression](#) <[Func](#) <T, S>>

An expression specifying the related data loader field to load.

Returns

T

The input model with the specified related data loader field loaded.

Type Parameters

T

The type of the input model, which must implement [IRelmModel](#) and have a parameterless constructor.

S

The type of the related model to load, which must implement [IRelmModel](#) and have a parameterless constructor.

Remarks

This method is an extension method that simplifies the process of loading a related data loader field for a given model. It creates a new [RelmContext](#) using the provided options builder and applies the specified predicate to determine the field to load.

LoadForeignKeyField<T, R>(T, IRelmContext, Expression<Func<T, ICollection<R>>> predicate)

Loads a foreign key collection property for the specified target model using the provided context and predicate.

```
public static T LoadForeignKeyField<T, R>(this T target, IRelmContext relmContext,
Expression<Func<T, ICollection<R>>> predicate) where T : IRelmModel, new() where R :
IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key collection property will be loaded.

`realmContext` [IRelmContext](#)

The context used to load the foreign key collection property.

`predicate` [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the foreign key collection property to load.

Returns

T

The target model instance with the specified foreign key collection property loaded.

Type Parameters

T

The type of the target model, which must implement [IRelmModel](#).

R

The type of the related model in the collection, which must implement [IRelmModel](#).

Remarks

This method is an extension method that simplifies the process of loading a foreign key collection property for a model. It uses the provided `realmContext` and `predicate` to determine which collection property to load.

LoadForeignKeyField<T, R>(T, IRelmContext, Expression<Func<T, ICollection<R>>>, Expression<Func<R, object>>)

Loads and initializes a foreign key collection property for the specified target model, applying the given constraints.

```
public static T LoadForeignKeyField<T, R>(this T target, IRelmContext realmContext,
Expression<Func<T, ICollection<R>>> predicate, Expression<Func<R, object>>
additionalConstraints) where T : IRelmModel, new() where R : IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key field will be loaded.

realmContext [IRelmContext](#)

The context used to manage the relationship and database operations.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the foreign key field to be loaded as a collection of related models.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#)>>

An expression defining additional constraints to filter the related models.

Returns

T

The target model instance with the foreign key field loaded and initialized.

Type Parameters

T

The type of the target model that contains the foreign key field. Must implement [IRelmModel](#).

R

The type of the related model referenced by the foreign key field. Must implement [IRelmModel](#).

LoadForeignKeyField<T, R>(T, IRelmContext, Expression<Func<T, R>>)

Loads a foreign key field for the specified target model using the provided context and predicate.

```
public static T LoadForeignKeyField<T, R>(this T target, IRelmContext realmContext,
Expression<Func<T, R>> predicate) where T : IRelmModel, new() where R : IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key field will be loaded.

realmContext [IRelmContext](#)

The context used to load the foreign key field.

predicate [Expression](#) <[Func](#) <T, R>>

An expression specifying the foreign key field to load.

Returns

T

The target model instance with the specified foreign key field loaded.

Type Parameters

T

The type of the target model. Must implement [IRelmModel](#) and have a parameterless constructor.

R

The type of the related model. Must implement [IRelmModel](#) and have a parameterless constructor.

Remarks

This method is an extension method that simplifies loading a foreign key field for a model by leveraging the provided context and predicate. The method ensures that the specified foreign key field is populated based on the context's configuration.

LoadForeignKeyField<T, R>(T, IRelmContext, Expression<Func<T, R>>, Expression<Func<R, object>>)

Loads and resolves a foreign key field for the specified target model, applying the given predicate and additional constraints.

```
public static T LoadForeignKeyField<T, R>(this T target, IRelmContext relmContext,
Expression<Func<T, R>> predicate, Expression<Func<R, object>> additionalConstraints) where T
: IRelmModel, new() where R : IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key field is being loaded.

relmContext [IRelmContext](#)

The context used to resolve the foreign key field, providing configuration and database access.

predicate [Expression](#) <[Func](#) <T, R>>

An expression specifying the foreign key relationship between the target model and the related model.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#)>>

An expression specifying additional constraints to apply when resolving the foreign key field.

Returns

T

The target model instance with the foreign key field resolved.

Type Parameters

T

The type of the target model. Must implement [IRelmModel](#).

R

The type of the related model. Must implement [IRelmModel](#).

Remarks

This method is an extension method that simplifies the process of resolving foreign key fields in models. It uses the provided context and constraints to load the related model data.

LoadForeignKeyField<T, R>(T, IRelmQuickContext, Expression<Func<T, ICollection<R>>>)

Loads a foreign key collection property for the specified target model.

```
public static T LoadForeignKeyField<T, R>(this T target, IRelmQuickContext relmContext,
Expression<Func<T, ICollection<R>>> predicate) where T : IRelmModel, new() where R :
IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key collection property will be loaded.

relmContext [IRelmQuickContext](#)

The context providing access to the database and configuration options.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression identifying the foreign key collection property to load.

Returns

T

The target model instance with the specified foreign key collection property loaded.

Type Parameters

T

The type of the target model, which must implement [IRelmModel](#).

R

The type of the related model in the collection, which must implement [IRelmModel](#).

Remarks

This method is an extension method that simplifies loading a foreign key collection property for a model. It uses the provided context and predicate to retrieve and populate the related data.

LoadForeignKeyField<T, R>(T, IRelmQuickContext, Expression<Func<T, ICollection<R>>>, Expression<Func<R, object>>>)

Loads a foreign key collection property for the specified target model, resolving the related collection based on the provided predicate and additional constraints.

```
public static T LoadForeignKeyField<T, R>(this T target, IRelmQuickContext relmContext,
Expression<Func<T, ICollection<R>>> predicate, Expression<Func<R, object>>
additionalConstraints) where T : IRelmModel, new() where R : IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key field is being loaded.

relmContext [IRelmQuickContext](#)

The context providing access to the database and configuration options.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the foreign key collection property on the target model.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#)>>

An expression defining additional constraints to filter the related models.

Returns

T

The target model instance with the foreign key field loaded.

Type Parameters

T

The type of the target model. Must implement [IRelmModel](#).

R

The type of the related model in the foreign key relationship. Must implement [IRelmModel](#).

LoadForeignKeyField<T, R>(T, IRelmQuickContext, Expression<Func<T, R>>)

Loads the foreign key field specified by the given predicate for the target model.

```
public static T LoadForeignKeyField<T, R>(this T target, IRelmQuickContext relmContext,
Expression<Func<T, R>> predicate) where T : IRelmModel, new() where R : IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key field will be loaded.

relmContext [IRelmQuickContext](#)

The context used to access the database or data source.

predicate [Expression](#) <[Func](#) <T, R>>

An expression specifying the foreign key field to load.

Returns

T

The target model instance with the specified foreign key field loaded.

Type Parameters

T

The type of the target model, which must implement [IRelmModel](#).

R

The type of the related model, which must implement [IRelmModel](#).

Remarks

This method is an extension method that simplifies loading a specific foreign key field for a model. The `predicate` parameter should specify the property representing the foreign key relationship.

LoadForeignKeyField<T, R>(T, IRelmQuickContext, Expression<Func<T, R>>, Expression<Func<R, object>>)

Loads a foreign key field for the specified target model, applying the given predicate and additional constraints.

```
public static T LoadForeignKeyField<T, R>(this T target, IRelmQuickContext relmContext,
Expression<Func<T, R>> predicate, Expression<Func<R, object>> additionalConstraints) where T
: IRelmModel, new() where R : IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key field is to be loaded.

relmContext [IRelmQuickContext](#)

The context used to access the database or data source.

predicate [Expression](#) <[Func](#) <T, R>>

An expression specifying the foreign key relationship between the target model and the related model.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#)>>

An expression specifying additional constraints to apply when loading the related model.

Returns

T

The target model instance with the foreign key field loaded based on the specified predicate and constraints.

Type Parameters

T

The type of the target model. Must implement [IRelmModel](#) and have a parameterless constructor.

R

The type of the related model. Must implement [IRelmModel](#) and have a parameterless constructor.

Remarks

This method is an extension method that simplifies loading related data for a model by resolving foreign key relationships. Ensure that the `relmContext` is properly configured to access the underlying data source.

LoadForeignKeyField<T, R>(T, RelmContextOptionsBuilder, Expression<Func<T, ICollection<R>>>)

Loads a foreign key collection property for the specified target model and returns the first related entity.

```
public static T LoadForeignKeyField<T, R>(this T target, RelmContextOptionsBuilder  
relmContextOptionsBuilder, Expression<Func<T, ICollection<R>>> predicate) where T :  
IRelmModel, new() where R : IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key field is being loaded.

relmContextOptionsBuilder [RelmContextOptionsBuilder](#)

The context options builder used to configure the data context.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the collection property on the target model that represents the foreign key relationship.

Returns

T

The first related entity of type **R** from the foreign key field, or [null](#) if no related entities are found.

Type Parameters

T

The type of the target model, which must implement [IRelmModel](#).

R

The type of the related model, which must implement [IRelmModel](#).

Remarks

This method uses a `SimpleRelm.RelmInternal.Helpers.Utilities.ForeignKeyLoader<T>` to load the foreign key field based on the specified predicate.

LoadForeignKeyField<T, R>(T, RelmContextOptionsBuilder, Expression<Func<T, ICollection<R>>>, Expression<Func<R, object>>>)

Loads a foreign key collection property for the specified target model, applying the given predicate and additional constraints.

```
public static T LoadForeignKeyField<T, R>(this T target, RelmContextOptionsBuilder  
relmContextOptionsBuilder, Expression<Func<T, ICollection<R>>> predicate, Expression<Func<R,  
object>>> additionalConstraints) where T : IRelmModel, new() where R : IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key field is being loaded.

relmContextOptionsBuilder [RelmContextOptionsBuilder](#)

The options builder used to configure the database context.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the collection navigation property on the target model.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#)>>

An expression specifying additional constraints to apply when loading the related models.

Returns

T

The first related model that matches the specified predicate and constraints, or [null](#) if no match is found.

Type Parameters

T

The type of the target model. Must implement [IRelmModel](#).

R

The type of the related model. Must implement [IRelmModel](#).

LoadForeignKeyField<T, R>(T, RelmContextOptionsBuilder, Expression<Func<T, R>>)

Loads a foreign key field for the specified target model using the provided context options and predicate.

```
public static T LoadForeignKeyField<T, R>(this T target, RelmContextOptionsBuilder  
relmContextOptionsBuilder, Expression<Func<T, R>> predicate) where T : IRelmModel, new()  
where R : IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key field is to be loaded.

relmContextOptionsBuilder [RelmContextOptionsBuilder](#)

The context options builder used to configure the database context for the operation.

predicate [Expression](#) <[Func](#) <T, R>>

An expression specifying the foreign key field to load.

Returns

T

The first related model instance matching the foreign key field, or [null](#) if no match is found.

Type Parameters

T

The type of the target model. Must implement [IRelmModel](#) and have a parameterless constructor.

R

The type of the related model. Must implement [IRelmModel](#) and have a parameterless constructor.

Remarks

This method uses a `SimpleRelm.RelmInternal.Helpers.Utilities.ForeignKeyLoader<T>` to load the foreign key field based on the provided predicate.

LoadForeignKeyField<T, R>(T, RelmContextOptionsBuilder, Expression<Func<T, R>>, Expression<Func<R, object>>)

Loads a foreign key field for the specified target model, applying the given predicate and additional constraints.

```
public static T LoadForeignKeyField<T, R>(this T target, RelmContextOptionsBuilder  
relmContextOptionsBuilder, Expression<Func<T, R>> predicate, Expression<Func<R, object>>  
additionalConstraints) where T : IRelmModel, new() where R : IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key field is being loaded.

relmContextOptionsBuilder [RelmContextOptionsBuilder](#)

The options builder used to configure the context for the operation.

predicate [Expression](#) <[Func](#) <T, R>>

An expression specifying the foreign key relationship to load.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#)>>

An expression specifying additional constraints to apply when loading the foreign key field.

Returns

T

The first related model that matches the specified predicate and constraints, or [null](#) if no match is found.

Type Parameters

T

The type of the target model. Must implement [IRelmModel](#).

R

The type of the related model. Must implement [IRelmModel](#).

Remarks

This method is typically used to load a related entity for a given model instance based on a foreign key relationship. Ensure that the provided expressions are valid and compatible with the underlying data context.

LoadForeignKeyField<T, R, S>(T, IRelmContext, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>)

Loads and initializes a foreign key collection property for the specified target model using the provided data loader.

```
public static T LoadForeignKeyField<T, R, S>(this T target, IRelmContext relmContext,
Expression<Func<T, ICollection<R>>> predicate, IRelmDataLoader<S> customDataLoader) where T
: IRelmModel, new() where R : IRelmModel, new() where S : IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key field will be loaded.

`realmContext` [IRelmContext](#)

The context used to manage the data loading operation.

`predicate` [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the foreign key collection property on the target model.

`customDataLoader` [IRelmDataLoader](#) <S>

A custom data loader used to retrieve the related data.

Returns

`T`

The target model instance with the foreign key field loaded.

Type Parameters

`T`

The type of the target model that contains the foreign key field.

`R`

The type of the related model in the foreign key collection.

`S`

The type of the model used by the custom data loader.

`LoadForeignKeyField` <T, R, S>(T, IRelmContext, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>, Expression<Func<R, object>>)

Loads a foreign key collection property for the specified target model, resolving related entities based on the provided predicate and constraints.

```
public static T LoadForeignKeyField<T, R, S>(this T target, IRelmContext realmContext,
Expression<Func<T, ICollection<R>>> predicate, IRelmDataLoader<S> customDataLoader,
```



```
Expression<Func<R, object>> additionalConstraints) where T : IRelmModel, new() where R :  
IRelmModel, new() where S : IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key field will be loaded.

realmContext [IRelmContext](#)

The context used to manage the data loading operation.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the foreign key collection property on the target model.

customDataLoader [IRelmDataLoader](#) <S>

A custom data loader used to resolve the related entities.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#)>>

An expression specifying additional constraints to apply when resolving the related entities.

Returns

T

The target model instance with the foreign key field loaded.

Type Parameters

T

The type of the target model. Must implement [IRelmModel](#).

R

The type of the related model in the foreign key collection. Must implement [IRelmModel](#).

S

The type of the model used by the custom data loader. Must implement [IRelmModel](#).

Remarks

This method facilitates the loading of related entities for a foreign key collection property on the target model. The `customDataLoader` allows for custom logic to be applied during the data loading process, and the `additionalConstraints` can be used to further filter the related entities.

LoadForeignKeyField<T, R, S>(T, IRelmContext, Expression<Func<T, R>>, IRelmDataLoader<S>)

Loads and assigns a foreign key field for the specified target model using the provided data loader.

```
public static T LoadForeignKeyField<T, R, S>(this T target, IRelmContext relmContext,
Expression<Func<T, R>> predicate, IRelmDataLoader<S> customDataLoader) where T : IRelmModel,
new() where R : IRelmModel, new() where S : IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key field will be loaded.

relmContext [IRelmContext](#)

The context used to configure the data loading operation.

predicate [Expression](#) <[Func](#) <T, R>>

An expression identifying the foreign key field to be loaded.

customDataLoader [IRelmDataLoader](#) <S>

A custom data loader used to retrieve the foreign key model.

Returns

T

The target model instance with the foreign key field loaded and assigned.

Type Parameters

T

The type of the target model. Must implement [IRelmModel](#).

R

The type of the foreign key model. Must implement [IRelmModel](#).

S

The type of the model used by the custom data loader. Must implement [IRelmModel](#).

LoadForeignKeyField<T, R, S>(T, IRelmContext,
Expression<Func<T, R>>, IRelmDataLoader<S>,
Expression<Func<R, object>>)

Loads and initializes a foreign key field for the specified model, using the provided data loader and constraints.

```
public static T LoadForeignKeyField<T, R, S>(this T target, IRelmContext relmContext,  
Expression<Func<T, R>> predicate, IRelmDataLoader<S> customDataLoader, Expression<Func<R,  
object>> additionalConstraints) where T : IRelmModel, new() where R : IRelmModel, new()  
where S : IRelmModel, new()
```

Parameters

target T

The instance of the model for which the foreign key field is being loaded.

relmContext [IRelmContext](#)

The context used to manage the data loading operation.

predicate [Expression](#) <[Func](#) <T, R>>

An expression identifying the foreign key field to be loaded.

customDataLoader [IRelmDataLoader](#)<S>

A custom data loader used to retrieve the related data.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#)>>

An expression specifying additional constraints to apply when loading the related data.

Returns

T

The updated instance of the model with the foreign key field loaded.

Type Parameters

T

The type of the model containing the foreign key field. Must implement [IRelmModel](#).

R

The type of the related model referenced by the foreign key. Must implement [IRelmModel](#).

S

The type of the model used by the custom data loader. Must implement [IRelmModel](#).

Remarks

This method provides a way to load and initialize a foreign key field for a model, allowing for custom data loading and additional constraints. It is particularly useful in scenarios where the default data loading behavior needs to be customized or extended.

LoadForeignKeyField<T, R, S>(T, IRelmQuickContext, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>)

Loads and initializes a foreign key collection property for the specified target model, using the provided data loader and predicate.

```
public static T LoadForeignKeyField<T, R, S>(this T target, IRelmQuickContext relmContext,
Expression<Func<T, ICollection<R>>> predicate, IRelmDataLoader<S> customDataLoader) where T
: IRelmModel, new() where R : IRelmModel, new() where S : IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key field will be loaded.

realmContext [IRelmQuickContext](#)

The context providing configuration and options for the operation.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R> > >

An expression specifying the foreign key collection property on the target model.

customDataLoader [IRelmDataLoader](#) <S>

A custom data loader used to retrieve the related data.

Returns

T

The target model instance with the foreign key field loaded.

Type Parameters

T

The type of the target model. Must implement [IRelmModel](#).

R

The type of the related model in the foreign key collection. Must implement [IRelmModel](#).

S

The type of the model used by the custom data loader. Must implement [IRelmModel](#).

Remarks

This method is an extension method that simplifies the process of loading and initializing foreign key fields for models in a relational context. The **customDataLoader** is used to retrieve the related data, and the **predicate** specifies the foreign key collection to be populated.

```
LoadForeignKeyField<T, R, S>(T, IRelmQuickContext,  
Expression<Func<T, ICollection<R> > >, IRelmDataLoader<S>,  
Expression<Func<R, object> >)
```

Loads and populates a foreign key collection property for the specified target model using the provided data loader and constraints.

```
public static T LoadForeignKeyField<T, R, S>(this T target, IRelmQuickContext relmContext,
Expression<Func<T, ICollection<R>>> predicate, IRelmDataLoader<S> customDataLoader,
Expression<Func<R, object>> additionalConstraints) where T : IRelmModel, new() where R :
IRelmModel, new() where S : IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key field will be loaded.

relmContext [IRelmQuickContext](#)

The context providing configuration and services for data loading.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression identifying the foreign key collection property on the target model.

customDataLoader [IRelmDataLoader](#) <S>

A custom data loader used to retrieve the related data.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#)>>

An expression specifying additional constraints to apply when loading the related data.

Returns

T

The target model instance with the foreign key field populated.

Type Parameters

T

The type of the target model that contains the foreign key field. Must implement [IRelmModel](#).

R

The type of the related model in the foreign key collection. Must implement [IRelmModel](#).

S

The type of the model used by the custom data loader. Must implement [IRelmModel](#).

Remarks

This method is an extension method that simplifies the process of loading related data for a foreign key field. It uses the provided `customDataLoader` and `additionalConstraints` to retrieve and populate the related data.

LoadForeignKeyField<T, R, S>(T, IRelmQuickContext, Expression<Func<T, R>>, IRelmDataLoader<S>)

Loads and initializes a foreign key field for the specified model using the provided data loader and context.

```
public static T LoadForeignKeyField<T, R, S>(this T target, IRelmQuickContext relmContext,
Expression<Func<T, R>> predicate, IRelmDataLoader<S> customDataLoader) where T : IRelmModel,
new() where R : IRelmModel, new() where S : IRelmModel, new()
```

Parameters

`target` T

The target model instance for which the foreign key field will be loaded.

`relmContext` [IRelmQuickContext](#)

The context providing configuration and options for the operation.

`predicate` [Expression](#) <[Func](#) <T, R>>

An expression identifying the foreign key field to be loaded.

`customDataLoader` [IRelmDataLoader](#) <S>

A custom data loader used to retrieve the foreign key field data.

Returns

T

The target model instance with the specified foreign key field loaded.

Type Parameters

T

The type of the target model. Must implement [IRelmModel](#).

R

The type of the foreign key field to be loaded. Must implement [IRelmModel](#).

S

The type of the model used by the custom data loader. Must implement [IRelmModel](#).

Remarks

This method is an extension method that simplifies the process of loading foreign key fields for models in the Relm framework. It delegates the operation to an overload that uses the context options from the provided `relmContext`.

LoadForeignKeyField<T, R, S>(T, IRelmQuickContext, Expression<Func<T, R>>, IRelmDataLoader<S>, Expression<Func<R, object>>)

Loads and initializes a foreign key field for the specified target model using the provided context, predicate, and data loader.

```
public static T LoadForeignKeyField<T, R, S>(this T target, IRelmQuickContext relmContext,
Expression<Func<T, R>> predicate, IRelmDataLoader<S> customDataLoader, Expression<Func<R,
object>> additionalConstraints) where T : IRelmModel, new() where R : IRelmModel, new()
where S : IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key field will be loaded.

realmContext [IRelmQuickContext](#)

The context used to configure and manage the data loading operation.

predicate [Expression](#) <[Func](#) <T, R> >

An expression identifying the foreign key field to be loaded on the target model.

customDataLoader [IRelmDataLoader](#) <S>

A custom data loader used to retrieve the foreign key data.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#) > >

An optional expression specifying additional constraints to apply when loading the foreign key data.

Returns

T

The target model instance with the specified foreign key field loaded and initialized.

Type Parameters

T

The type of the target model. Must implement [IRelmModel](#).

R

The type of the foreign key model. Must implement [IRelmModel](#).

S

The type of the model used by the custom data loader. Must implement [IRelmModel](#).

Remarks

This method is an extension method that simplifies the process of loading foreign key fields in models. It delegates the operation to an overload that uses the context options from the provided **realmContext**.

LoadForeignKeyField<T, R, S>(T, RelmContextOptionsBuilder, Expression<Func<T, ICollection<R> > >, IRelmDataLoader<S>)

Loads a foreign key collection property for the specified target model using the provided predicate and custom data loader.

```
public static T LoadForeignKeyField<T, R, S>(this T target, RelmContextOptionsBuilder  
    relmContextOptionsBuilder, Expression<Func<T, ICollection<R>>> predicate, IRelmDataLoader<S>  
    customDataLoader) where T : IRelmModel, new() where R : IRelmModel, new() where S :  
    IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key field is being loaded.

relmContextOptionsBuilder [RelmContextOptionsBuilder](#)

The options builder used to configure the data loading context.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the foreign key collection property on the target model.

customDataLoader [IRelmDataLoader](#)<S>

A custom data loader used to retrieve the related data.

Returns

T

The first related model from the foreign key collection, or [null](#) if no related models are found.

Type Parameters

T

The type of the target model. Must implement [IRelmModel](#).

R

The type of the related model in the foreign key collection. Must implement [IRelmModel](#).

S

The type of the model used by the custom data loader. Must implement [IRelmModel](#).

Remarks

This method uses a `SimpleRelm.RelmInternal.Helpers.Utilities.ForeignKeyLoader<T>` to load the foreign key field based on the specified predicate and custom data loader. The method is designed to return only the first related model from the collection.

LoadForeignKeyField<T, R, S>(T, RelmContextOptionsBuilder, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>, Expression<Func<R, object>>)

Loads a foreign key collection property for the specified target model, applying the given constraints and using a custom data loader.

```
public static T LoadForeignKeyField<T, R, S>(this T target, RelmContextOptionsBuilder
relmContextOptionsBuilder, Expression<Func<T, ICollection<R>>> predicate, IRelmDataLoader<S>
customDataLoader, Expression<Func<R, object>> additionalConstraints) where T : IRelmModel,
new() where R : IRelmModel, new() where S : IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key field is being loaded.

relmContextOptionsBuilder [RelmContextOptionsBuilder](#)

The options builder used to configure the context for data loading.

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <R>>>

An expression specifying the navigation property on the target model that represents the foreign key relationship.

customDataLoader [IRelmDataLoader](#) <S>

The custom data loader used to retrieve the related data.

additionalConstraints [Expression](#) <[Func](#) <R, [object](#)>>

An expression specifying additional constraints to apply when loading the related data.

Returns

T

The first related entity that matches the specified constraints, or [null](#) if no matching entity is found.

Type Parameters

T

The type of the target model that implements [IRelmModel](#).

R

The type of the related model that implements [IRelmModel](#).

S

The type of the model used by the custom data loader that implements [IRelmModel](#).

LoadForeignKeyField<T, R, S>(T, RelmContextOptionsBuilder, Expression<Func<T, R>>, IRelmDataLoader<S>)

Loads a foreign key field for the specified target model using the provided predicate and data loader.

```
public static T LoadForeignKeyField<T, R, S>(this T target, RelmContextOptionsBuilder
relmContextOptionsBuilder, Expression<Func<T, R>> predicate, IRelmDataLoader<S>
customDataLoader) where T : IRelmModel, new() where R : IRelmModel, new() where S :
IRelmModel, new()
```

Parameters

target T

The target model instance for which the foreign key field is being loaded.

relmContextOptionsBuilder [RelmContextOptionsBuilder](#)

The options builder used to configure the context for data loading.

predicate [Expression](#) <[Func](#) <T, R>>

An expression that specifies the foreign key field to load.

`customDataLoader` [IRelmDataLoader](#)<S>

A custom data loader used to retrieve the related data.

Returns

T

The first related model of type **R** loaded for the specified foreign key field, or [null](#) if no related data is found.

Type Parameters

T

The type of the target model. Must implement [IRelmModel](#).

R

The type of the related model represented by the foreign key. Must implement [IRelmModel](#).

S

The type of the model used by the custom data loader. Must implement [IRelmModel](#).

Remarks

This method uses a `SimpleRelm.RelmInternal.Helpers.Utilities.ForeignKeyLoader<T>` to load the foreign key field based on the provided predicate and custom data loader. The method returns the first related model found, or [null](#) if no data matches.

`LoadForeignKeyField<T, R, S>(T, RelmContextOptionsBuilder, Expression<Func<T, R>>, IRelmDataLoader<S>, Expression<Func<R, object>>)`

Loads a foreign key field for the specified target model using the provided predicate, data loader, and additional constraints.

```
public static T LoadForeignKeyField<T, R, S>(this T target, RelmContextOptionsBuilder
relmContextOptionsBuilder, Expression<Func<T, R>> predicate, IRelmDataLoader<S>
customDataLoader, Expression<Func<R, object>> additionalConstraints) where T : IRelmModel,
new() where R : IRelmModel, new() where S : IRelmModel, new()
```

Parameters

target `T`

The target model instance for which the foreign key field is being loaded.

realmContextOptionsBuilder [RealmContextOptionsBuilder](#)

The options builder used to configure the context for the operation.

predicate [Expression](#) `<Func <T, R>>`

An expression specifying the foreign key property on the target model.

customDataLoader [IRelmDataLoader](#) `<S>`

A custom data loader used to retrieve the related data.

additionalConstraints [Expression](#) `<Func <R, object>>`

An expression specifying additional constraints to apply when loading the foreign key field.

Returns

`T`

The first related model that matches the specified predicate and constraints, or [null](#) if no match is found.

Type Parameters

`T`

The type of the target model. Must implement [IRelmModel](#) and have a parameterless constructor.

`R`

The type of the related model representing the foreign key. Must implement [IRelmModel](#) and have a parameterless constructor.

`S`

The type of the model used by the custom data loader. Must implement [IRelmModel](#) and have a parameterless constructor.

Namespace SimpleRealm.Interfaces

Interfaces

[IRelmContext](#)

[IRelmDataLoader<T>](#)

Defines methods and properties for loading, writing, and managing data, as well as executing commands with associated expressions.

[IRelmDataSetBase](#)

[IRelmDataSet<T>](#)

[IRelmExecutionCommand](#)

[IRelmFieldLoader](#)

[IRelmFieldLoaderBase](#)

[IRelmMember](#)

[IRelmModel](#)

Defines the contract for a Realm-compatible model, providing properties and methods for managing entity state, database interactions, and data transfer object (DTO) generation.

[IRelmModelApartment](#)

Interface IRealmContext

Namespace: [SimpleRealm.Interfaces](#)

Assembly: SimpleRealm.dll

```
public interface IRealmContext
```

Extension Methods

[DbContextExtensions.SetLockWaitTimeout\(IRealmContext, int\)](#)

Properties

ContextOptions

```
RealmContextOptionsBuilder ContextOptions { get; }
```

Property Value

[RealmContextOptionsBuilder](#)

Methods

BulkTableWrite<T>(T, string, MySqlConnection, Type, int, bool, bool, bool)

```
int BulkTableWrite<T>(T SourceData, string TableName = null, MySqlConnection sqlTransaction  
= null, Type ForceType = null, int BatchSize = 100, bool allowAutoIncrementColumns = false,  
bool allowPrimaryKeyColumns = false, bool allowUniqueColumns = false)
```

Parameters

SourceData T

TableName [string](#) 

sqlTransaction MySqlConnection

ForceType [Type](#)

BatchSize [int](#)

allowAutoIncrementColumns [bool](#)

allowPrimaryKeyColumns [bool](#)

allowUniqueColumns [bool](#)

Returns

[int](#)

Type Parameters

T

CommitTransaction()

```
void CommitTransaction()
```

DoDatabaseWork(string, Dictionary<string, object>, bool, bool)

```
void DoDatabaseWork(string QueryString, Dictionary<string, object> Parameters = null, bool  
throwException = true, bool useTransaction = false)
```

Parameters

QueryString [string](#)

Parameters [Dictionary](#) <[string](#), [object](#)>

throwException [bool](#)

useTransaction [bool](#)

DoDatabaseWork(string, Func<MySqlCommand, object>, bool, bool)

```
void DoDatabaseWork(string QueryString, Func<MySqlCommand, object> ActionCallback, bool  
throwException = true, bool useTransaction = false)
```

Parameters

QueryString [string](#)

ActionCallback [Func](#) <MySqlCommand, [object](#)>

throwException [bool](#)

useTransaction [bool](#)

DoDatabaseWork<T>(string, Dictionary<string, object>, bool, bool)

```
T DoDatabaseWork<T>(string QueryString, Dictionary<string, object> Parameters = null, bool  
throwException = true, bool useTransaction = false)
```

Parameters

QueryString [string](#)

Parameters [Dictionary](#) <[string](#), [object](#)>

throwException [bool](#)

useTransaction [bool](#)

Returns

T

Type Parameters

T

DoDatabaseWork<T>(string, Func<MySQLCommand, object>, bool, bool)

```
T DoDatabaseWork<T>(string QueryString, Func<MySQLCommand, object> ActionCallback, bool  
throwException = true, bool useTransaction = false)
```

Parameters

QueryString [string](#)

ActionCallback [Func](#) <MySQLCommand, [object](#)>

throwException [bool](#)

useTransaction [bool](#)

Returns

T

Type Parameters

T

EndConnection(bool)

```
void EndConnection(bool commitTransaction = true)
```

Parameters

commitTransaction [bool](#)

FirstOrDefault<T>(Expression<Func<T, bool>>, bool)

```
T FirstOrDefault<T>(Expression<Func<T, bool>> predicate, bool loadDataLoaders = false) where  
T : IRelmModel, new()
```

Parameters

`predicate` [Expression](#) <[Func](#) <T, [bool](#)>>

`loadDataLoaders` [bool](#)

Returns

T

Type Parameters

T

GetBulkTableWriter<T>(string, bool, bool, bool, bool, bool)

```
BulkTableWriter<T> GetBulkTableWriter<T>(string InsertQuery = null, bool useTransaction =  
false, bool throwException = true, bool allowAutoIncrementColumns = false, bool  
allowPrimaryKeyColumns = false, bool allowUniqueColumns = false)
```

Parameters

`InsertQuery` [string](#)

`useTransaction` [bool](#)

`throwException` [bool](#)

`allowAutoIncrementColumns` [bool](#)

`allowPrimaryKeyColumns` [bool](#)

`allowUniqueColumns` [bool](#)

Returns

[BulkTableWriter](#)<T>

Type Parameters

T

GetDataList<T>(string, Dictionary<string, object>, bool)

```
IEnumerable<T> GetDataList<T>(string QueryString, Dictionary<string, object> Parameters =  
null, bool throwException = true)
```

Parameters

QueryString [string](#)

Parameters [Dictionary](#) <[string](#), [object](#)>

throwException [bool](#)

Returns

[IEnumerable](#) <T>

Type Parameters

T

GetObject<T>(string, Dictionary<string, object>, bool)

```
T GetObject<T>(string QueryString, Dictionary<string, object> Parameters = null, bool  
throwException = true) where T : IRelmModel, new()
```

Parameters

QueryString [string](#)

Parameters [Dictionary](#) <[string](#), [object](#)>

throwException [bool](#)

Returns

T

Type Parameters

T

GetDataObjects<T>(string, Dictionary<string, object>, bool)

```
IEnumerable<T> GetDataObjects<T>(string QueryString, Dictionary<string, object> Parameters =  
null, bool throwException = true) where T : IRealmModel, new()
```

Parameters

QueryString [string](#)

Parameters [Dictionary](#) <[string](#), [object](#)>

throwException [bool](#)

Returns

[IEnumerable](#) <T>

Type Parameters

T

GetDataRow(string, Dictionary<string, object>, bool)

```
DataRow GetDataRow(string QueryString, Dictionary<string, object> Parameters = null, bool  
throwException = true)
```

Parameters

QueryString [string](#)

Parameters [Dictionary](#) <[string](#), [object](#)>

throwException [bool](#)

Returns

[DataRow](#)

GetDataSet(Type)

`IRealmDataSetBase GetDataSet(Type dataSetType)`

Parameters

`dataSetType` [Type](#)↗

Returns

[IRealmDataSetBase](#)

GetDataSet(Type, bool)

`IRealmDataSetBase GetDataSet(Type dataSetType, bool throwException)`

Parameters

`dataSetType` [Type](#)↗

`throwException` [bool](#)↗

Returns

[IRealmDataSetBase](#)

GetDataSetType(Type)

`IRealmDataSetBase GetDataSetType(Type dataSetType)`

Parameters

`dataSetType` [Type](#)↗

Returns

[IRelmDataSetBase](#)

GetDataSetType(Type, bool)

```
IRelmDataSetBase GetDataSetType(Type dataSetType, bool throwException)
```

Parameters

dataSetType [Type](#)[↗]

throwException [bool](#)[↗]

Returns

[IRelmDataSetBase](#)

GetDataSetType<T>()

```
IRelmDataSet<T> GetDataSetType<T>() where T : IRelmModel, new()
```

Returns

[IRelmDataSet](#)<T>

Type Parameters

T

GetDataSetType<T>(bool)

```
IRelmDataSet<T> GetDataSetType<T>(bool throwException) where T : IRelmModel, new()
```

Parameters

`throwException` [bool](#)

Returns

[IRelmDataSet](#)<T>

Type Parameters

T

GetDataSet<T>()

```
IRelmDataSet<T> GetDataSet<T>() where T : IRelmModel, new()
```

Returns

[IRelmDataSet](#)<T>

Type Parameters

T

GetDataSet<T>(bool)

```
IRelmDataSet<T> GetDataSet<T>(bool throwException) where T : IRelmModel, new()
```

Parameters

`throwException` [bool](#)

Returns

[IRelmDataSet](#)<T>

Type Parameters

T

GetDataTable(string, Dictionary<string, object>, bool)

```
DataTable GetDataTable(string QueryString, Dictionary<string, object> Parameters = null,  
bool throwException = true)
```

Parameters

QueryString [string](#)

Parameters [Dictionary](#) <[string](#), [object](#)>

throwException [bool](#)

Returns

[DataTable](#)

GetIdFromInternalId(string, string)

```
string GetIdFromInternalId(string Table, string InternalId)
```

Parameters

Table [string](#)

InternalId [string](#)

Returns

[string](#)

GetLastInsertId()

```
string GetLastInsertId()
```

Returns

[string](#)

GetScalar<T>(string, Dictionary<string, object>, bool)

```
T GetScalar<T>(string query, Dictionary<string, object> parameters = null, bool  
throwException = true)
```

Parameters

query [string](#)

parameters [Dictionary](#) <[string](#), [object](#)>

throwException [bool](#)

Returns

T

Type Parameters

T

Get<T>(bool)

```
ICollection<T> Get<T>(bool loadDataLoaders = false) where T : IRelmModel, new()
```

Parameters

loadDataLoaders [bool](#)

Returns

[ICollection](#) <T>

Type Parameters

T

Get<T>(Expression<Func<T, bool>>, bool)

```
ICollection<T> Get<T>(Expression<Func<T, bool>> predicate, bool loadDataLoaders = false)  
where T : IRelmModel, new()
```

Parameters

predicate [Expression](#) <[Func](#) <T, [bool](#)>>

loadDataLoaders [bool](#)

Returns

[ICollection](#) <T>

Type Parameters

T

HasDataSet(Type, bool)

```
bool HasDataSet(Type dataSetType, bool throwException = true)
```

Parameters

dataSetType [Type](#)

throwException [bool](#)

Returns

[bool](#)

HasDataSet<T>(bool)

```
bool HasDataSet<T>(bool throwException = true) where T : IRealmModel, new()
```

Parameters

throwException [bool](#)

Returns

[bool](#)

Type Parameters

T

RollbackTransaction()

```
void RollbackTransaction()
```

RollbackTransactions()

```
void RollbackTransactions()
```

Run<T>(string, Dictionary<string, object>)

```
ICollection<T> Run<T>(string query, Dictionary<string, object> parameters = null) where T :  
IRealmModel, new()
```

Parameters

query [string](#)

parameters [Dictionary](#) <[string](#), [object](#)>

Returns

[ICollection](#) <T>

Type Parameters

T

SetDataLoader<T>(IRelmDataLoader<T>)

```
void SetDataLoader<T>(IRelmDataLoader<T> dataLoader) where T : RelmModel, new()
```

Parameters

dataLoader [IRelmDataLoader](#) <T>

Type Parameters

T

StartConnection(bool, int)

```
void StartConnection(bool autoOpenTransaction = false, int lockWaitTimeoutSeconds = 0)
```

Parameters

autoOpenTransaction [bool](#)

lockWaitTimeoutSeconds [int](#)

Where<T>(Expression<Func<T, bool>>)

```
IRelmDataSet<T> Where<T>(Expression<Func<T, bool>> predicate) where T : IRelmModel, new()
```

Parameters

predicate [Expression](#) <[Func](#) <T, [bool](#)>>

Returns

[IRelmDataSet](#)<T>

Type Parameters

T

WriteToDatabase(IRelmModel, int, bool, bool, bool, bool)

```
int WriteToDatabase(IRelmModel relmModel, int batchSize = 100, bool  
allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool  
allowUniqueColumns = false, bool allowAutoDateColumns = false)
```

Parameters

relmModel [IRelmModel](#)

batchSize [int](#)

allowAutoIncrementColumns [bool](#)

allowPrimaryKeyColumns [bool](#)

allowUniqueColumns [bool](#)

allowAutoDateColumns [bool](#)

Returns

[int](#)

WriteToDatabase(IEnumerable<IRelmModel>, int, bool, bool, bool, bool)

```
int WriteToDatabase(IEnumerable<IRelmModel> relmModels, int batchSize = 100, bool  
allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool  
allowUniqueColumns = false, bool allowAutoDateColumns = false)
```

Parameters

realmModels [IEnumerable<IRelmModel>](#)

batchSize [int](#)

allowAutoIncrementColumns [bool](#)

allowPrimaryKeyColumns [bool](#)

allowUniqueColumns [bool](#)

allowAutoDateColumns [bool](#)

Returns

[int](#)

Interface IRealmDataLoader<T>

Namespace: [SimpleRealm.Interfaces](#)

Assembly: SimpleRealm.dll

Defines methods and properties for loading, writing, and managing data, as well as executing commands with associated expressions.

```
public interface IRealmDataLoader<T>
```

Type Parameters

T

The type of data managed by the loader.

Properties

LastCommandsExecuted

Gets or sets the collection of the most recently executed commands and their associated execution details.

```
Dictionary<Commands.Command, List<IRealmExecutionCommand>> LastCommandsExecuted { get; set; }
```

Property Value

[Dictionary](#)[↗] <[Commands.Command](#), [List](#)[↗] <[IRealmExecutionCommand](#)>>

Remarks

This property provides a record of the last executed commands along with their execution details. It can be used to analyze or inspect the history of command executions.

Methods

AddExpression(Command, Expression)

Adds an expression to the specified command and returns the resulting execution command.

```
IRealmExecutionCommand AddExpression(Commands.Command command, Expression expression)
```

Parameters

command [Commands.Command](#)

The command to which the expression will be added. Cannot be null.

expression [Expression](#) 

The expression to add to the command. Cannot be null.

Returns

[IRealmExecutionCommand](#)

An [IRealmExecutionCommand](#) representing the updated execution command with the added expression.

AddSingleExpression(Command, Expression)

Adds a single expression to the specified command and returns the resulting execution command.

```
IRealmExecutionCommand AddSingleExpression(Commands.Command command, Expression expression)
```

Parameters

command [Commands.Command](#)

The command to which the expression will be added. Cannot be [null](#) .

expression [Expression](#) 

The expression to add to the command. Cannot be [null](#) .

Returns

[IRelmExecutionCommand](#)

An [IRelmExecutionCommand](#) representing the updated command with the added expression.

GetLoadData()

Retrieves a collection of data items of type **T**.

```
ICollection<T> GetLoadData()
```

Returns

[ICollection](#)  <T>

A collection of data items of type **T**. The collection will be empty if no data is available.

Remarks

The returned collection contains the data items that are to be loaded. The collection may be empty if no data is available.

HasUnderscoreProperty(string)

Determines whether the specified property key contains an underscore.

```
bool HasUnderscoreProperty(string propertyKey)
```

Parameters

propertyKey [string](#) 

The property key to check. Cannot be null or empty.

Returns

[bool](#) 

[true](#)  if the property key contains at least one underscore; otherwise, [false](#) .

WriteData()

Writes data to the underlying storage and returns the number of rows written.

```
int WriteData()
```

Returns

[int](#)

The number of rows successfully written to the storage.

Interface IRealmDataSetBase

Namespace: [SimpleRealm.Interfaces](#)

Assembly: SimpleRealm.dll

```
public interface IRealmDataSetBase
```

Interface IRealmDataSet<T>

Namespace: [SimpleRelm.Interfaces](#)

Assembly: SimpleReIm.dll

```
public interface IRelmDataSet<T> : ICollection<T>, IEnumerable<T>, IEnumerable,
IRelmDataSetBase where T : IRelmModel, new()
```

Type Parameters

T

Inherited Members

[ICollection<T>.Clear\(\)](#), [ICollection<T>.Contains\(T\)](#), [ICollection<T>.CopyTo\(T\[\],int\)](#), [ICollection<T>.Remove\(T\)](#), [ICollection<T>.Count](#), [ICollection<T>.IsReadOnly](#), [IEnumerable<T>.GetEnumerator\(\)](#)

Extension Methods

[ListExtensions.LoadDataLoaderField<T, R>\(ICollection<T>, IRealmContext, Expression<Func<T, R>>\),](#)
[ListExtensions.LoadDataLoaderField<T, R>\(ICollection<T>, IRealmQuickContext, Expression<Func<T,](#)
[R>>\),](#)
[ListExtensions.LoadDataLoaderField<T, R>\(ICollection<T>, RealmContextOptionsBuilder,](#)
[Expression<Func<T, R>>\),](#)
[ListExtensions.LoadForeignKeyField<T, R>\(ICollection<T>, IRealmContext, Expression<Func<T,](#)
[ICollection<R>>>\),](#)
[ListExtensions.LoadForeignKeyField<T, R>\(ICollection<T>, IRealmContext, Expression<Func<T,](#)
[ICollection<R>>>, Expression<Func<R, object>>\),](#)
[ListExtensions.LoadForeignKeyField<T, R>\(ICollection<T>, IRealmContext, Expression<Func<T, R>>\),](#)
[ListExtensions.LoadForeignKeyField<T, R>\(ICollection<T>, IRealmContext, Expression<Func<T, R>>,](#)
[Expression<Func<R, object>>\),](#)
[ListExtensions.LoadForeignKeyField<T, R>\(ICollection<T>, IRealmQuickContext, Expression<Func<T,](#)
[ICollection<R>>>\),](#)
[ListExtensions.LoadForeignKeyField<T, R>\(ICollection<T>, IRealmQuickContext, Expression<Func<T,](#)
[ICollection<R>>>, Expression<Func<R, object>>\),](#)
[ListExtensions.LoadForeignKeyField<T, R>\(ICollection<T>, IRealmQuickContext, Expression<Func<T, R>>\),](#)
[ListExtensions.LoadForeignKeyField<T, R>\(ICollection<T>, IRealmQuickContext, Expression<Func<T, R>>,](#)
[Expression<Func<R, object>>\),](#)

[ListExtensions.LoadForeignKeyField<T, R>\(ICollection<T>, RelmContextOptionsBuilder, Expression<Func<T, ICollection<R>>>\),](#)
[ListExtensions.LoadForeignKeyField<T, R>\(ICollection<T>, RelmContextOptionsBuilder, Expression<Func<T, ICollection<R>>>, Expression<Func<R, object>>\),](#)
[ListExtensions.LoadForeignKeyField<T, R>\(ICollection<T>, RelmContextOptionsBuilder, Expression<Func<T, R>>\),](#)
[ListExtensions.LoadForeignKeyField<T, R>\(ICollection<T>, RelmContextOptionsBuilder, Expression<Func<T, R>>, Expression<Func<R, object>>\),](#)
[ListExtensions.LoadForeignKeyField<T, R, S>\(ICollection<T>, IRelmContext, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>\),](#)
[ListExtensions.LoadForeignKeyField<T, R, S>\(ICollection<T>, IRelmContext, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>, Expression<Func<R, object>>\),](#)
[ListExtensions.LoadForeignKeyField<T, R, S>\(ICollection<T>, IRelmContext, Expression<Func<T, R>>, IRelmDataLoader<S>\),](#)
[ListExtensions.LoadForeignKeyField<T, R, S>\(ICollection<T>, IRelmContext, Expression<Func<T, R>>, IRelmDataLoader<S>, Expression<Func<R, object>>\),](#)
[ListExtensions.LoadForeignKeyField<T, R, S>\(ICollection<T>, IRelmQuickContext, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>\),](#)
[ListExtensions.LoadForeignKeyField<T, R, S>\(ICollection<T>, IRelmQuickContext, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>, Expression<Func<R, object>>\),](#)
[ListExtensions.LoadForeignKeyField<T, R, S>\(ICollection<T>, IRelmQuickContext, Expression<Func<T, R>>, IRelmDataLoader<S>\),](#)
[ListExtensions.LoadForeignKeyField<T, R, S>\(ICollection<T>, IRelmQuickContext, Expression<Func<T, R>>, IRelmDataLoader<S>, Expression<Func<R, object>>\),](#)
[ListExtensions.LoadForeignKeyField<T, R, S>\(ICollection<T>, RelmContextOptionsBuilder, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>\),](#)
[ListExtensions.LoadForeignKeyField<T, R, S>\(ICollection<T>, RelmContextOptionsBuilder, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>, Expression<Func<R, object>>\),](#)
[ListExtensions.LoadForeignKeyField<T, R, S>\(ICollection<T>, RelmContextOptionsBuilder, Expression<Func<T, R>>, IRelmDataLoader<S>\),](#)
[ListExtensions.LoadForeignKeyField<T, R, S>\(ICollection<T>, RelmContextOptionsBuilder, Expression<Func<T, R>>, IRelmDataLoader<S>, Expression<Func<R, object>>\),](#)
[ListExtensions.FlattenTreeObject<T>\(IEnumerable<T>, Func<T, ICollection<T>>\),](#)
[ListExtensions.GenerateDTO<T>\(IEnumerable<T>, ICollection<string>, ICollection<string>, string, Func<IRelmModel, Dictionary<string, object>>\),](#)
[ListExtensions.WriteToDatabase<T>\(IEnumerable<T>, MySqlConnection, MySqlTransaction, string, Type, int, string, bool, bool, bool, bool\),](#)
[ListExtensions.WriteToDatabase<T>\(IEnumerable<T>, IRelmContext, string, Type, int, string, bool, bool, bool, bool\),](#)

[ListExtensions.WriteToDatabase<T>\(IEnumerable<T>, IRelmQuickContext, string, Type, int, string, bool, bool, bool, bool\) ,](#)
[ListExtensions.WriteToDatabase<T>\(IEnumerable<T>, Enum, string, Type, bool, int, string, bool, bool, bool, bool\)](#)

Methods

Add(ICollection<T>)

```
int Add(ICollection<T> items)
```

Parameters

items [ICollection](#)<T>

Returns

[int](#)

Add(ICollection<T>, bool)

```
int Add(ICollection<T> items, bool Persist)
```

Parameters

items [ICollection](#)<T>

Persist [bool](#)

Returns

[int](#)

Add(T)


```
int Add(T item)
```

Parameters

item T

Returns

[int](#)

Add(T, bool)

```
int Add(T item, bool Persist)
```

Parameters

item T

Persist [bool](#)

Returns

[int](#)

DistinctBy(Expression<Func<T, object>>)

```
IRealmDataSet<T> DistinctBy(Expression<Func<T, object>> predicate)
```

Parameters

predicate [Expression](#) <[Func](#) <T, [object](#)>>

Returns

[IRealmDataSet](#) <T>

Entry(T)

```
IRealmDataSet<T> Entry(T Item)
```

Parameters

Item T

Returns

[IRealmDataSet](#)<T>

Entry(T, bool)

```
IRealmDataSet<T> Entry(T Item, bool Persist = true)
```

Parameters

Item T

Persist [bool](#)

Returns

[IRealmDataSet](#)<T>

Find(int)

```
T Find(int ItemId)
```

Parameters

ItemId [int](#)

Returns

T

Find(string)

```
T Find(string ItemInternalId)
```

Parameters

ItemInternalId [string](#)

Returns

T

FirstOrDefault()

```
T FirstOrDefault()
```

Returns

T

FirstOrDefault(bool)

```
T FirstOrDefault(bool LoadItems)
```

Parameters

LoadItems [bool](#)

Returns

T

FirstOrDefault(Expression<Func<T, bool>>)

```
T FirstOrDefault(Expression<Func<T, bool>> predicate)
```

Parameters

predicate [Expression](#) <[Func](#) <T, [bool](#)>>

Returns

T

FirstOrDefault(Expression<Func<T, bool>>, bool)

```
T FirstOrDefault(Expression<Func<T, bool>> predicate, bool LoadItems)
```

Parameters

predicate [Expression](#) <[Func](#) <T, [bool](#)>>

LoadItems [bool](#)

Returns

T

GroupBy(Expression<Func<T, object>>)

```
IRealmDataSet<T> GroupBy(Expression<Func<T, object>> predicate)
```

Parameters

predicate [Expression](#) <[Func](#) <T, [object](#)>>

Returns

[IRealmDataSet](#) <T>

Limit(int)

`IRealmDataSet<T> Limit(int LimitCount)`

Parameters

`LimitCount` [int](#)

Returns

[IRealmDataSet](#)<T>

Load()

`ICollection<T> Load()`

Returns

[ICollection](#)<T>

Load(bool)

`ICollection<T> Load(bool loadDataLoaders)`

Parameters

`loadDataLoaders` [bool](#)

Returns

[ICollection](#)<T>

LoadAsDataSet()

`IRealmDataSet<T> LoadAsDataSet()`

Returns

[IRelmDataSet](#)<T>

New(bool)

```
T New(bool Persist = true)
```

Parameters

Persist [bool](#)

Returns

T

New(dynamic, bool)

```
T New(dynamic NewObjectParameters, bool Persist = true)
```

Parameters

NewObjectParameters dynamic

Persist [bool](#)

Returns

T

OrderBy(Expression<Func<T, object>>)

```
IRelmDataSet<T> OrderBy(Expression<Func<T, object>> predicate)
```

Parameters

predicate [Expression](#) <[Func](#) <T, [object](#)>>>

Returns

[IRelmDataSet](#)<T>

OrderByDescending(Expression<Func<T, object>>)

[IRelmDataSet](#)<T> **OrderByDescending**(Expression<Func<T, [object](#)>> predicate)

Parameters

predicate [Expression](#) <[Func](#) <T, [object](#)>>>

Returns

[IRelmDataSet](#)<T>

Reference<S>(Expression<Func<T, ICollection<S>>>, ICollection<Expression<Func<S, object>>>)

[IRelmDataSet](#)<T> **Reference**<S>(Expression<Func<T, ICollection<S>>> predicate, ICollection<Expression<Func<S, [object](#)>>> additionalConstraints)

Parameters

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <S>>>>

additionalConstraints [ICollection](#) <[Expression](#) <[Func](#) <S, [object](#)>>>>

Returns

[IRelmDataSet](#)<T>

Type Parameters

S

Reference<S>(Expression<Func<T, ICollection<S>>>, Expression<Func<S, object>>)

```
IRealmDataSet<T> Reference<S>(Expression<Func<T, ICollection<S>>> predicate,  
Expression<Func<S, object>>> additionalConstraints)
```

Parameters

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <S>>>

additionalConstraints [Expression](#) <[Func](#) <S, [object](#)>>

Returns

[IRealmDataSet](#) <T>

Type Parameters

S

Reference<S>(Expression<Func<T, S>>)

```
IRealmDataSet<T> Reference<S>(Expression<Func<T, S>> predicate)
```

Parameters

predicate [Expression](#) <[Func](#) <T, S>>

Returns

[IRealmDataSet](#) <T>

Type Parameters

S

Reference<S>(Expression<Func<T, S>>, ICollection<Expression<Func<S, object>>>)

```
IRealmDataSet<T> Reference<S>(Expression<Func<T, S>> predicate,
    ICollection<Expression<Func<S, object>>> additionalConstraints)
```

Parameters

predicate [Expression](#) <[Func](#) <T, S>>

additionalConstraints [ICollection](#) <[Expression](#) <[Func](#) <S, [object](#)>>>

Returns

[IRealmDataSet](#) <T>

Type Parameters

S

Reference<S>(Expression<Func<T, S>>, Expression<Func<S, object>>)

```
IRealmDataSet<T> Reference<S>(Expression<Func<T, S>> predicate, Expression<Func<S,
    object>> additionalConstraints)
```

Parameters

predicate [Expression](#) <[Func](#) <T, S>>

additionalConstraints [Expression](#) <[Func](#) <S, [object](#)>>

Returns

[IRealmDataSet](#) <T>

Type Parameters

S

Save()

```
int Save()
```

Returns

[int](#)

Save(T)

```
int Save(T Item)
```

Parameters

Item T

Returns

[int](#)

Set(Expression<Func<T, T>>)

```
IRealmDataSet<T> Set(Expression<Func<T, T>> predicate)
```

Parameters

predicate [Expression](#) <[Func](#) <T, T>>

Returns

[IRealmDataSet](#) <T>

SetDataLoader(IRealmDataLoader<T>)

```
IRealmDataLoader<T> SetDataLoader(IRealmDataLoader<T> dataLoader)
```

Parameters

dataLoader [IRealmDataLoader](#)<T>

Returns

[IRealmDataLoader](#)<T>

SetFieldLoader(string, IRealmFieldLoader)

```
IRealmFieldLoader SetFieldLoader(string fieldName, IRealmFieldLoader dataLoader)
```

Parameters

fieldName [string](#)[↗]

dataLoader [IRealmFieldLoader](#)

Returns

[IRealmFieldLoader](#)

Where(Expression<Func<T, bool>>)

```
IRealmDataSet<T> Where(Expression<Func<T, bool>> predicate)
```

Parameters

predicate [Expression](#)[↗] <[Func](#)[↗] <T, [bool](#)[↗]>>

Returns

[IRealmDataSet](#)<T>

Write()

```
int Write()
```

Returns

[int](#)

Interface IRelmExecutionCommand

Namespace: [SimpleRelm.Interfaces](#)

Assembly: SimpleRelm.dll

```
public interface IRelmExecutionCommand
```

Properties

AdditionalCommandCount

```
int AdditionalCommandCount { get; }
```

Property Value

[int](#)

InitialCommand

```
Commands.Command InitialCommand { get; }
```

Property Value

[Commands.Command](#)

InitialExpression

```
Expression InitialExpression { get; }
```

Property Value

[Expression](#)

Methods

AddAdditionalCommand(Command, Expression)

RealmExecutionCommand **AddAdditionalCommand**(Commands.Command command, Expression expression)

Parameters

command [Commands.Command](#)

expression [Expression](#) 

Returns

[RealmExecutionCommand](#)

GetAdditionalCommands()

List<RealmExecutionCommand> **GetAdditionalCommands**()

Returns

[List](#)  <[RealmExecutionCommand](#)>

GetForeignKeyNavigationOptions<T>(ICollection<T>)

ForeignKeyNavigationOptions **GetForeignKeyNavigationOptions**<T>(ICollection<T> _items)

Parameters

_items [ICollection](#)  <T>

Returns

[ForeignKeyNavigationOptions](#)

Type Parameters

T

Interface IRealmFieldLoader

Namespace: [SimpleRealm.Interfaces](#)

Assembly: SimpleRealm.dll

```
public interface IRealmFieldLoader : IRealmFieldLoaderBase
```

Inherited Members

[IRealmFieldLoaderBase.FieldName](#) , [IRealmFieldLoaderBase.KeyFields](#) ,
[IRealmFieldLoaderBase.GetFieldData<S>\(ICollection<S\[\]>\)](#).

Properties

RealmContext

```
IRealmContext RealmContext { get; }
```

Property Value

[IRealmContext](#)

Interface IRealmFieldLoaderBase

Namespace: [SimpleRealm.Interfaces](#)

Assembly: SimpleRealm.dll

```
public interface IRealmFieldLoaderBase
```

Properties

FieldName

```
string FieldName { get; }
```

Property Value

[string](#) 

KeyFields

```
string[] KeyFields { get; }
```

Property Value

[string](#)  []

Methods

GetFieldData<S>(ICollection<S[]>)

```
Dictionary<S[], object> GetFieldData<S>(ICollection<S[]> keyData)
```

Parameters

keyData [ICollection](#) <S[]>

Returns

[Dictionary](#) <S[], [object](#)>

Type Parameters

S

Interface IRealmMember

Namespace: [SimpleRealm.Interfaces](#)

Assembly: SimpleRealm.dll

```
public interface IRealmMember
```

Properties

Email

```
string Email { get; set; }
```

Property Value

[string](#) 

Id

```
long Id { get; set; }
```

Property Value

[long](#) 

Login

```
string Login { get; set; }
```

Property Value

[string](#) 

Name

```
string Name { get; set; }
```

Property Value

[string](#)

Methods

GetValue<T>()

```
T GetValue<T>()
```

Returns

T

Type Parameters

T

SetValue<T>(T)

```
void SetValue<T>(T value)
```

Parameters

value T

Type Parameters

T

Interface IRealmModel

Namespace: [SimpleRealm.Interfaces](#)

Assembly: SimpleRealm.dll

Defines the contract for a Realm-compatible model, providing properties and methods for managing entity state, database interactions, and data transfer object (DTO) generation.

```
public interface IRealmModel
```

Remarks

This interface is designed to represent a database entity with common attributes such as identifiers, timestamps, and active state. It also includes methods for resetting attributes, writing data to the database, and generating dynamic DTOs. Implementations of this interface are expected to handle database-specific operations and provide fine-grained control over column constraints during write operations.

Properties

Active

Gets or sets a value indicating whether the entity is active.

```
bool Active { get; set; }
```

Property Value

[bool](#)

CreateDate

Gets or sets the date and time when the entity was created.

```
DateTime CreateDate { get; set; }
```

Property Value

[DateTime](#)↗

Id

Gets or sets the database row identifier for the entity.

```
long? Id { get; set; }
```

Property Value

[long](#)↗?

Remarks

This ID corresponds to the primary key in the database table.

InternalId

Gets or sets the internal identifier for the entity.

```
string InternalId { get; set; }
```

Property Value

[string](#)↗

Remarks

This GUID identifier is globally unique and is intended to uniquely identify this entity across all platforms.

LastUpdated

Gets or sets the date and time when the object was last updated.

```
DateTime LastUpdated { get; set; }
```

Property Value

[DateTime](#)

Methods

GenerateDTO(IEnumerable<string>, IEnumerable<string>, string, Func<IRelmModel, Dictionary<string, object>>, int)

Generates a dynamic Data Transfer Object (DTO) based on the specified properties and additional configuration.

```
dynamic GenerateDTO(IEnumerable<string> includeProperties = null, IEnumerable<string>
excludeProperties = null, string sourceObjectName = null, Func<IRelmModel,
Dictionary<string, object>> getAdditionalObjectProperties = null, int iteration = 0)
```

Parameters

includeProperties [IEnumerable](#) <[string](#)>

A collection of property names to include in the generated DTO. If [null](#), all properties are included by default.

excludeProperties [IEnumerable](#) <[string](#)>

A collection of property names to exclude from the generated DTO. If [null](#), no properties are excluded.

sourceObjectName [string](#)

The name of the source object from which the DTO is generated. Can be [null](#) if the source object name is not required.

getAdditionalObjectProperties [Func](#) <[IRelmModel](#), [Dictionary](#) <[string](#), [object](#)>>

A function that takes an [IRelmModel](#) instance and returns a dictionary of additional properties to include in the DTO. If [null](#), no additional properties are added.

iteration [int](#)

The current iteration count, used to track recursive or iterative calls. Defaults to 0.

Returns

dynamic

A dynamic object representing the generated DTO, including the specified properties and any additional properties provided.

Remarks

The method allows fine-grained control over the properties included in the DTO by specifying inclusion and exclusion lists. If both `includeProperties` and `excludeProperties` are provided, the exclusion list takes precedence.

GetUnderscoreProperties(bool)

Retrieves a list of properties with each name converted to underscore case.

```
List<KeyValuePair<string, Tuple<string, PropertyInfo>>> GetUnderscoreProperties(bool  
getOnlyRealmColumns = true)
```

Parameters

`getOnlyRealmColumns` [bool](#)

A boolean value indicating whether to include only properties marked as Realm columns. If [true](#), only Realm column properties are included; otherwise, all underscore-prefixed properties are included.

Returns

[List](#) < [KeyValuePair](#) < [string](#), [Tuple](#) < [string](#), [PropertyInfo](#) > > >

A list of key-value pairs where the key is the property name, and the value is a tuple containing the property's metadata string and its [PropertyInfo](#).

ResetCoreAttributes(bool, bool)

Resets the core attributes of the model to their default values.

```
IRealmModel ResetCoreAttributes(bool nullInternalId = false, bool resetCreateDate = true)
```


Parameters

nullInternalId [bool](#)

A value indicating whether the internal ID should be set to [null](#). Pass [true](#) to nullify the internal ID; otherwise, [false](#).

resetCreateDate [bool](#)

A value indicating whether the creation date should be reset to the current date and time. Pass [true](#) to reset the creation date; otherwise, [false](#).

Returns

[IRelmModel](#)

The updated model instance with the core attributes reset.

Remarks

Resets fields [Id](#), [Active](#), [InternalId](#), and [CreateDate](#).

ResetWithData(DataRow, string)

Resets the current model's state using the specified data and optionally sets an alternate table name.

```
IRelmModel ResetWithData(DataRow modelData, string alternateTableName = null)
```

Parameters

modelData [DataRow](#)

The [DataRow](#) containing the data to reset the model with. Cannot be [null](#).

alternateTableName [string](#)

An optional alternate table name to associate with the model. If [null](#), the default table name is used.

Returns

[IRelmModel](#)

An updated instance of the model implementing [IRealmModel](#) with the new data applied.

WriteToDatabase(MySqlConnection, MySqlConnection, int, bool, bool, bool, bool)

Writes data to the database using the specified connection and optional transaction.

```
int WriteToDatabase(MySqlConnection existingConnection, MySqlConnection sqlTransaction
= null, int BatchSize = 10, bool allowAutoIncrementColumns = false, bool
allowPrimaryKeyColumns = false, bool allowUniqueColumns = false, bool allowAutoDateColumns
= false)
```

Parameters

existingConnection MySqlConnection

An open `MySql.Data.MySqlClient.MySqlConnection` to the database where the data will be written. The connection must remain open for the duration of the operation.

sqlTransaction MySqlConnection

An optional `MySql.Data.MySqlClient.MySqlTransaction` to use for the operation. If null, the operation will not be part of a transaction.

BatchSize [int](#)

The number of rows to write in each batch. Must be greater than zero. Defaults to 10.

allowAutoIncrementColumns [bool](#)

A value indicating whether columns with auto-increment constraints are allowed to be written. If [true](#), auto-increment columns will be included; otherwise, they will be excluded.

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns are allowed to be written. If [true](#), primary key columns will be included; otherwise, they will be excluded.

allowUniqueColumns [bool](#)

A value indicating whether unique columns are allowed to be written. If [true](#), unique columns will be included; otherwise, they will be excluded.

allowAutoDateColumns [bool](#)

A value indicating whether columns with automatic date generation constraints are allowed to be written. If [true](#), such columns will be included; otherwise, they will be excluded.

Returns

[int](#)

The number of rows successfully written to the database.

WriteToDatabase(IRelmContext, int, bool, bool, bool, bool)

Writes data to the database using the specified context and batch size, with options to control column behavior.

```
int WriteToDatabase(IRelmContext relmContext, int batchSize = 10, bool
allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool
allowUniqueColumns = false, bool allowAutoDateColumns = false)
```

Parameters

relmContext [IRelmContext](#)

The database context used to perform the write operation. This cannot be [null](#).

batchSize [int](#)

The number of records to write in each batch. Must be greater than 0. The default value is 10.

allowAutoIncrementColumns [bool](#)

If [true](#), allows writing to columns with auto-increment constraints; otherwise, these columns are ignored.

allowPrimaryKeyColumns [bool](#)

If [true](#), allows writing to primary key columns; otherwise, these columns are ignored.

allowUniqueColumns [bool](#)

If [true](#), allows writing to columns with unique constraints; otherwise, these columns are ignored.

allowAutoDateColumns [bool](#)

If [true](#), allows writing to columns with automatic date generation constraints; otherwise, these columns are ignored.

Returns

[int](#)

The number of records successfully written to the database.

Remarks

This method provides fine-grained control over how data is written to the database by allowing or disallowing writes to specific types of columns. Use the optional parameters to customize the behavior based on the constraints of your database schema.

WriteToDatabase(IRelmQuickContext, int, bool, bool, bool, bool)

Writes data to the database using the specified context and batch size, with options to control column constraints.

```
int WriteToDatabase(IRelmQuickContext relmQuickContext, int batchSize = 10, bool
allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool
allowUniqueColumns = false, bool allowAutoDateColumns = false)
```

Parameters

relmQuickContext [IRelmQuickContext](#)

The database context used to perform the write operation. This context must be properly initialized before calling this method.

batchSize [int](#)

The number of records to write in each batch. Must be greater than zero. The default value is 10.

allowAutoIncrementColumns [bool](#)

A value indicating whether auto-increment columns are allowed during the write operation. If [true](#), auto-increment columns will be included; otherwise, they will be excluded.

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns are allowed during the write operation. If [true](#), primary key columns will be included; otherwise, they will be excluded.

allowUniqueColumns [bool](#)

A value indicating whether unique columns are allowed during the write operation. If [true](#), unique columns will be included; otherwise, they will be excluded.

allowAutoDateColumns [bool](#)

A value indicating whether auto-date columns are allowed during the write operation. If [true](#), auto-date columns will be included; otherwise, they will be excluded.

Returns

[int](#)

The total number of records successfully written to the database.

Remarks

This method provides fine-grained control over which types of columns are included during the write operation. Use the boolean parameters to enable or disable specific column constraints as needed.

WriteToDatabase(Enum, int, bool, bool, bool, bool)

Writes data to the specified database connection in batches.

```
int WriteToDatabase(Enum connectionName, int batchSize = 10, bool allowAutoIncrementColumns  
= false, bool allowPrimaryKeyColumns = false, bool allowUniqueColumns = false, bool  
allowAutoDateColumns = false)
```

Parameters

connectionName [Enum](#)

The name of the database connection to use. Must be a valid connection identifier.

batchSize [int](#)

The number of records to write in each batch. Defaults to 10. Must be greater than 0.

allowAutoIncrementColumns [bool](#)

Indicates whether auto-increment columns are allowed in the data being written. Defaults to [false](#).

allowPrimaryKeyColumns [bool](#)

Indicates whether primary key columns are allowed in the data being written. Defaults to [false](#).

allowUniqueColumns [bool](#)

Indicates whether unique columns are allowed in the data being written. Defaults to [false](#).

allowAutoDateColumns [bool](#)

Indicates whether auto-generated date columns are allowed in the data being written. Defaults to [false](#).

Returns

[int](#)

The number of records successfully written to the database.

Remarks

This method writes data to the database in batches to optimize performance. Ensure that the specified connection is valid and that the data conforms to the constraints specified by the parameter flags. If any of the flags are set to [true](#), the corresponding column types will be allowed in the data being written.

Interface IRealmModelApartment

Namespace: [SimpleRealm.Interfaces](#)

Assembly: SimpleRealm.dll

```
public interface IRealmModelApartment
```

Properties

ApartmentId

```
string ApartmentId { get; set; }
```

Property Value

[string](#) 

Member

```
IRealmMember Member { get; set; }
```

Property Value

[IRealmMember](#)

UserEmail

```
string UserEmail { get; set; }
```

Property Value

[string](#) 

UserId

```
int UserId { get; set; }
```

Property Value

[int](#)↗

UserName

```
string UserName { get; set; }
```

Property Value

[string](#)↗

Namespace SimpleRealm.Interfaces.RealmQuick

Interfaces

[IRealmQuickContext](#)

Defines a context for interacting with a Realm database, providing methods for managing connections, transactions, and data operations. This interface supports querying, data manipulation, and bulk operations while ensuring proper resource management.

[IRealmQuickFieldLoader](#)

Interface IRelmQuickContext

Namespace: [SimpleRelm.Interfaces.RelmQuick](#)

Assembly: SimpleRelm.dll

Defines a context for interacting with a Relm database, providing methods for managing connections, transactions, and data operations. This interface supports querying, data manipulation, and bulk operations while ensuring proper resource management.

```
public interface IRelmQuickContext : IDisposable
```

Inherited Members

[IDisposable.Dispose\(\)](#) 

Remarks

Implementations of this interface are designed to facilitate database operations in a structured and transactional manner. The context provides methods for starting and ending connections, managing transactions, and performing CRUD operations on data sets. It also includes support for executing raw queries and bulk operations. The interface extends [IDisposable](#)  to ensure that resources are properly released when the context is no longer needed. Thread safety is not guaranteed unless explicitly stated by the implementation. Users should ensure proper synchronization when accessing the context from multiple threads.

Properties

ContextOptions

Gets the builder used to configure options for the current Relm context.

```
RelmContextOptionsBuilder ContextOptions { get; }
```

Property Value

[RelmContextOptionsBuilder](#)

Methods

BulkTableWrite<T>(T, string, MySqlConnection, Type, int, bool, bool, bool)

Performs a bulk write operation to insert or update data in the specified database table.

```
int BulkTableWrite<T>(T sourceData, string tableName = null, MySqlConnection sqlTransaction = null, Type forceType = null, int batchSize = 100, bool allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool allowUniqueColumns = false)
```

Parameters

sourceData T

The data to be written to the table. Must not be null. If a collection is provided, each item will be processed in the bulk operation.

tableName [string](#)

The name of the target database table. If null, the table name will be inferred from the type T.

sqlTransaction MySqlConnection

An optional MySql.Data.MySqlClient.MySqlTransaction to associate the bulk write operation with an existing transaction. If null, the operation will execute without a transaction.

forceType [Type](#)

An optional [Type](#) to explicitly specify the type of the data being written. If null, the type will be inferred from T.

batchSize [int](#)

The maximum number of rows to include in each batch during the bulk write operation. Must be greater than zero. Defaults to 100.

allowAutoIncrementColumns [bool](#)

Indicates whether auto-increment columns in the target table are allowed to be explicitly written. Defaults to [false](#).

allowPrimaryKeyColumns [bool](#)

Indicates whether primary key columns in the target table are allowed to be explicitly written. Defaults to [false](#).

`allowUniqueColumns` [bool](#)

Indicates whether unique columns in the target table are allowed to be explicitly written. Defaults to [false](#).

Returns

[int](#)

The number of rows successfully written to the database table.

Type Parameters

T

The type of the source data. This can be a collection or a single object representing the data to be written.

Remarks

This method is optimized for high-performance bulk operations and supports optional batching to handle large datasets efficiently. Ensure that the source data aligns with the schema of the target table to avoid runtime errors.

CommitTransaction()

Commits the current transaction, making all changes permanent in the database.

```
void CommitTransaction()
```

DoDatabaseWork(string, Dictionary<string, object>, bool, bool)

Executes a database operation using the specified query and parameters.

```
void DoDatabaseWork(string query, Dictionary<string, object> parameters = null, bool  
throwException = true, bool useTransaction = false)
```

Parameters

query [string](#)

The SQL query to execute. Cannot be null or empty.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. If null, no parameters are applied.

throwException [bool](#)

A value indicating whether an exception should be thrown if the operation fails. If [true](#), an exception is thrown on failure; otherwise, the failure is silently handled.

useTransaction [bool](#)

A value indicating whether the operation should be executed within a transaction. If [true](#), the operation is wrapped in a transaction; otherwise, it is executed without one.

Remarks

This method allows for executing parameterized SQL queries with optional transaction support. Use the **throwException** parameter to control error handling behavior.

DoDatabaseWork(string, Func<MySQLCommand, object>, bool, bool)

Executes a database operation using the specified query and callback function.

```
void DoDatabaseWork(string query, Func<MySQLCommand, object> actionCallback, bool  
throwException = true, bool useTransaction = false)
```

Parameters

query [string](#)

The SQL query to execute. Must not be null or empty.

actionCallback [Func](#) <MySQLCommand, [object](#)>

A callback function that processes the MySQL.Data.MySqlClient.MySqlCommand object and returns a result. The callback must not be null.

throwException [bool](#)

A value indicating whether to throw an exception if an error occurs during the operation. If [true](#), exceptions will be thrown; otherwise, errors will be suppressed.

useTransaction [bool](#)

A value indicating whether the operation should be executed within a database transaction. If [true](#), the operation will be wrapped in a transaction; otherwise, it will not.

Remarks

This method provides a flexible way to execute database operations by allowing the caller to define custom logic through the **actionCallback** parameter. Ensure that the **query** is properly sanitized to prevent SQL injection attacks.

DoDatabaseWork<T>(string, Dictionary<string, object>, bool, bool)

Executes a database query and returns the result as the specified type.

```
T DoDatabaseWork<T>(string query, Dictionary<string, object> parameters = null, bool  
throwException = true, bool useTransaction = false)
```

Parameters

query [string](#)

The SQL query to execute. Cannot be null or empty.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to include in the query. Can be null if no parameters are required.

throwException [bool](#)

Specifies whether an exception should be thrown if the query fails. If [true](#), an exception is thrown on failure; otherwise, the method returns the default value of **T**.

useTransaction [bool](#)

Specifies whether the query should be executed within a transaction. If [true](#), the query is executed in a transactional context; otherwise, it is executed without a transaction.

Returns

T

The result of the query as an instance of type **T**. Returns the default value of **T** if `throwException` is [false](#) and the query fails.

Type Parameters

T

The type of the result expected from the query.

Remarks

Use this method to execute queries that return a single result, such as scalar values or objects. Ensure that the type **T** matches the expected result of the query to avoid runtime errors.

DoDatabaseWork<T>(string, Func<MySqlCommand, object>, bool, bool)

Executes a database operation using the specified query and callback function.

```
T DoDatabaseWork<T>(string query, Func<MySqlCommand, object> actionCallback, bool  
throwException = true, bool useTransaction = false)
```

Parameters

query [string](#)

The SQL query to be executed. Cannot be null or empty.

actionCallback [Func](#)<MySqlCommand, [object](#)>

A callback function that defines the operation to perform with the `MySQL.Data.MySqlClient.MySqlCommand` object. The function should return an object of type **T**.

throwException [bool](#)

A value indicating whether an exception should be thrown if an error occurs during the operation. The default value is [true](#).

useTransaction [bool](#)

A value indicating whether the operation should be executed within a database transaction. The default value is [false](#).

Returns

T

The result of the operation, as returned by the **actionCallback** function.

Type Parameters

T

The type of the result returned by the callback function.

Remarks

This method provides a flexible way to execute database operations by allowing the caller to define the specific action to perform using the provided `MySQL.Data.MySqlClient.MySqlCommand` object. If **useTransaction** is [true](#), the operation will be executed within a transaction, which will be committed or rolled back based on the success or failure of the operation.

EndConnection(bool)

Ends the current connection and optionally commits any active transaction.

```
void EndConnection(bool commitTransaction = true)
```

Parameters

commitTransaction [bool](#)

A value indicating whether to commit the active transaction before ending the connection. [true](#) to commit the transaction; [false](#) to roll it back. The default is [true](#).

Remarks

Use this method to cleanly terminate a connection. If a transaction is active, you can specify whether to commit or roll it back before the connection is closed. Ensure that any necessary operations are completed before calling this method, as the connection will no longer be available afterward.

FirstOrDefault<T>(Expression<Func<T, bool>>, bool)

Retrieves the first element of a sequence from the data source that satisfies the specified condition, or a default value if no such element is found.

```
T FirstOrDefault<T>(Expression<Func<T, bool>> predicate, bool loadDataLoaders = false) where  
T : IRelmModel, new()
```

Parameters

predicate [Expression](#) <[Func](#) <T, [bool](#)>>

An expression that defines the condition to test each element for.

loadDataLoaders [bool](#)

A boolean value indicating whether to load associated data loaders for the retrieved element. If [true](#), data loaders will be initialized; otherwise, they will not be loaded.

Returns

T

The first element of type **T** that satisfies the specified condition, or the default value of **T** if no such element is found.

Type Parameters

T

The type of the elements in the sequence. Must implement [IRelmModel](#) and have a parameterless constructor.

GetBulkTableWriter<T>(string, bool, bool, bool, bool, bool)

Creates and returns a [BulkTableWriter<T>](#) instance for performing bulk insert operations on a database table.

```
BulkTableWriter<T> GetBulkTableWriter<T>(string insertQuery = null, bool useTransaction =  
false, bool throwException = true, bool allowAutoIncrementColumns = false, bool  
allowPrimaryKeyColumns = false, bool allowUniqueColumns = false)
```

Parameters

insertQuery [string](#) 

An optional SQL insert query to use for the bulk operation. If [null](#) , a default query is generated based on the type **T**.

useTransaction [bool](#) 

Specifies whether the bulk operation should be performed within a transaction. If [true](#) , the operation is transactional; otherwise, it is not.

throwException [bool](#) 

Specifies whether exceptions should be thrown if an error occurs during the bulk operation. If [true](#) , exceptions are thrown; otherwise, errors are suppressed.

allowAutoIncrementColumns [bool](#) 

Indicates whether auto-increment columns in the database table are allowed to be included in the bulk operation. If [true](#) , these columns are included; otherwise, they are excluded.

allowPrimaryKeyColumns [bool](#) 

Indicates whether primary key columns in the database table are allowed to be included in the bulk operation. If [true](#) , these columns are included; otherwise, they are excluded.

allowUniqueColumns [bool](#) 

Indicates whether unique columns in the database table are allowed to be included in the bulk operation. If [true](#) , these columns are included; otherwise, they are excluded.

Returns

[BulkTableWriter<T>](#)

A [BulkTableWriter<T>](#) instance configured for the specified bulk operation settings.

Type Parameters

T

The type of the objects to be written to the database table. Each object represents a row in the table.

Remarks

The [BulkTableWriter<T>](#) provides an efficient way to insert large amounts of data into a database table. Use the optional parameters to customize the behavior of the bulk operation, such as enabling transactions or allowing specific column types.

GetDataList<T>(string, Dictionary<string, object>, bool)

Executes the specified query and retrieves a collection of data mapped to the specified type.

```
IEnumerable<T> GetDataList<T>(string query, Dictionary<string, object> parameters = null,  
bool throwException = true)
```

Parameters

query [string](#)

The SQL query to execute. Must not be null or empty.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. Can be null if no parameters are required.

throwException [bool](#)

A value indicating whether an exception should be thrown if the query fails. If [true](#), an exception will be thrown on failure; otherwise, the method will return an empty collection.

Returns

[IEnumerable](#) <T>

An [IEnumerable<T>](#) containing the results of the query mapped to the specified type. Returns an empty collection if no results are found or if **throwException** is [false](#) and the query fails.

Type Parameters

T

The type to which the query results will be mapped.

GetDataObject<T>(string, Dictionary<string, object>, bool)

Executes the specified query and retrieves a data object of the specified type.

```
T GetDataObject<T>(string query, Dictionary<string, object> parameters = null, bool  
throwException = true) where T : IRealmModel, new()
```

Parameters

query [string](#)

The query string used to retrieve the data object. Cannot be [null](#) or empty.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameters to be used in the query. Keys represent parameter names, and values represent their corresponding values.

throwException [bool](#)

A value indicating whether an exception should be thrown if the query fails or no data is found. If [true](#), an exception is thrown; otherwise, [default](#) is returned.

Returns

T

An instance of the specified type **T** populated with the data retrieved by the query. Returns [default](#) if no data is found and **throwException** is [false](#).

Type Parameters

T

The type of the data object to retrieve. Must implement [IRelmModel](#) and have a parameterless constructor.

GetDataObjects<T>(string, Dictionary<string, object>, bool)

Executes a query and retrieves a collection of data objects of the specified type.

```
IEnumerable<T> GetDataObjects<T>(string query, Dictionary<string, object> parameters = null,
bool throwException = true) where T : IRelmModel, new()
```

Parameters

query [string](#)

The query string used to retrieve the data objects. Cannot be null or empty.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. If null, no parameters are applied.

throwException [bool](#)

A boolean value indicating whether an exception should be thrown if the query fails. If [true](#), an exception is thrown on failure; otherwise, the method returns an empty collection.

Returns

[IEnumerable](#) <T>

An [IEnumerable<T>](#) containing the data objects retrieved by the query. Returns an empty collection if no data is found or if **throwException** is [false](#) and the query fails.

Type Parameters

T

The type of data objects to retrieve. Must implement [IRelmModel](#) and have a parameterless constructor.

GetDataRow(string, Dictionary<string, object>, bool)

Executes the specified query and retrieves the first row of the result set as a [DataRow](#).

```
DataRow GetDataRow(string query, Dictionary<string, object> parameters = null, bool  
throwException = true)
```

Parameters

query [string](#)

The SQL query to execute. Must be a valid SQL statement.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. If null, no parameters are applied.

throwException [bool](#)

A boolean value indicating whether an exception should be thrown if the query does not return any rows. If [true](#), an exception is thrown when no rows are found; otherwise, [null](#) is returned.

Returns

[DataRow](#)

A [DataRow](#) representing the first row of the result set, or [null](#) if no rows are found and **throwException** is set to [false](#).

GetDataSet(Type)

Retrieves an initialized instance of a dataset based on the specified type.

```
IRealmDataSetBase GetDataSet(Type dataSetType)
```

Parameters

dataSetType [Type](#)

The [Type](#) of the dataset to retrieve. This must be a type that implements [IRealmDataSetBase](#).

Returns

[IRealmDataSetBase](#)

An instance of the dataset that matches the specified type. Returns [null](#) if no matching dataset is found.

GetDataSet(Type, bool)

Retrieves an initialized instance of a dataset of the specified type.

```
IRealmDataSetBase GetDataSet(Type dataSetType, bool throwException)
```

Parameters

dataSetType [Type](#)

The [Type](#) of the dataset to retrieve. This must implement [IRealmDataSetBase](#).

throwException [bool](#)

A value indicating whether an exception should be thrown if the dataset cannot be found. If [true](#), an exception is thrown when the dataset is not found; otherwise, [null](#) is returned.

Returns

[IRealmDataSetBase](#)

An instance of [IRealmDataSetBase](#) representing the requested dataset, or [null](#) if the dataset is not found and **throwException** is [false](#).

GetDataSetType(Type)

Retrieves an uninitialized dataset of type specified by **dataSetType**.

```
IRealmDataSetBase GetDataSetType(Type dataSetType)
```

Parameters

dataSetType [Type](#)

The [Type](#) of the dataset to retrieve. This must implement [IRealmDataSetBase](#).

Returns

[IRelmDataSetBase](#)

An instance of [IRelmDataSetBase](#) that corresponds to the specified `dataSetType`.

GetDataSetType(Type, bool)

Retrieves an uninitialized dataset of type specified by `dataSetType`.

```
IRelmDataSetBase GetDataSetType(Type dataSetType, bool throwException)
```

Parameters

`dataSetType` [Type](#) 

The [Type](#)  of the dataset to retrieve. Must implement [IRelmDataSetBase](#).

`throwException` [bool](#) 

A boolean value indicating whether to throw an exception if the specified `dataSetType` is invalid. [true](#)  to throw an exception; otherwise, [false](#) .

Returns

[IRelmDataSetBase](#)

An instance of [IRelmDataSetBase](#) corresponding to the specified `dataSetType`. Returns [null](#)  if `throwException` is [false](#)  and the dataset type is invalid.

GetDataSetType<T>()

Retrieves an uninitialized dataset of the specified type.

```
IRelmDataSet<T> GetDataSetType<T>() where T : IRelmModel, new()
```

Returns

[IRelmDataSet](#)<T>

An instance of [IRelmDataSet<T>](#) representing the dataset of the specified type.

Type Parameters

T

The type of the dataset to retrieve. Must implement [IRelmModel](#) and have a parameterless constructor.

Remarks

This method is generic and allows retrieval of datasets for any type that satisfies the constraints.

GetDataSetType<T>(bool)

Retrieves an uninitialized dataset of the specified type.

```
IRelmDataSet<T> GetDataSetType<T>(bool throwException) where T : IRelmModel, new()
```

Parameters

throwException [bool](#) 

A value indicating whether an exception should be thrown if the dataset cannot be retrieved. If [true](#) , an exception is thrown; otherwise, [null](#)  may be returned.

Returns

[IRelmDataSet<T>](#)

An instance of [IRelmDataSet<T>](#) representing the dataset of the specified type, or [null](#)  if the dataset cannot be retrieved and **throwException** is [false](#) .

Type Parameters

T

The type of the dataset to retrieve. Must implement [IRelmModel](#) and have a parameterless constructor.

GetDataSet<T>()

Retrieves an initialized instance of a dataset of the specified type.

```
IRealmDataSet<T> GetDataSet<T>() where T : IRealmModel, new()
```

Returns

[IRealmDataSet<T>](#)

An instance of [IRealmDataSet<T>](#) containing the data for the specified type.

Type Parameters

T

The type of the dataset to retrieve. Must implement [IRealmModel](#) and have a parameterless constructor.

Remarks

Use this method to access a dataset for a specific model type. The type parameter **T** must represent a model that conforms to the [IRealmModel](#) interface.

GetDataSet<T>(bool)

Retrieves an initialized instance of a dataset of the specified type.

```
IRealmDataSet<T> GetDataSet<T>(bool throwException) where T : IRealmModel, new()
```

Parameters

throwException [bool](#) 

A value indicating whether an exception should be thrown if the dataset cannot be retrieved. If [true](#) , an exception is thrown on failure; otherwise, [null](#)  is returned.

Returns

[IRealmDataSet<T>](#)

An instance of [IRelmDataSet<T>](#) containing the dataset of type **T**. Returns [null](#) if the dataset cannot be retrieved and `throwException` is [false](#).

Type Parameters

T

The type of the dataset to retrieve. Must implement [IRelmModel](#) and have a parameterless constructor.

GetDataTable(string, Dictionary<string, object>, bool)

Executes the specified SQL query and returns the results as a [DataTable](#).

```
DataTable GetDataTable(string query, Dictionary<string, object> parameters = null, bool  
throwException = true)
```

Parameters

query [string](#)

The SQL query to execute. This must be a valid SQL statement.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. If provided, the parameters will be added to the query to prevent SQL injection. Defaults to [null](#).

throwException [bool](#)

A value indicating whether an exception should be thrown if an error occurs during query execution. If [true](#), exceptions will be propagated to the caller. If [false](#), the method will suppress exceptions and return [null](#) in case of an error. Defaults to [true](#).

Returns

[DataTable](#)

A [DataTable](#) containing the results of the query. Returns [null](#) if `throwException` is [false](#) and an error occurs during execution.

Remarks

This method is designed to execute read-only queries, such as SELECT statements. It is not intended for executing queries that modify data (e.g., INSERT, UPDATE, DELETE).

GetIdFromInternalId(string, string)

Converts an internal identifier to its corresponding row identifier for a specified table.

```
string GetIdFromInternalId(string table, string InternalId)
```

Parameters

table [string](#)

The name of the table containing the internal identifier. Cannot be null or empty.

InternalId [string](#)

The internal identifier to be converted. Cannot be null or empty.

Returns

[string](#)

The row identifier corresponding to the specified internal identifier and table.

GetLastInsertId()

Retrieves the row identifier of the most recently inserted record in the database.

```
string GetLastInsertId()
```

Returns

[string](#)

The identifier of the last inserted record as a string. The format and value depend on the database implementation.

Remarks

This method is typically used after an insert operation to obtain the unique identifier generated for the new record. Ensure that the database connection and context are properly configured before calling this method.

GetScalar<T>(string, Dictionary<string, object>, bool)

Executes the specified SQL query and retrieves a single scalar value of the specified type.

```
T GetScalar<T>(string query, Dictionary<string, object> parameters = null, bool  
throwException = true)
```

Parameters

query [string](#)

The SQL query to execute. Must not be null or empty.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to include in the query. If null, no parameters are added.

throwException [bool](#)

A boolean value indicating whether an exception should be thrown if the query fails. If [true](#), an exception is thrown on failure; otherwise, the default value of **T** is returned.

Returns

T

The scalar value of type **T** returned by the query. If the query does not return a result and **throwException** is [false](#), the default value of **T** is returned.

Type Parameters

T

The type of the scalar value to return.

Remarks

Use this method to retrieve a single value, such as a count or aggregate result, from a database query. Ensure that the query is written to return only one value; otherwise, an exception may occur.

Get<T>(bool)

Retrieves a collection of entities of type **T** from the data source.

```
ICollection<T> Get<T>(bool loadDataLoaders = false) where T : IRealmModel, new()
```

Parameters

loadDataLoaders [bool](#)

A boolean value indicating whether to load associated data loaders. If [true](#), data loaders will be initialized; otherwise, they will not.

Returns

[ICollection](#) <T>

A collection of objects of type **T**. The collection may be empty if no objects are found.

Type Parameters

T

The type of objects to retrieve. Must implement [IRealmModel](#) and have a parameterless constructor.

Get<T>(Expression<Func<T, bool>>, bool)

Retrieves a collection of entities of type **T** from the data source that satisfy the specified predicate.

```
ICollection<T> Get<T>(Expression<Func<T, bool>> predicate, bool loadDataLoaders = false)  
where T : IRealmModel, new()
```

Parameters

predicate [Expression](#) <[Func](#) <T, [bool](#)>>>

An expression that defines the conditions the entities must satisfy.

loadDataLoaders [bool](#)

A boolean value indicating whether to load associated data loaders for the retrieved entities. [true](#) to load data loaders; otherwise, [false](#).

Returns

[ICollection](#) <T>

A collection of entities of type **T** that match the specified predicate. Returns an empty collection if no entities match.

Type Parameters

T

The type of the entities to retrieve. Must implement [IRelmModel](#) and have a parameterless constructor.

HasDataSet(Type, bool)

Determines whether a dataset of the specified type is available.

```
bool HasDataSet(Type dataSetType, bool throwException = true)
```

Parameters

dataSetType [Type](#)

The [Type](#) of the dataset to check for availability. This parameter cannot be [null](#).

throwException [bool](#)

A value indicating whether an exception should be thrown if the dataset is not available. If [true](#), an exception is thrown when the dataset is not found; otherwise, the method returns [false](#).

Returns

[bool](#)

[true](#) if the dataset of the specified type is available; otherwise, [false](#).

HasDataSet<T>(bool)

Determines whether a dataset of the specified type exists in the current context.

```
bool HasDataSet<T>(bool throwException = true) where T : IReImModel, new()
```

Parameters

throwException [bool](#)

A value indicating whether to throw an exception if the dataset does not exist. [true](#) to throw an exception; [false](#) to return [false](#) instead.

Returns

[bool](#)

[true](#) if the dataset of the specified type exists; otherwise, [false](#).

Type Parameters

T

The type of the dataset to check for. Must implement [IReImModel](#) and have a parameterless constructor.

RollbackTransaction()

Rolls back the current transaction, undoing any changes made since the transaction began.

```
void RollbackTransaction()
```

Remarks

This method should be called to revert changes if an error occurs or if the transaction cannot be completed successfully. Ensure that a transaction is active before calling this method; otherwise, an exception may be thrown.

RollbackTransactions()

Rolls back the current transaction, undoing any changes made since the transaction began.

```
void RollbackTransactions()
```

Remarks

This method should be called to revert changes if an error occurs or if the transaction cannot be completed successfully. Ensure that a transaction is active before calling this method; otherwise, an exception may be thrown.

Run<T>(string, Dictionary<string, object>)

Executes the specified query and returns a collection of results mapped to the specified type.

```
ICollection<T> Run<T>(string query, Dictionary<string, object> parameters = null) where T :  
IRelmModel, new()
```

Parameters

query [string](#)

The query string to execute. This string must be a valid query in the context of the underlying data source.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. If null, no parameters are applied.

Returns

[ICollection](#) <T>

A collection of objects of type `T` representing the query results. The collection will be empty if no results are found.

Type Parameters

`T`

The type of the objects in the result collection. Must implement [IRelmModel](#) and have a parameterless constructor.

SetDataLoader<T>(IRelmDataLoader<T>)

Configures the data loader for the specified model type.

```
void SetDataLoader<T>(IRelmDataLoader<T> dataLoader) where T : IRelmModel, new()
```

Parameters

`dataLoader` [IRelmDataLoader](#)<T>

The data loader instance to associate with the specified model type. Cannot be [null](#).

Type Parameters

`T`

The type of the model that the data loader will handle. Must inherit from [RelmModel](#) and have a parameterless constructor.

StartConnection(bool, int)

Starts a connection to the database.

```
void StartConnection(bool autoOpenTransaction = false, int lockWaitTimeoutSeconds = 0)
```

Parameters

`autoOpenTransaction` [bool](#)

Specifies whether a transaction should be automatically opened after the connection is established. Pass [true](#) to open a transaction automatically; otherwise, [false](#).

lockWaitTimeoutSeconds [int](#)

The lock wait timeout in seconds. A value of 0 indicates the default timeout for the database. Specify a positive integer to set a custom timeout duration.

Remarks

If **autoOpenTransaction** is set to [true](#), ensure that the transaction is committed or rolled back to avoid leaving it open. This method must be called before performing any database operations.

Where<T>(Expression<Func<T, bool>>)

Retrieves data from the data source, filtered based on the specified predicate.

```
IRealmDataSet<T> Where<T>(Expression<Func<T, bool>> predicate) where T : IRealmModel, new()
```

Parameters

predicate [Expression](#) <[Func](#) <T, [bool](#)>>

An expression that defines the conditions for filtering the dataset.

Returns

[IRealmDataSet](#) <T>

A new dataset containing only the elements that satisfy the specified predicate.

Type Parameters

T

The type of the model in the dataset. Must implement [IRealmModel](#) and have a parameterless constructor.

Remarks

The predicate is evaluated for each element in the dataset, and only those elements for which the predicate returns [true](#) are included in the result.

WriteToDatabase(IRelmModel, int, bool, bool, bool, bool)

Writes the specified [IRelmModel](#) to the database in batches.

```
int WriteToDatabase(IRelmModel relmModel, int batchSize = 100, bool  
allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool  
allowUniqueColumns = false, bool allowAutoDateColumns = false)
```

Parameters

relmModel [IRelmModel](#)

The model containing the data to be written to the database. Cannot be [null](#).

batchSize [int](#)

The number of records to write in each batch. Must be greater than 0. The default value is 100.

allowAutoIncrementColumns [bool](#)

A value indicating whether columns with auto-increment constraints are allowed to be written. If [true](#), auto-increment columns will be included in the write operation; otherwise, they will be excluded.

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns are allowed to be written. If [true](#), primary key columns will be included in the write operation; otherwise, they will be excluded.

allowUniqueColumns [bool](#)

A value indicating whether columns with unique constraints are allowed to be written. If [true](#), unique columns will be included in the write operation; otherwise, they will be excluded.

allowAutoDateColumns [bool](#)

A value indicating whether columns with automatic date generation constraints are allowed to be written. If [true](#), auto-date columns will be included in the write operation; otherwise, they will be excluded.

Returns

[int](#)

The total number of records successfully written to the database.

Remarks

This method writes data to the database in batches to optimize performance. The behavior of the write operation can be customized using the boolean parameters to control the inclusion of specific column types.

WriteToDatabase(IEnumerable<IRelmModel>, int, bool, bool, bool, bool)

Writes a collection of Relm models to the database in batches.

```
int WriteToDatabase(IEnumerable<IRelmModel> relmModels, int batchSize = 100, bool allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool allowUniqueColumns = false, bool allowAutoDateColumns = false)
```

Parameters

relmModels [IEnumerable](#) <[IRelmModel](#)>

The collection of models to be written to the database. Each model must implement the [IRelmModel](#) interface.

batchSize [int](#)

The number of models to include in each batch. Must be a positive integer. The default value is 100.

allowAutoIncrementColumns [bool](#)

A value indicating whether columns with auto-increment constraints are allowed to be written. If [true](#), auto-increment columns will be included; otherwise, they will be excluded. The default value is [false](#).

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns are allowed to be written. If [true](#), primary key columns will be included; otherwise, they will be excluded. The default value is [false](#).

allowUniqueColumns [bool](#)

A value indicating whether columns with unique constraints are allowed to be written. If [true](#), unique columns will be included; otherwise, they will be excluded. The default value is [false](#).

allowAutoDateColumns [bool](#)

A value indicating whether columns with automatic date generation constraints are allowed to be written. If [true](#), auto-date columns will be included; otherwise, they will be excluded. The default value is [false](#).

Returns

[int](#)

The total number of models successfully written to the database.

Remarks

This method processes the provided models in batches to optimize database writes. The behavior of the write operation can be customized using the optional parameters to control which types of columns are included.

Interface IRealmQuickFieldLoader

Namespace: [SimpleRealm.Interfaces.RealmQuick](#)

Assembly: SimpleRealm.dll

```
public interface IRealmQuickFieldLoader : IRealmFieldLoaderBase
```

Inherited Members

[IRealmFieldLoaderBase.FieldName](#) , [IRealmFieldLoaderBase.KeyFields](#) ,
[IRealmFieldLoaderBase.GetFieldData<S>\(ICollection<S\[\]>\)](#).

Properties

RealmContext

```
IRealmQuickContext RealmContext { get; }
```

Property Value

[IRealmQuickContext](#)

Namespace SimpleReIm.Interfaces.Resolvers

Interfaces

[IReImResolverBase](#)

[IReImResolver_MySQL](#)

[IReImResolver_ODBC](#)

Interface IRealmResolverBase

Namespace: [SimpleRealm.Interfaces.Resolvers](#)

Assembly: SimpleRealm.dll

```
public interface IRealmResolverBase
```

Methods

GetConnectionStringBuilder(Enum)

```
DbConnectionStringBuilder GetConnectionStringBuilder(Enum ConnectionType)
```

Parameters

ConnectionType [Enum](#) 

Returns

[DbConnectionStringBuilder](#) 

GetConnectionStringBuilder(string)

```
DbConnectionStringBuilder GetConnectionStringBuilder(string ConnectionString)
```

Parameters

ConnectionString [string](#) 

Returns

[DbConnectionStringBuilder](#) 

Interface IRealmResolver_MySQL

Namespace: [SimpleRealm.Interfaces.Resolvers](#)

Assembly: SimpleRealm.dll

```
public interface IRealmResolver_MySQL : IRealmResolverBase
```

Inherited Members

[IRealmResolverBase.GetConnectionBuilder\(Enum\)](#) , [IRealmResolverBase.GetConnectionBuilder\(string\)](#).

Methods

GetConnectionBuilderFromConnectionString(string)

```
MySqlConnectionStringBuilder GetConnectionBuilderFromConnectionString(string  
connectionString)
```

Parameters

connectionString [string](#) 

Returns

MySqlConnectionStringBuilder

GetConnectionBuilderFromName(string)

```
MySqlConnectionStringBuilder GetConnectionBuilderFromName(string connectionString)
```

Parameters

ConnectionString [string](#) 

Returns

MySqlConnectionStringBuilder

GetConnectionBuilderFromType(Enum)

MySqlConnectionStringBuilder `GetConnectionBuilderFromType`(Enum ConnectionType)

Parameters

ConnectionType [Enum](#)

Returns

MySqlConnectionStringBuilder

Interface IRealmResolver_ODBC

Namespace: [SimpleRealm.Interfaces.Resolvers](#)

Assembly: SimpleRealm.dll

```
public interface IRealmResolver_ODBC : IRealmResolverBase
```

Methods

GetConnectionStringBuilder(Enum)

```
OdbcConnectionStringBuilder GetConnectionStringBuilder(Enum ConnectionType)
```

Parameters

ConnectionType [Enum](#) 

Returns

[OdbcConnectionStringBuilder](#) 

GetConnectionStringBuilder(string)

```
OdbcConnectionStringBuilder GetConnectionStringBuilder(string ConnectionString)
```

Parameters

ConnectionString [string](#) 

Returns

[OdbcConnectionStringBuilder](#) 

Namespace SimpleRelm.Models

Classes

[RelmContext](#)

[RelmDataSet<T>](#)

Represents a dataset that provides functionality for managing, querying, and persisting a collection of entities of type **T**.

[RelmDefaultDataLoader<T>](#)

Provides a default implementation of the [IRelmDataLoader<T>](#) interface for loading, querying, and writing data for a specified model type. This class is designed to work with models that implement the [IRelmModel](#) interface.

[RelmExecutionCommand](#)

[RelmModel](#)

Represents a base model for entities in the Relm framework, providing core attributes and functionality for data manipulation, database operations, and DTO generation.

[RelmModelApartment](#)

[RelmQuickContext](#)

[RelmTrigger<T>](#)

Represents a database trigger associated with a specific table and operation type.

Class RelmContext

Namespace: [SimpleRelm.Models](#)

Assembly: SimpleRelm.dll

```
public class RelmContext : IDisposable, IRelmContext
```

Inheritance

[object](#) ← RelmContext

Implements

[IDisposable](#), [IRelmContext](#)

Inherited Members

[object.ToString\(\)](#), [object.Equals\(object\)](#), [object.Equals\(object, object\)](#), [object.ReferenceEquals\(object, object\)](#), [object.GetHashCode\(\)](#), [object.GetType\(\)](#), [object.MemberwiseClone\(\)](#)

Extension Methods

[DbContextExtensions.SetLockWaitTimeout\(IRelmContext, int\)](#)

Constructors

RelmContext(MySqlConnection, MySqlConnectionTransaction, bool, bool, bool, int)

```
public RelmContext(MySqlConnection connection, MySqlConnectionTransaction transaction, bool  
autoOpenConnection = true, bool allowUserVariables = false, bool convertZeroDateTime =  
false, int lockWaitTimeoutSeconds = 0)
```

Parameters

connection MySqlConnection

transaction MySqlConnectionTransaction

autoOpenConnection [bool](#)

allowUserVariables [bool](#)

convertZeroDateTime [bool](#)

lockWaitTimeoutSeconds [int](#)

RelmContext(MySqlConnection, bool, bool, bool, bool, int)

```
public RelmContext(MySqlConnection connection, bool autoOpenConnection = true, bool autoOpenTransaction = false, bool allowUserVariables = false, bool convertZeroDateTime = false, int lockWaitTimeoutSeconds = 0)
```

Parameters

connection MySqlConnection

autoOpenConnection [bool](#)

autoOpenTransaction [bool](#)

allowUserVariables [bool](#)

convertZeroDateTime [bool](#)

lockWaitTimeoutSeconds [int](#)

RelmContext(IRelmContext, bool, bool, bool, bool, int)

```
public RelmContext(IRelmContext relmContext, bool autoOpenConnection = true, bool autoOpenTransaction = false, bool allowUserVariables = false, bool convertZeroDateTime = false, int lockWaitTimeoutSeconds = 0)
```

Parameters

relmContext [IRelmContext](#)

autoOpenConnection [bool](#)

autoOpenTransaction [bool](#)

allowUserVariables [bool](#)

convertZeroDateTime [bool](#)

lockWaitTimeoutSeconds [int](#)

RealmContext(RealmContextOptionsBuilder, bool, bool, bool, bool, int)

```
public RealmContext(RealmContextOptionsBuilder optionsBuilder, bool autoOpenConnection = true,
bool autoOpenTransaction = false, bool allowUserVariables = false, bool convertZeroDateTime
= false, int lockWaitTimeoutSeconds = 0)
```

Parameters

optionsBuilder [RealmContextOptionsBuilder](#)

autoOpenConnection [bool](#)

autoOpenTransaction [bool](#)

allowUserVariables [bool](#)

convertZeroDateTime [bool](#)

lockWaitTimeoutSeconds [int](#)

RealmContext(Enum, bool, bool, bool, bool, int)

```
public RealmContext(Enum connectionStringType, bool autoOpenConnection = true, bool
autoOpenTransaction = false, bool allowUserVariables = false, bool convertZeroDateTime =
false, int lockWaitTimeoutSeconds = 0)
```

Parameters

connectionStringType [Enum](#)

autoOpenConnection [bool](#)

autoOpenTransaction [bool](#)

allowUserVariables [bool](#)

convertZeroDateTime [bool](#)

lockWaitTimeoutSeconds [int](#)

RealmContext(string, bool, bool, bool, bool, int)

```
public RealmContext(string connectionDetails, bool autoOpenConnection = true, bool
autoOpenTransaction = false, bool allowUserVariables = false, bool convertZeroDateTime =
false, int lockWaitTimeoutSeconds = 0)
```

Parameters

connectionDetails [string](#)

autoOpenConnection [bool](#)

autoOpenTransaction [bool](#)

allowUserVariables [bool](#)

convertZeroDateTime [bool](#)

lockWaitTimeoutSeconds [int](#)

Properties

ContextOptions

```
public RealmContextOptionsBuilder ContextOptions { get; }
```

Property Value

[RealmContextOptionsBuilder](#)

Methods

BeginTransaction()

```
public MySqlConnection BeginTransaction()
```

Returns

MySqlConnection

BulkTableWrite<T>(T, string, MySqlConnection, Type, int, bool, bool, bool)

```
public int BulkTableWrite<T>(T SourceData, string TableName = null, MySqlConnection  
sqlTransaction = null, Type ForceType = null, int BatchSize = 100, bool  
allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool  
allowUniqueColumns = false)
```

Parameters

SourceData T

TableName [string](#)

sqlTransaction MySqlConnection

ForceType [Type](#)

BatchSize [int](#)

allowAutoIncrementColumns [bool](#)

allowPrimaryKeyColumns [bool](#)

allowUniqueColumns [bool](#)

Returns

[int](#)

Type Parameters

T

CommitTransaction()

```
public void CommitTransaction()
```

Dispose()

Performs application-defined tasks associated with freeing, releasing, or resetting unmanaged resources.

```
public void Dispose()
```

Dispose(bool)

```
protected virtual void Dispose(bool disposing)
```

Parameters

disposing [bool](#) 

DoDatabaseWork(string, Dictionary<string, object>, bool, bool)

```
public void DoDatabaseWork(string queryString, Dictionary<string, object> Parameters = null,
bool throwException = true, bool useTransaction = false)
```

Parameters

queryString [string](#) 

Parameters [Dictionary](#)  <[string](#) , [object](#)  >

throwException [bool](#) 

useTransaction [bool](#) 

DoDatabaseWork(string, Func<MySqlCommand, object>, bool, bool)

```
public void DoDatabaseWork(string QueryString, Func<MySqlCommand, object> ActionCallback,
    bool throwException = true, bool useTransaction = false)
```

Parameters

QueryString [string](#)

ActionCallback [Func](#) <MySqlCommand, [object](#)>

throwException [bool](#)

useTransaction [bool](#)

DoDatabaseWork<T>(string, Dictionary<string, object>, bool, bool)

```
public T DoDatabaseWork<T>(string QueryString, Dictionary<string, object> Parameters = null,
    bool throwException = true, bool useTransaction = false)
```

Parameters

QueryString [string](#)

Parameters [Dictionary](#) <[string](#), [object](#)>

throwException [bool](#)

useTransaction [bool](#)

Returns

T

Type Parameters

T

DoDatabaseWork<T>(string, Func<MySQLCommand, object>, bool, bool)

```
public T DoDatabaseWork<T>(string QueryString, Func<MySQLCommand, object> ActionCallback,
    bool throwException = true, bool useTransaction = false)
```

Parameters

QueryString [string](#)

ActionCallback [Func](#) <MySQLCommand, [object](#)>

throwException [bool](#)

useTransaction [bool](#)

Returns

T

Type Parameters

T

EndConnection(bool)

```
public void EndConnection(bool commitTransaction = true)
```

Parameters

commitTransaction [bool](#)

~RealmContext()

```
protected ~RealmContext()
```

FirstOrDefault<T>(Expression<Func<T, bool>>, bool)

```
public T FirstOrDefault<T>(Expression<Func<T, bool>> predicate, bool loadDataLoaders = false) where T : IRealmModel, new()
```

Parameters

predicate [Expression](#) <[Func](#) <T, [bool](#)>>

loadDataLoaders [bool](#)

Returns

T

Type Parameters

T

GetBulkTableWriter<T>(string, bool, bool, bool, bool, bool)

```
public BulkTableWriter<T> GetBulkTableWriter<T>(string InsertQuery = null, bool useTransaction = false, bool throwException = true, bool allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool allowUniqueColumns = false)
```

Parameters

InsertQuery [string](#)

useTransaction [bool](#)

throwException [bool](#)

allowAutoIncrementColumns [bool](#)

allowPrimaryKeyColumns [bool](#)

allowUniqueColumns [bool](#)

Returns

[BulkTableWriter](#)<T>

Type Parameters

T

GetDataList<T>(string, Dictionary<string, object>, bool)

```
public IEnumerable<T> GetDataList<T>(string QueryString, Dictionary<string, object>  
Parameters = null, bool throwException = true)
```

Parameters

QueryString [string](#)

Parameters [Dictionary](#)<[string](#), [object](#)>

throwException [bool](#)

Returns

[IEnumerable](#)<T>

Type Parameters

T

GetObject<T>(string, Dictionary<string, object>, bool)

```
public T GetObject<T>(string QueryString, Dictionary<string, object> Parameters = null,  
bool throwException = true) where T : IRelmModel, new()
```

Parameters

QueryString [string](#)

Parameters [Dictionary](#)<[string](#), [object](#)>

throwException [bool](#)

Returns

T

Type Parameters

T

GetDataObjects<T>(string, Dictionary<string, object>, bool)

```
public IEnumerable<T> GetDataObjects<T>(string queryString, Dictionary<string, object>  
Parameters = null, bool throwException = true) where T : IRelmModel, new()
```

Parameters

queryString [string](#)

Parameters [Dictionary](#) <[string](#), [object](#)>

throwException [bool](#)

Returns

[IEnumerable](#) <T>

Type Parameters

T

GetDataRow(string, Dictionary<string, object>, bool)

```
public DataRow GetDataRow(string query, Dictionary<string, object> parameters = null, bool  
throwException = true)
```

Parameters

query [string](#)

`parameters` [Dictionary](#) <[string](#), [object](#)>

`throwException` [bool](#)

Returns

[DataRow](#)

GetDataSet(Type)

```
public IRelmDataSetBase GetDataSet(Type dataSetType)
```

Parameters

`dataSetType` [Type](#)

Returns

[IRelmDataSetBase](#)

GetDataSet(Type, bool)

```
public IRelmDataSetBase GetDataSet(Type dataSetType, bool throwException)
```

Parameters

`dataSetType` [Type](#)

`throwException` [bool](#)

Returns

[IRelmDataSetBase](#)

GetDataSetType(Type)

```
public IRealmDataSetBase GetDataSetType(Type dataSetType)
```

Parameters

dataSetType [Type](#) 

Returns

[IRealmDataSetBase](#)

GetDataSetType(Type, bool)

Gets the dataset of the given type.

```
public IRealmDataSetBase GetDataSetType(Type dataSetType, bool throwException)
```

Parameters

dataSetType [Type](#) 

Type of the dataset.

throwException [bool](#) 

Returns

[IRealmDataSetBase](#)

An IDALDataSetBase instance of the given type.

Exceptions

[InvalidOperationException](#) 

Thrown when no matching dataset is found.

GetDataSetType<T>()

```
public IRelmDataSet<T> GetDataSetType<T>() where T : IRelmModel, new()
```

Returns

[IRelmDataSet](#)<T>

Type Parameters

T

GetDataSetType<T>(bool)

Gets the dataset of the given type.

```
public IRelmDataSet<T> GetDataSetType<T>(bool throwException) where T : IRelmModel, new()
```

Parameters

throwException [bool](#)

Returns

[IRelmDataSet](#)<T>

An instance of IDALDataSet of the specified type.

Type Parameters

T

The type of the dataset, which should inherit from CS_DbModel.

Exceptions

[InvalidOperationException](#)

Thrown when no matching dataset is found.

GetDataSet<T>()

```
public IRealmDataSet<T> GetDataSet<T>() where T : IRealmModel, new()
```

Returns

[IRealmDataSet<T>](#)

Type Parameters

T

GetDataSet<T>(bool)

```
public IRealmDataSet<T> GetDataSet<T>(bool throwException) where T : IRealmModel, new()
```

Parameters

throwException [bool](#)

Returns

[IRealmDataSet<T>](#)

Type Parameters

T

GetDataTable(string, Dictionary<string, object>, bool)

```
public DataTable GetDataTable(string query, Dictionary<string, object> parameters = null,  
bool throwException = true)
```

Parameters

query [string](#)

parameters [Dictionary](#) <[string](#), [object](#)>

throwException [bool](#)

Returns

[DataTable](#)

GetIdFromInternalId(string, string)

```
public string GetIdFromInternalId(string Table, string InternalId)
```

Parameters

Table [string](#)

InternalId [string](#)

Returns

[string](#)

GetLastInsertId()

```
public string GetLastInsertId()
```

Returns

[string](#)

GetScalar<T>(string, Dictionary<string, object>, bool)

```
public T GetScalar<T>(string query, Dictionary<string, object> parameters = null, bool  
throwException = true)
```

Parameters

query [string](#)

parameters [Dictionary](#) <[string](#), [object](#)>

throwException [bool](#)

Returns

T

Type Parameters

T

Get<T>(bool)

```
public ICollection<T> Get<T>(bool loadDataLoaders = false) where T : IRealmModel, new()
```

Parameters

loadDataLoaders [bool](#)

Returns

[ICollection](#) <T>

Type Parameters

T

Get<T>(Expression<Func<T, bool>>, bool)

```
public ICollection<T> Get<T>(Expression<Func<T, bool>> predicate, bool loadDataLoaders = false) where T : IRealmModel, new()
```

Parameters

predicate [Expression](#) <[Func](#) <T, [bool](#)>>

`loadDataLoaders` [bool](#)

Returns

[ICollection](#) <T>

Type Parameters

T

HasDataSet(Type, bool)

Checks if the DALDataSet of a specific type is attached to the current DALContext instance.

```
public bool HasDataSet(Type dataSetType, bool throwException = true)
```

Parameters

`dataSetType` [Type](#)

The System.Type of the dataset to check.

`throwException` [bool](#)

Returns

[bool](#)

True if the dataset exists, otherwise false.

HasDataSet<T>(bool)

Checks if the DALDataSet of a specific type is attached to the current DALContext instance.

```
public bool HasDataSet<T>(bool throwException = true) where T : IReImModel, new()
```

Parameters

`throwException` [bool](#)

Returns

[bool](#)

True if the dataset exists, otherwise false.

Type Parameters

T

The type of the dataset, which should inherit from CS_DbModel.

HasTransaction()

```
public bool HasTransaction()
```

Returns

[bool](#)

OnConfigure(RelmContextOptionsBuilder)

```
public virtual void OnConfigure(RelmContextOptionsBuilder OptionsBuilder)
```

Parameters

OptionsBuilder [RelmContextOptionsBuilder](#)

RollbackTransaction()

```
public void RollbackTransaction()
```

RollbackTransactions()


```
public void RollbackTransactions()
```

Run<T>(string, Dictionary<string, object>)

```
public ICollection<T> Run<T>(string query, Dictionary<string, object> parameters = null)
where T : IRealmModel, new()
```

Parameters

query [string](#)

parameters [Dictionary](#) <[string](#), [object](#)>

Returns

[ICollection](#) <T>

Type Parameters

T

SaveAll()

```
public void SaveAll()
```

SetDataLoader<T>(IRelmDataLoader<T>)

```
public void SetDataLoader<T>(IRelmDataLoader<T> dataLoader) where T : RealmModel, new()
```

Parameters

dataLoader [IRelmDataLoader](#) <T>

Type Parameters

T

StartConnection(bool, int)

```
public void StartConnection(bool autoOpenTransaction = false, int lockWaitTimeoutSeconds = 0)
```

Parameters

autoOpenTransaction [bool](#)

lockWaitTimeoutSeconds [int](#)

Where<T>(Expression<Func<T, bool>>)

```
public IRelmDataSet<T> Where<T>(Expression<Func<T, bool>> predicate) where T : IRelmModel, new()
```

Parameters

predicate [Expression](#) <[Func](#) <T, [bool](#)>>

Returns

[IRelmDataSet](#) <T>

Type Parameters

T

WriteToDatabase(IRelmModel, int, bool, bool, bool, bool)

```
public int WriteToDatabase(IRelmModel relmModel, int batchSize = 100, bool allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool allowUniqueColumns = false, bool allowAutoDateColumns = false)
```

Parameters

realmModel [IRelmModel](#)

batchSize [int](#)

allowAutoIncrementColumns [bool](#)

allowPrimaryKeyColumns [bool](#)

allowUniqueColumns [bool](#)

allowAutoDateColumns [bool](#)

Returns

[int](#)

WriteToDatabase(IEnumerable<IRelmModel>, int, bool, bool, bool, bool)

```
public int WriteToDatabase(IEnumerable<IRelmModel> realmModels, int batchSize = 100, bool allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool allowUniqueColumns = false, bool allowAutoDateColumns = false)
```

Parameters

realmModels [IEnumerable](#) <[IRelmModel](#)>

batchSize [int](#)

allowAutoIncrementColumns [bool](#)

allowPrimaryKeyColumns [bool](#)

allowUniqueColumns [bool](#)

allowAutoDateColumns [bool](#)

Returns

[int](#)

Class RelmDataSet<T>

Namespace: [SimpleRelm.Models](#)

Assembly: SimpleRelm.dll

Represents a dataset that provides functionality for managing, querying, and persisting a collection of entities of type **T**.

```
public class RelmDataSet<T> : IRelmDataSet<T>, ICollection<T>, IEnumerable<T>, IEnumerable,
IRelmDataSetBase where T : IRelmModel, new()
```

Type Parameters

T

The type of the entities in the dataset. Must implement [IRelmModel](#) and have a parameterless constructor.

Inheritance

[object](#)  ← RelmDataSet<T>

Implements

[IRelmDataSet](#)  <T>, [ICollection](#)  <T>, [IEnumerable](#)  <T>, [IEnumerable](#) , [IRelmDataSetBase](#)

Inherited Members

[object.ToString\(\)](#) , [object.Equals\(object\)](#) , [object.Equals\(object, object\)](#) ,
[object.ReferenceEquals\(object, object\)](#) , [object.GetHashCode\(\)](#) , [object.GetType\(\)](#) ,
[object.MemberwiseClone\(\)](#) 

Extension Methods

[ListExtensions.LoadDataLoaderField<T, R>\(ICollection<T>, IRelmContext, Expression<Func<T, R>>\)](#),
[ListExtensions.LoadDataLoaderField<T, R>\(ICollection<T>, IRelmQuickContext, Expression<Func<T, R>>\)](#),
[ListExtensions.LoadDataLoaderField<T, R>\(ICollection<T>, RelmContextOptionsBuilder, Expression<Func<T, R>>\)](#),
[ListExtensions.LoadForeignKeyField<T, R>\(ICollection<T>, IRelmContext, Expression<Func<T, ICollection<R>>>\)](#),
[ListExtensions.LoadForeignKeyField<T, R>\(ICollection<T>, IRelmContext, Expression<Func<T, ICollection<R>>>, Expression<Func<R, object>>\)](#),
[ListExtensions.LoadForeignKeyField<T, R>\(ICollection<T>, IRelmContext, Expression<Func<T, R>>\)](#),

[illegible]

[ListExtensions.LoadForeignKeyField<T, R, S>\(ICollection<T>, RelmContextOptionsBuilder, Expression<Func<T, R>>, IRelmDataLoader<S>, Expression<Func<R, object>>\),](#)
[ListExtensions.FlattenTreeObject<T>\(IEnumerable<T>, Func<T, ICollection<T>>\),](#)
[ListExtensions.GenerateDTO<T>\(IEnumerable<T>, ICollection<string>, ICollection<string>, string, Func<IRelmModel, Dictionary<string, object>>\),](#)
[ListExtensions.WriteToDatabase<T>\(IEnumerable<T>, MySqlConnection, MySqlTransaction, string, Type, int, string, bool, bool, bool, bool\),](#)
[ListExtensions.WriteToDatabase<T>\(IEnumerable<T>, IRelmContext, string, Type, int, string, bool, bool, bool, bool\),](#)
[ListExtensions.WriteToDatabase<T>\(IEnumerable<T>, IRelmQuickContext, string, Type, int, string, bool, bool, bool, bool\),](#)
[ListExtensions.WriteToDatabase<T>\(IEnumerable<T>, Enum, string, Type, bool, int, string, bool, bool, bool, bool\),](#)

Remarks

The [RelmDataSet<T>](#) class provides a flexible API for working with collections of entities, including support for filtering, ordering, grouping, and managing relationships between entities. It integrates with a data loader to dynamically load and persist data as needed. The dataset also supports deferred execution for query operations, ensuring efficient data handling. This class is designed to work within the context of a relational data management system, leveraging the provided context and data loader to manage the lifecycle and scope of the dataset.

Constructors

RelmDataSet(IRelmContext, IRelmDataLoader<T>)

Initializes a new instance of the [RelmDataSet<T>](#) class with the specified context and data loader.

```
public RelmDataSet(IRelmContext currentContext, IRelmDataLoader<T> dataLoader)
```

Parameters

currentContext [IRelmContext](#)

The current context used to manage the lifecycle and scope of the dataset. Cannot be [null](#) .

dataLoader [IRelmDataLoader<T>](#)

The data loader responsible for loading and managing the data for the dataset. Cannot be [null](#) .

Exceptions

[ArgumentNullException](#) 

Thrown if `currentContext` is [null](#) .

RealmDataSet(IRelmQuickContext, IRelmDataLoader<T>)

Initializes a new instance of the [RealmDataSet<T>](#) class with the specified context and data loader.

```
public RealmDataSet(IRelmQuickContext currentContext, IRelmDataLoader<T> dataLoader)
```

Parameters

`currentContext` [IRelmQuickContext](#)

The current quick context used to manage the dataset's operational scope. Cannot be [null](#) .

`dataLoader` [IRelmDataLoader](#)<T>

The data loader responsible for loading and managing the dataset's data. Cannot be [null](#) .

Exceptions

[ArgumentNullException](#) 

Thrown if `currentContext` is [null](#) .

Properties

Count

Gets the number of items in the collection.

```
public int Count { get; }
```

Property Value

[int](#) 

IsReadOnly

Gets a value indicating whether the collection is read-only.

```
public bool IsReadOnly { get; }
```

Property Value

[bool](#)

Modified

Gets or sets a value indicating whether the object has been modified.

```
public bool Modified { get; set; }
```

Property Value

[bool](#)

Methods

Add(ICollection<T>)

Adds the specified collection of items to the current instance and persists the change.

```
public int Add(ICollection<T> items)
```

Parameters

items [ICollection](#)<T>

The collection of items to add. Cannot be null.

Returns

[int](#)

The number of items successfully added.

Add(ICollection<T>, bool)

Adds a collection of items to the current instance and optionally persists the changes.

```
public int Add(ICollection<T> items, bool Persist)
```

Parameters

items [ICollection<T>](#)

The collection of items to add. Cannot be null.

Persist [bool](#)

A value indicating whether the changes should be persisted after adding the items. If [true](#), the method persists the changes and returns the result of the save operation. If [false](#), the method only adds the items and returns the count of items added.

Returns

[int](#)

The number of items added if **Persist** is [false](#), or the result of the save operation if **Persist** is [true](#).

Add(T)

Adds the specified item to the collection and persists the change.

```
public int Add(T item)
```

Parameters

item T

The item to add to the collection. Cannot be [null](#).

Returns

[int](#)

The index at which the item was added.

Add(T, bool)

Adds the specified item to the collection and optionally persists it to the database.

```
public int Add(T item, bool Persist)
```

Parameters

item T

The item to add to the collection.

Persist [bool](#)

A value indicating whether the item should be persisted to the database. If [true](#), the item is written to the database; otherwise, it is only added to the collection.

Returns

[int](#)

An integer indicating the result of the operation. Returns 1 if the item is added to the collection without persistence, or the result of the database write operation if **Persist** is [true](#).

Remarks

If **Persist** is [true](#), the method writes the item to the database using the current database context. The database connection and transaction details are determined by the context options. If **Persist** is [false](#), the collection's state is marked as modified.

Clear()

Removes all items from the collection.

```
public void Clear()
```

Remarks

After calling this method, the collection will be empty. If the collection is already empty, this method has no effect.

Contains(T)

Determines whether the collection contains the specified item.

```
public bool Contains(T item)
```

Parameters

item T

The item to locate in the collection.

Returns

[bool](#)

[true](#) if the specified item is found in the collection; otherwise, [false](#).

Remarks

If the collection is null, this method returns [false](#).

CopyTo(T[], int)

Copies the elements of the collection to the specified array, starting at the specified index.

```
public void CopyTo(T[] array, int arrayIndex)
```

Parameters

array T[]

The one-dimensional array that is the destination of the elements copied from the collection. The array must have zero-based indexing.

`arrayIndex` [int](#)

The zero-based index in the `array` at which copying begins.

Remarks

This method copies the elements in the same order they are enumerated by the collection.

DistinctBy(Expression<Func<T, object>>)

Filters the dataset to include only distinct elements based on the specified key selector.

```
public IRelmDataSet<T> DistinctBy(Expression<Func<T, object>> predicate)
```

Parameters

`predicate` [Expression](#) <[Func](#) <T, [object](#)>>

An expression that specifies the key used to determine distinct elements. The key is derived from the properties of the dataset elements.

Returns

[IRelmDataSet](#) <T>

A dataset containing only distinct elements based on the specified key.

Remarks

This method modifies the current dataset by adding a distinct operation to the query. The distinctness is determined by the value of the key selected by the `predicate` expression.

Entry(T)

Clears the current dataset, then adds the specified item to the dataset and marks the dataset as modified.

```
public IRelmDataSet<T> Entry(T Item)
```

Parameters

Item T

The item to be added to the dataset. Cannot be null.

Returns

[IRelmDataSet](#)<T>

The current dataset instance, allowing for method chaining.

Remarks

The item is added to the cleared dataset without persisting the change. The dataset's state is marked as modified.

Entry(T, bool)

Clears the current dataset, then adds the specified item to the dataset and optionally persists it.

```
public IRelmDataSet<T> Entry(T Item, bool Persist = true)
```

Parameters

Item T

The item to add to the dataset. Cannot be [null](#).

Persist [bool](#)

A value indicating whether the item should be persisted. The default value is [true](#).

Returns

[IRelmDataSet](#)<T>

The current dataset instance with the added item.

Remarks

This method modifies the dataset by clearing then adding the specified item and marks the dataset as modified. If `Persist` is [true](#), the item will be persisted.

Find(int)

Finds and returns the first item with the specified identifier.

```
public T Find(int id)
```

Parameters

`id` [int](#)

The unique identifier of the item to find.

Returns

`T`

The first item that matches the specified identifier, or [null](#) if no such item is found.

Remarks

This method searches for an item based on its `Id` property. If multiple items share the same identifier, only the first match is returned.

Find(string)

Finds and returns the first element in the collection that matches the specified internal identifier.

```
public T Find(string InternalId)
```

Parameters

`InternalId` [string](#)

The internal identifier to search for. Cannot be null.

Returns

T

The first element that matches the specified internal identifier, or [null](#) if no match is found.

FirstOrDefault()

Returns the first element of the sequence, or the default value for the type if the sequence is empty.

```
public T FirstOrDefault()
```

Returns

T

The first element of the sequence, or the default value for the type T if the sequence is empty.

Remarks

This method retrieves the first element of the sequence. If the sequence contains no elements, it returns the default value for the type T (e.g., [null](#) for reference types, or the default zero value for value types).

FirstOrDefault(bool)

Returns the first element of the collection, or the default value for the type if the collection is empty.

```
public T FirstOrDefault(bool loadItems)
```

Parameters

loadItems [bool](#)

A value indicating whether to load items into the collection before retrieving the first element.

Returns

T

The first element of the collection if it contains any elements; otherwise, the default value for the type T.

Remarks

If `loadItems` is [true](#), the method ensures that items are loaded into the collection before attempting to retrieve the first element.

FirstOrDefault(Expression<Func<T, bool>>)

Loads items from the database using the existing predicate conditions and then returns the first element of a sequence that satisfies the specified condition, or the default value for the type if no such element is found.

```
public T FirstOrDefault(Expression<Func<T, bool>> predicate)
```

Parameters

predicate [Expression](#) <[Func](#) <T, [bool](#)>>

A function to test each element for a condition. The function must not be [null](#).

Returns

T

The first element in the sequence that satisfies the condition defined by **predicate**, or the default value of type T if no such element is found.

FirstOrDefault(Expression<Func<T, bool>>, bool)

Retrieves the first element of a sequence that satisfies the specified condition, or a default value if no such element is found.

```
public T FirstOrDefault(Expression<Func<T, bool>> predicate, bool loadItems)
```

Parameters

predicate [Expression](#) <[Func](#) <T, [bool](#)>>

An expression that defines the condition to test each element for. If [null](#), no condition is applied.

`loadItems` [bool](#)

A value indicating whether to load the items from the database using the existing predicate conditions before evaluating the condition. If [true](#), the items are loaded from the database; otherwise, the method operates on the existing items.

Returns

`T`

The first element that satisfies the condition defined by `predicate`, or the default value of type `T` if no such element is found.

Remarks

If `loadItems` is [true](#), the method loads the items and applies the condition specified by `predicate`. If `loadItems` is [false](#), the method evaluates the condition on the existing items.

GetEnumerator()

Returns an enumerator that iterates through the collection.

```
public IEnumerator<T> GetEnumerator()
```

Returns

[IEnumerator](#) <T>

An enumerator for the collection of items.

Remarks

If the collection is not already loaded, it will attempt to load the items dynamically. If no items are available, the enumerator will iterate over an empty collection.

GroupBy(Expression<Func<T, object>>)

Groups the elements of the dataset based on the specified key selector.

```
public IRelmDataSet<T> GroupBy(Expression<Func<T, object>> predicate)
```

Parameters

predicate [Expression](#) <[Func](#) <T, [object](#)>>

An expression that specifies the key to group by. The key is derived from the elements of the dataset.

Returns

[IRelmDataSet](#)<T>

A dataset grouped by the specified key.

Remarks

The grouping is applied to the underlying query, modifying the dataset to reflect the grouping operation. This method does not execute the query; it only adds the grouping condition to the query definition.

Limit(int)

Limits the number of results returned by the dataset to the specified count.

```
public IRelmDataSet<T> Limit(int limitCount)
```

Parameters

limitCount [int](#)

The maximum number of results to include in the dataset. Must be a non-negative integer.

Returns

[IRelmDataSet](#)<T>

The current dataset instance with the applied limit, allowing for further query chaining.

Load()

Loads a collection of items of type **T**.

```
public ICollection<T> Load()
```

Returns

[ICollection](#)[↗] <T>

A collection of items of type **T**. The collection may be empty if no items are available.

Remarks

This method retrieves the items and returns them as a collection. By default, it includes all items unless specified otherwise in an overload.

Load(bool)

Loads the data for the current context and optionally initializes and executes field loaders.

```
public ICollection<T> Load(bool loadDataLoaders)
```

Parameters

loadDataLoaders [bool](#)[↗]

A value indicating whether to initialize and execute field loaders for properties marked with the [Relm DataLoader](#) attribute. If [true](#)[↗], field loaders are registered and executed; otherwise, only the data is loaded.

Returns

[ICollection](#)[↗] <T>

A collection of items of type **T** representing the loaded data. The collection will be empty if no data is available.

Remarks

If **loadDataLoaders** is [true](#)[↗], the method identifies properties in the type **T** that are marked with the [Relm DataLoader](#) attribute and initializes field loaders for them. These field loaders are then executed to load

additional data related to the fields. If the data loader has executed commands related to references, the method also loads all references associated with the data.

LoadAsDataSet()

Loads the current data and returns it as a dataset.

```
public IRealmDataSet<T> LoadAsDataSet()
```

Returns

[IRealmDataSet<T>](#)

An [IRealmDataSet<T>](#) representing the loaded dataset.

Remarks

This method ensures that the data is loaded before returning the dataset. It can be used to retrieve the data in its current state for further processing or querying.

New(bool)

Creates a new blank instance of the object, with an option to persist it.

```
public T New(bool Persist = true)
```

Parameters

Persist [bool](#)

A value indicating whether the new instance should be persisted. [true](#) to persist the instance; otherwise, [false](#).

Returns

T

A new instance of the object.

New(dynamic, bool)

Creates a new instance of the specified type **T** and initializes its properties based on the provided dynamic parameters.

```
public T New(dynamic NewObjectParameters, bool Persist = true)
```

Parameters

NewObjectParameters dynamic

A dynamic object containing property names and values to initialize the new instance. Only properties matching the keys in the underscore properties of **T** will be set.

Persist [bool](#) 

A boolean value indicating whether the newly created object should be persisted. The default value is [true](#) .

Returns

T

A new instance of **T** with its properties initialized based on the provided parameters.

Remarks

This method uses reflection to set the properties of the new instance. Ensure that the property names in **NewObjectParameters** match the expected property names of **T**.

OrderBy(Expression<Func<T, object>>)

Orders the elements in the dataset based on the specified key selector.

```
public IRelmDataSet<T> OrderBy(Expression<Func<T, object>> predicate)
```

Parameters

predicate [Expression](#)  <[Func](#)  <T, [object](#)  >>

An expression that specifies the key to order the elements by. The key is derived from the dataset elements.

Returns

[IRelmDataSet](#)<T>

A dataset with the elements ordered according to the specified key.

Remarks

This method modifies the query to include an "ORDER BY" clause based on the provided key selector. The ordering is applied in ascending order by default.

OrderByDescending(Expression<Func<T, object>>)

Orders the elements of the dataset in descending order based on the specified key.

```
public IRelmDataSet<T> OrderByDescending(Expression<Func<T, object>> predicate)
```

Parameters

predicate [Expression](#) <[Func](#) <T, [object](#)>>

An expression that specifies the key to use for ordering the elements. The key is derived from the property or computed value defined in the expression.

Returns

[IRelmDataSet](#)<T>

A dataset with the elements ordered in descending order based on the specified key.

Remarks

This method modifies the query by appending an "ORDER BY DESC" clause using the specified key. The ordering is applied to the dataset when the query is executed.

Reference<S>(Expression<Func<T, ICollection<S>>>),

ICollection<Expression<Func<S, object>>>)

Configures a reference navigation property for the current entity, allowing additional constraints to be applied.

```
public IRealmDataSet<T> Reference<S>(Expression<Func<T, ICollection<S>>> predicate,
    ICollection<Expression<Func<S, object>>> additionalConstraints)
```

Parameters

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <S>>>

An expression that specifies the collection navigation property to configure.

additionalConstraints [ICollection](#) <[Expression](#) <[Func](#) <S, [object](#)>>>

A collection of expressions representing additional constraints to apply to the related entities.

Returns

[IRealmDataSet](#) <T>

An [IRealmDataSet](#) <T> representing the configured reference navigation property.

Type Parameters

S

The type of the related entity in the collection.

Remarks

This method is typically used to define relationships between entities and apply additional filtering or constraints on the related entities. The **predicate** parameter identifies the navigation property, while the **additionalConstraints** parameter allows specifying further conditions on the related entities.

Reference<S>(Expression<Func<T, ICollection<S>>>, Expression<Func<S, object>>>)

Configures a reference navigation property for inclusion in the query, allowing additional constraints to be applied to the related entities.


```
public IRealmDataSet<T> Reference<S>(Expression<Func<T, ICollection<S>>> predicate,  
Expression<Func<S, object>> additionalConstraints)
```

Parameters

predicate [Expression](#) <[Func](#) <T, [ICollection](#) <S>>>

An expression that specifies the navigation property to include.

additionalConstraints [Expression](#) <[Func](#) <S, [object](#)>>

An expression that defines additional constraints to apply to the related entities.

Returns

[IRealmDataSet](#) <T>

An [IRealmDataSet](#) <T> that includes the specified navigation property and applies the given constraints.

Type Parameters

S

The type of the related entities in the collection.

Remarks

This method is typically used to include a collection navigation property in a query and apply additional filtering or constraints to the related entities.

Reference<S>(Expression<Func<T, S>>)

Creates a reference to the specified property or field of the current entity.

```
public IRealmDataSet<T> Reference<S>(Expression<Func<T, S>> predicate)
```

Parameters

predicate [Expression](#) <[Func](#) <T, S>>

An expression that specifies the property or field to reference.

Returns

[IRelmDataSet](#)<T>

An [IRelmDataSet](#)<T> that includes the specified reference.

Type Parameters

S

The type of the property or field being referenced.

Remarks

This method allows you to define a reference to a property or field of the entity, which can be used to include related data in subsequent operations.

Reference<S>(Expression<Func<T, S>>, ICollection<Expression<Func<S, object>>>)

Creates a reference to a related dataset based on the specified predicate and additional constraints.

```
public IRelmDataSet<T> Reference<S>(Expression<Func<T, S>> predicate,
    ICollection<Expression<Func<S, object>>> additionalConstraints)
```

Parameters

predicate [Expression](#)  <[Func](#)  <T, S>>

An expression that specifies the relationship between the current entity and the related entity.

additionalConstraints [ICollection](#)  <[Expression](#)  <[Func](#)  <S, [object](#)  >>>

A collection of expressions that define additional constraints to apply to the related dataset.

Returns

[IRelmDataSet](#)<T>

An [IRelmDataSet](#)<T> representing the related dataset that matches the specified predicate and constraints.

Type Parameters

S

The type of the related entity being referenced.

Reference<S>(Expression<Func<T, S>>, Expression<Func<S, object>>)

Creates a reference to a related dataset based on the specified predicate and additional constraints.

```
public IRelmDataSet<T> Reference<S>(Expression<Func<T, S>> predicate, Expression<Func<S, object>> additionalConstraints)
```

Parameters

predicate [Expression](#) <[Func](#) <T, S>>

An expression that specifies the relationship between the current entity and the related entity.

additionalConstraints [Expression](#) <[Func](#) <S, [object](#)>>

An expression that defines additional constraints to apply to the related entity.

Returns

[IRelmDataSet](#)<T>

An [IRelmDataSet<T>](#) representing the related dataset that matches the specified predicate and constraints.

Type Parameters

S

The type of the related entity being referenced.

Remarks

This method allows you to define a reference to a related dataset by specifying a predicate for the relationship and additional constraints to further filter the related data. Use this method when you need to reference a related dataset with specific filtering criteria.

Remove(T)

Removes the specified item from the collection.

```
public bool Remove(T item)
```

Parameters

item T

The item to remove from the collection.

Returns

[bool](#)[↗]

[true](#)[↗] if the item was successfully removed; otherwise, [false](#)[↗]. Returns [false](#)[↗] if the item was not found in the collection or if the collection is null.

Save()

Saves the current items to the database and returns the number of rows updated.

```
public int Save()
```

Returns

[int](#)[↗]

The number of rows updated in the database.

Remarks

The method determines the database connection settings based on the current context options. If the context options specify an open connection, the method uses the provided database connection and transaction. Otherwise, it uses the connection string type to establish the connection. After the save operation, the [Modified](#) property is set to [false](#)[↗].

Save(T)

Saves the specified item to the collection. If an item with the same internal identifier already exists, it is replaced; otherwise, the item is added to the collection.

```
public int Save(T Item)
```

Parameters

Item T

The item to save. The item must have a valid internal identifier.

Returns

[int](#)

An integer representing the result of the save operation. The exact meaning of the return value depends on the underlying implementation of the save or add operation.

Remarks

This method ensures that the collection does not contain duplicate items based on their internal identifiers. If an item with the same identifier already exists, it is replaced with the new item. Otherwise, the item is added to the collection, and the operation is persisted.

Set(Expression<Func<T, T>>)

Updates a single column's value in the dataset based on the specified expression.

```
public IRelmDataSet<T> Set(Expression<Func<T, T>> predicate)
```

Parameters

predicate [Expression](#) <[Func](#) <T, T>>

An expression that specifies the column to update and the value to assign. The expression must be in the form of a lambda, such as `x => x.Property = value`.

Returns

[IRelmDataSet](#)<T>

The current dataset instance, allowing for method chaining.

Remarks

This method modifies the dataset by applying the specified update expression. The changes are not persisted until the dataset is committed.

SetDataLoader(IRealmDataLoader<T>)

Sets the data loader for the current instance.

```
public IRealmDataLoader<T> SetDataLoader(IRealmDataLoader<T> dataLoader)
```

Parameters

dataLoader [IRealmDataLoader](#)<T>

The data loader to be used. Cannot be [null](#)[↗].

Returns

[IRealmDataLoader](#)<T>

The data loader that was set.

SetFieldLoader(string, IRealmFieldLoader)

Registers a field loader for the specified field name.

```
public IRealmFieldLoader SetFieldLoader(string fieldName, IRealmFieldLoader dataLoader)
```

Parameters

fieldName [string](#)[↗]

The name of the field on the model for which the loader is being registered. The field must exist on the model type **T**.

dataLoader [IRealmFieldLoader](#)

The [IRelmFieldLoader](#) instance responsible for loading data for the specified field.

Returns

[IRelmFieldLoader](#)

The [IRelmFieldLoader](#) instance that was registered for the specified field.

Remarks

This method ensures that the specified field exists on the model type `T` before registering the loader.

Exceptions

[ArgumentException](#) 

Thrown if `fieldName` does not correspond to a property on the model type `T`.

SetFieldLoader(string, IRelmQuickFieldLoader)

Registers a field loader for the specified field name.

```
public IRelmQuickFieldLoader SetFieldLoader(string fieldName, IRelmQuickFieldLoader
dataLoader)
```

Parameters

`fieldName` [string](#) 

The name of the field on the model for which the loader is being registered. The field must exist on the model type `T`.

`dataLoader` [IRelmQuickFieldLoader](#)

An instance of [IRelmQuickFieldLoader](#) that provides the logic for loading the field's data.

Returns

[IRelmQuickFieldLoader](#)

The registered [IRelmQuickFieldLoader](#) instance for the specified field.

Remarks

This method ensures that the specified field exists on the model type `T` before registering the loader.

Exceptions

[ArgumentException](#)

Thrown if the specified `fieldName` does not exist on the model type `T`.

Where(Expression<Func<T, bool>>)

Filters the dataset based on the specified predicate.

```
public IRelmDataSet<T> Where(Expression<Func<T, bool>> predicate)
```

Parameters

predicate [Expression](#) <[Func](#) <T, [bool](#)>>

An expression that defines the conditions of the filter. The predicate is a function that takes an element of type `T` and returns [true](#) if the element should be included in the result; otherwise, [false](#).

Returns

[IRelmDataSet](#) <T>

A dataset containing only the elements that satisfy the specified predicate.

Remarks

This method allows you to apply a filtering condition to the dataset. The filtering is deferred, meaning the predicate is not evaluated until the dataset is enumerated or further operations are performed.

Write()

Writes data using the underlying data loader.

```
public int Write()
```


Returns

[int](#) 

The number of records successfully written.

Class RelmDefaultDataLoader<T>

Namespace: [SimpleRelm.Models](#)

Assembly: SimpleRelm.dll

Provides a default implementation of the [IRelmDataLoader<T>](#) interface for loading, querying, and writing data for a specified model type. This class is designed to work with models that implement the [IRelmModel](#) interface.

```
public class RelmDefaultDataLoader<T> : IRelmDataLoader<T> where T : IRelmModel, new()
```

Type Parameters

T

The type of the model to be loaded, queried, or written. The type must implement [IRelmModel](#) and have a parameterless constructor.

Inheritance

[object](#)  ← RelmDefaultDataLoader<T>

Implements

[IRelmDataLoader](#)<T>

Inherited Members

[object.ToString\(\)](#)  , [object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  ,
[object.ReferenceEquals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  , [object.GetType\(\)](#)  ,
[object.MemberwiseClone\(\)](#) 

Remarks

This class supports operations such as adding query expressions, retrieving data, and writing data to the database. It uses a combination of database column metadata and query expressions to dynamically build SQL queries.

Constructors

RelmDefaultDataLoader()

Initializes a new instance of the RelmDefaultDataLoader class.

```
public RealmDefaultDataLoader()
```

Remarks

This constructor performs the initial setup required for the data loader by invoking the `SimpleRealm.Models.RealmDefaultDataLoader<T>.InitialSetup()` method.

RealmDefaultDataLoader(RealmContextOptionsBuilder)

Initializes a new instance of the `RealmDefaultDataLoader` class with the specified context options builder.

```
public RealmDefaultDataLoader(RealmContextOptionsBuilder contextOptionsBuilder)
```

Parameters

`contextOptionsBuilder` [RealmContextOptionsBuilder](#)

The builder used to configure options for the [RealmContext](#).

Properties

LastCommandsExecuted

Gets or sets the collection of the most recently executed commands and their associated execution details.

```
public Dictionary<Commands.Command, List<IRelmExecutionCommand>> LastCommandsExecuted { get; set; }
```

Property Value

[Dictionary](#) [<Commands.Command, List<IRelmExecutionCommand>>](#)

Remarks

This property provides a record of the last executed commands along with their execution details. The dictionary keys represent the commands, and the associated lists contain the execution information for each command. The property can be used to inspect or analyze the history of command executions.

Methods

AddExpression(Command, Expression)

Adds an expression to the specified command and returns a new execution command.

```
public IRelmExecutionCommand AddExpression(Commands.Command command, Expression expression)
```

Parameters

command [Commands.Command](#)

The command to which the expression will be added. Must not be [null](#).

expression [Expression](#)

The expression to add to the command. Must not be [null](#).

Returns

[IRelmExecutionCommand](#)

A new [IRelmExecutionCommand](#) instance representing the command with the added expression.

Remarks

This method creates a new execution command by associating the provided expression with the specified command. The new execution command is added to the prewarmed query for the given command.

AddSingleExpression(Command, Expression)

Adds a single expression to the specified command and returns the resulting execution command.

```
public IRelmExecutionCommand AddSingleExpression(Commands.Command command,  
Expression expression)
```

Parameters

command [Commands.Command](#)

The command to which the expression will be added.

expression [Expression](#)

The expression to associate with the command.

Returns

[IRelmExecutionCommand](#)

An [IRelmExecutionCommand](#) representing the updated execution command with the specified expression.

Remarks

If the command does not already have any associated expressions, a new execution command is created.

GetLoadData()

Retrieves a collection of data entities based on the current query configuration.

```
public virtual ICollection<T> GetLoadData()
```

Returns

[ICollection](#) <T>

A collection of data entities of type **T**. The collection will be empty if no data matches the query.

Remarks

This method constructs a query using the current configuration and retrieves the corresponding data entities. The returned collection may be empty if no matching data is found.

HasUnderscoreProperty(string)

Determines whether the specified property key exists in the column registry.

```
public bool HasUnderscoreProperty(string PropertyKey)
```

Parameters

PropertyKey [string](#)

The key of the property to check for existence.

Returns

[bool](#)

[true](#) if the column registry contains the specified property key; otherwise, [false](#).

Remarks

This method checks the presence of a property key in the internal column registry. If the column registry is null, the method returns [false](#).

PullData(string, Dictionary<string, object>)

Executes the specified SQL query and retrieves a collection of data objects of type **T**.

```
public virtual ICollection<T> PullData(string selectQuery, Dictionary<string, object> findOptions)
```

Parameters

selectQuery [string](#)

The SQL query to execute. This query should be a valid SELECT statement that matches the structure of the data objects being retrieved.

findOptions [Dictionary](#) <[string](#), [object](#)>

A dictionary of parameters to be used in the query. The keys represent parameter names, and the values represent their corresponding values.

Returns

[ICollection](#) <**T**>

A collection of data objects of type **T** that match the results of the query. Returns an empty collection if no data is found.

Remarks

This method supports two modes of database connection: - If the context is configured with an open database connection, the query is executed using the provided connection and transaction. - Otherwise, the query is executed using the configured connection string type.

WriteData()

Executes a database operation to write data and returns the result of the operation.

```
public int WriteData()
```

Returns

[int](#)

The result of the database operation as an integer. The value typically represents the number of rows affected by the operation.

Remarks

This method constructs an update query and performs the database operation based on the configuration of the context options. It supports both open database connections and connection strings, depending on the specified options.

Class RelayCommand

Namespace: [SimpleRelm.Models](#)

Assembly: SimpleRelm.dll

```
public class RelayCommand : IRelmExecutionCommand
```

Inheritance

[object](#) ← RelayCommand

Implements

[IRelmExecutionCommand](#)

Inherited Members

[object.ToString\(\)](#), [object.Equals\(object\)](#), [object.Equals\(object, object\)](#),
[object.ReferenceEquals\(object, object\)](#), [object.GetHashCode\(\)](#), [object.GetType\(\)](#),
[object.MemberwiseClone\(\)](#)

Constructors

RelmExecutionCommand()

```
public RelayCommand()
```

RelmExecutionCommand(Command, Expression)

```
public RelayCommand(Commands.Command command, Expression expression)
```

Parameters

command [Commands.Command](#)

expression [Expression](#)

Properties

AdditionalCommandCount

```
public int AdditionalCommandCount { get; }
```

Property Value

[int](#)

InitialCommand

```
public Commands.Command InitialCommand { get; }
```

Property Value

[Commands.Command](#)

InitialExpression

```
public Expression InitialExpression { get; }
```

Property Value

[Expression](#)

Methods

AddAdditionalCommand(Command, Expression)

```
public RealmExecutionCommand AddAdditionalCommand(Commands.Command command,  
Expression expression)
```

Parameters

command [Commands.Command](#)

expression [Expression](#)

Returns

[RelmExecutionCommand](#)

AddAdditionalCommand<T>(Command, Expression<Func<T, object>> >)

```
public RelmExecutionCommand AddAdditionalCommand<T>(Commands.Command command,
Expression<Func<T, object>> expression)
```

Parameters

command [Commands.Command](#)

expression [Expression](#) <[Func](#) <T, [object](#)> >

Returns

[RelmExecutionCommand](#)

Type Parameters

T

GetAdditionalCommands()

```
public List<RelmExecutionCommand> GetAdditionalCommands()
```

Returns

[List](#) <[RelmExecutionCommand](#)>

GetForeignKeyNavigationOptions<T>(ICollection<T>)

```
public ForeignKeyNavigationOptions GetForeignKeyNavigationOptions<T>(ICollection<T> _items)
```

Parameters

_items [ICollection](#)<T>

Returns

[ForeignKeyNavigationOptions](#)

Type Parameters

T

Class RelmModel

Namespace: [SimpleRelm.Models](#)

Assembly: SimpleRelm.dll

Represents a base model for entities in the Relm framework, providing core attributes and functionality for data manipulation, database operations, and DTO generation.

```
public class RelmModel : IRelmModel
```

Inheritance

[object](#) ← RelmModel

Implements

[IRelmModel](#)

Derived

[RelmModelApartment](#)

Inherited Members

[object.ToString\(\)](#), [object.Equals\(object\)](#), [object.Equals\(object, object\)](#),
[object.ReferenceEquals\(object, object\)](#), [object.GetHashCode\(\)](#), [object.GetType\(\)](#),
[object.MemberwiseClone\(\)](#)

Extension Methods

[ModelExtensions.LoadDataLoaderField<T, S>\(T, IRelmContext, Expression<Func<T, S>>\)](#),
[ModelExtensions.LoadDataLoaderField<T, S>\(T, IRelmQuickContext, Expression<Func<T, S>>\)](#),
[ModelExtensions.LoadDataLoaderField<T, S>\(T, RelmContextOptionsBuilder, Expression<Func<T, S>>\)](#),
[ModelExtensions.LoadForeignKeyField<T, R>\(T, IRelmContext, Expression<Func<T, ICollection<R>>>\)](#),
[ModelExtensions.LoadForeignKeyField<T, R>\(T, IRelmContext, Expression<Func<T, ICollection<R>>>, Expression<Func<R, object>>\)](#),
[ModelExtensions.LoadForeignKeyField<T, R>\(T, IRelmContext, Expression<Func<T, R>>\)](#),
[ModelExtensions.LoadForeignKeyField<T, R>\(T, IRelmContext, Expression<Func<T, R>>, Expression<Func<R, object>>\)](#),
[ModelExtensions.LoadForeignKeyField<T, R>\(T, IRelmQuickContext, Expression<Func<T, ICollection<R>>>\)](#),
[ModelExtensions.LoadForeignKeyField<T, R>\(T, IRelmQuickContext, Expression<Func<T, ICollection<R>>>, Expression<Func<R, object>>\)](#),
[ModelExtensions.LoadForeignKeyField<T, R>\(T, IRelmQuickContext, Expression<Func<T, R>>\)](#),

[ModelExtensions.LoadForeignKeyField<T, R>\(T, IRelmQuickContext, Expression<Func<T, R>>, Expression<Func<R, object>>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R>\(T, RelmContextOptionsBuilder, Expression<Func<T, ICollection<R>>>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R>\(T, RelmContextOptionsBuilder, Expression<Func<T, ICollection<R>>>, Expression<Func<R, object>>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R>\(T, RelmContextOptionsBuilder, Expression<Func<T, R>>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R>\(T, RelmContextOptionsBuilder, Expression<Func<T, R>>, Expression<Func<R, object>>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R, S>\(T, IRelmContext, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R, S>\(T, IRelmContext, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>, Expression<Func<R, object>>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R, S>\(T, IRelmContext, Expression<Func<T, R>>, IRelmDataLoader<S>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R, S>\(T, IRelmContext, Expression<Func<T, R>>, IRelmDataLoader<S>, Expression<Func<R, object>>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R, S>\(T, IRelmQuickContext, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R, S>\(T, IRelmQuickContext, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>, Expression<Func<R, object>>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R, S>\(T, IRelmQuickContext, Expression<Func<T, R>>, IRelmDataLoader<S>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R, S>\(T, IRelmQuickContext, Expression<Func<T, R>>, IRelmDataLoader<S>, Expression<Func<R, object>>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R, S>\(T, RelmContextOptionsBuilder, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R, S>\(T, RelmContextOptionsBuilder, Expression<Func<T, ICollection<R>>>, IRelmDataLoader<S>, Expression<Func<R, object>>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R, S>\(T, RelmContextOptionsBuilder, Expression<Func<T, R>>, IRelmDataLoader<S>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R, S>\(T, RelmContextOptionsBuilder, Expression<Func<T, R>>, IRelmDataLoader<S>, Expression<Func<R, object>>\)](#) .

Remarks

The [RelmModel](#) class serves as a foundational class for entities, offering features such as:

- Core attributes like [Id](#), [Active](#), [InternalId](#), [CreateDate](#), and [LastUpdated](#).
- Support for resetting attributes to default values using [ResetCoreAttributes\(bool, bool\)](#).
- Data population from database rows via [ResetWithData\(DataRow, string\)](#).

- Bulk database write operations through various `WriteToDatabase` overloads.
- Dynamic Data Transfer Object (DTO) generation with [GenerateDTO\(IEnumerable<string>, IEnumerable<string>, string, Func<IRelmModel, Dictionary<string, object>>, int\)](#).

This class is designed to be extended by specific entity types and provides a flexible foundation for working with relational data in the Relm framework.

Constructors

RelmModel()

Initializes a new instance of the [RelmModel](#) class.

```
public RelmModel()
```

Remarks

This constructor initializes the core attributes of the model by invoking the [ResetCoreAttributes\(bool, bool\)](#) method.

RelmModel(IRelmModel)

Initializes a new instance of the [RelmModel](#) class by copying all writable properties from the specified source model.

```
public RelmModel(IRelmModel fromModel)
```

Parameters

`fromModel` [IRelmModel](#)

The source model from which to copy property values. Must not be [null](#) .

Remarks

This constructor performs a shallow copy of all writable properties from the specified source model to the new instance. Only properties with matching names and compatible types between the source and target models are copied. Properties that are read-only or do not exist in the target model are ignored.

Exceptions

[ArgumentNullException](#)

Thrown if `fromModel` is [null](#).

RelmModel(DataRow, string)

Initializes a new instance of the [RelmModel](#) class and populates its properties using data from the specified database row.

```
public RelmModel(DataRow modelData, string alternateTableName = null)
```

Parameters

`modelData` [DataRow](#)

A [DataRow](#) containing the data to populate the model. The column names in the `modelData` must match the property names of the model for successful mapping.

`alternateTableName` [string](#)

An optional alternate table name to use when searching for data in the `modelData`. If not specified, the default table name is used.

Remarks

This constructor automatically maps the data from the provided `modelData` to the properties of the model based on naming conventions. Ensure that the column names in the `modelData` match the property names of the model for accurate mapping.

Properties

Active

Gets or sets a value indicating whether the entity is active.

```
[RelmColumn(null, -1, null, false, false, false, false, "1", null, false, false, false)]  
public bool Active { get; set; }
```

Property Value

[bool](#)

CreateDate

Gets or sets the creation date and time of the entity.

```
[RealmColumn(null, -1, null, false, false, false, false, "CURRENT_TIMESTAMP", null, false, false, false)]  
public DateTime CreateDate { get; set; }
```

Property Value

[DateTime](#)

Id

Gets or sets the unique auto-number row identifier for the entity.

```
[RealmColumn(null, -1, null, false, true, true, false, null, null, false, false, false)]  
public long? Id { get; set; }
```

Property Value

[long](#)

InternalId

Gets or sets the unique internal identifier for the entity.

```
[RealmColumn(null, -1, null, false, false, false, true, null, null, false, false, false)]  
public string InternalId { get; set; }
```

Property Value

[string](#)

LastUpdated

Gets or sets the timestamp of the last update.

```
[RealmColumn(null, -1, null, false, false, false, false, "CURRENT_TIMESTAMP", null, false, false, false)]  
public DateTime LastUpdated { get; set; }
```

Property Value

[DateTime](#)

Methods

CopyFromSource<T>(T)

Creates a new instance of the specified type **T** and copies all public properties and fields from the specified **source** object to the new instance.

```
public T CopyFromSource<T>(T source) where T : RealmModel, new()
```

Parameters

source T

The source object from which to copy property and field values. Cannot be [null](#).

Returns

T

A new instance of type **T** with all public properties and fields copied from the **source** object.

Type Parameters

T

The type of the object to create and copy values to. Must be a class that derives from [RelmModel](#) and has a parameterless constructor.

Remarks

This method performs a shallow copy of all public properties and fields. Only properties that are writable and not indexed are copied. Fields are copied regardless of their accessibility.

Exceptions

[ArgumentNullException](#) 

Thrown if `source` is [null](#) .

Duplicate()

Creates a shallow copy of the current [RelmModel](#) instance.

```
public RelmModel Duplicate()
```

Returns

[RelmModel](#)

A new [RelmModel](#) instance that is a shallow copy of the current instance.

Remarks

The returned object is a shallow copy, meaning that only the top-level fields of the object are duplicated. References to other objects within the instance are not deeply copied.

GenerateDTO(IEnumerable<string>, IEnumerable<string>, string, Func<IRelmModel, Dictionary<string, object>>, int)

Generates a dynamic Data Transfer Object (DTO) containing properties from the current object based on specific inclusion and exclusion criteria.

```
public dynamic GenerateDTO(IEnumerable<string> includeProperties = null, IEnumerable<string>  
excludeProperties = null, string sourceObjectName = null, Func<IRelmModel,
```

```
Dictionary<string, object>> getAdditionalObjectProperties = null, int iteration = 0)
```

Parameters

includeProperties [IEnumerable](#) <[string](#)>

A collection of property names to explicitly include in the DTO, even if they are not marked with the [RelmDto](#) attribute.

excludeProperties [IEnumerable](#) <[string](#)>

A collection of property names to explicitly exclude from the DTO, even if they are marked with the [RelmDto](#) attribute.

sourceObjectName [string](#)

An optional string representing the source object name, used to resolve nested property paths.

getAdditionalObjectProperties [Func](#) <[IRelmModel](#), [Dictionary](#) <[string](#), [object](#)>>

A function that provides additional properties to include in the DTO. The function takes the current object as input and returns a dictionary of property names and values.

iteration [int](#)

The current recursion depth, used internally to track nested object processing. Defaults to 0.

Returns

dynamic

A dynamic object containing the selected properties from the current object. The resulting object includes properties marked with the [RelmDto](#) attribute, explicitly included properties, and additional properties provided by the **getAdditionalObjectProperties** function, while excluding explicitly excluded properties.

Remarks

This method supports recursive generation of DTOs for nested objects. If a property is a collection of objects, each item in the collection is processed recursively. Properties not marked with the [RelmDto](#) attribute are included only if explicitly specified in **includeProperties**.

GetUnderscoreProperties(bool)

Retrieves a list of properties for the current object, with their names converted to underscore-separated format.

```
public List<KeyValuePair<string, Tuple<string, PropertyInfo>>> GetUnderscoreProperties(bool  
getOnlyRealmColumns = true)
```

Parameters

getOnlyRealmColumns [bool](#)

A value indicating whether to include only properties marked with the **RealmColumn** attribute. If [true](#), only such properties are included; otherwise, all properties are included.

Returns

[List](#) < [KeyValuePair](#) < [string](#), [Tuple](#) < [string](#), [PropertyInfo](#) > > >

A list of key-value pairs where the key is the underscore-separated name of the property, and the value is a tuple containing the original property name and its [PropertyInfo](#) metadata.

ResetCoreAttributes(bool, bool)

Resets the core attributes of the model to their default values.

```
public IRealmModel ResetCoreAttributes(bool nullInternalId = false, bool resetCreateDate  
= true)
```

Parameters

nullInternalId [bool](#)

If [true](#), sets the internal ID to [null](#); otherwise, generates a new unique identifier.

resetCreateDate [bool](#)

If [true](#), resets the creation date to the current date and time.

Returns

[IRelmModel](#)

The current instance of the model with updated core attributes.

ResetWithData(DataRow, string)

Resets the current model instance with data from the specified [DataRow](#).

```
public IRelmModel ResetWithData(DataRow modelData, string alternateTableName = null)
```

Parameters

modelData [DataRow](#)

The [DataRow](#) containing the data to populate the model. The column names in the [DataRow](#) should match the model's property names, using underscore naming conventions.

alternateTableName [string](#)

An optional alternate table name used to match column names in the [DataRow](#). If not provided, the model's type name is used as the table name.

Returns

[IRelmModel](#)

The current model instance, updated with the data from the specified [DataRow](#).

Remarks

This method maps the columns in the provided [DataRow](#) to the model's properties based on underscore naming conventions. If a property has a `Newtonsoft.Json.JsonConverterAttribute`, the data is deserialized using the specified JSON converter. The method supports both default column names and column names suffixed with the table name.

WriteToDatabase(MySqlConnection, MySqlConnection, int, bool, bool, bool, bool)

Writes the current object to the database using the table specified in the `RelmTable` attribute.

```
public int WriteToDatabase(MySqlConnection existingConnection, MySqlTransaction
sqlTransaction = null, int batchSize = 100, bool allowAutoIncrementColumns = false, bool
allowPrimaryKeyColumns = false, bool allowUniqueColumns = false, bool allowAutoDateColumns
= false)
```

Parameters

existingConnection MySqlConnection

An existing and open `MySql.Data.MySqlClient.MySqlConnection` to use for writing the data. The connection must remain open for the duration of the operation.

sqlTransaction MySqlTransaction

An optional `MySql.Data.MySqlClient.MySqlTransaction` under which the data will be written. If not provided, the operation will execute outside of a transaction.

batchSize [int](#)

The number of rows to write to the database in each batch. Must be greater than zero. Defaults to 100.

allowAutoIncrementColumns [bool](#)

A value indicating whether auto-increment columns should be included in the write operation. If [true](#), auto-increment columns will be written; otherwise, they will be excluded.

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns should be included in the write operation. If [true](#), primary key columns will be written; otherwise, they will be excluded.

allowUniqueColumns [bool](#)

A value indicating whether unique columns should be included in the write operation. If [true](#), unique columns will be written; otherwise, they will be excluded.

allowAutoDateColumns [bool](#)

A value indicating whether auto-generated date columns (e.g., timestamps) should be included in the write operation. If [true](#), auto-date columns will be written; otherwise, they will be excluded.

Returns

[int](#)

The number of rows successfully written to the database.

Remarks

This method performs a bulk write operation to the database. The table to which the data is written is determined by the `RealmTable` attribute applied to the object's type. Ensure that the database schema matches the structure of the object being written.

WriteToDatabase(IRelmContext, int, bool, bool, bool, bool)

Writes the current object to the database using the table specified in the `RealmTable` attribute.

```
public int WriteToDatabase(IRelmContext relmContext, int batchSize = 100, bool
allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool
allowUniqueColumns = false, bool allowAutoDateColumns = false)
```

Parameters

`relmContext` [IRelmContext](#)

An [IRelmContext](#) instance that provides an open connection and transaction for database operations.

`batchSize` [int](#)

The number of items to write to the database in each batch. Must be greater than zero. The default value is 100.

`allowAutoIncrementColumns` [bool](#)

A value indicating whether columns marked as auto-increment are allowed to be written. If [true](#), auto-increment columns will be included in the write operation; otherwise, they will be excluded.

`allowPrimaryKeyColumns` [bool](#)

A value indicating whether primary key columns are allowed to be written. If [true](#), primary key columns will be included in the write operation; otherwise, they will be excluded.

`allowUniqueColumns` [bool](#)

A value indicating whether columns with unique constraints are allowed to be written. If [true](#), unique columns will be included in the write operation; otherwise, they will be excluded.

`allowAutoDateColumns` [bool](#)

A value indicating whether columns with automatic date generation (e.g., timestamps) are allowed to be written. If [true](#), such columns will be included in the write operation; otherwise, they will be excluded.

Returns

[int](#)

The number of rows successfully written to the database.

Remarks

This method performs a bulk write operation to the database. The behavior of the write operation can be customized using the optional parameters to control whether specific types of columns (e.g., auto-increment, primary key, unique, or auto-date columns) are included in the operation. The table to which the object is written is determined by the `RealmTable` attribute applied to the object's type.

WriteToDatabase(IRelmQuickContext, int, bool, bool, bool, bool)

Writes the current object to the database using the table specified in the `RealmTable` attribute.

```
public int WriteToDatabase(IRelmQuickContext relmContext, int batchSize = 100, bool
allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool
allowUniqueColumns = false, bool allowAutoDateColumns = false)
```

Parameters

`relmContext` [IRelmQuickContext](#)

The database context used to perform the write operation. This context must be properly configured to connect to the target database.

`batchSize` [int](#)

The number of records to include in each batch during the bulk write operation. The default value is 100.

`allowAutoIncrementColumns` [bool](#)

A value indicating whether columns with auto-increment constraints are allowed to be written. If [true](#), auto-increment columns will be included in the write operation; otherwise, they will be excluded. The default value is [false](#).

`allowPrimaryKeyColumns` [bool](#)

A value indicating whether primary key columns are allowed to be written. If [true](#), primary key columns will be included in the write operation; otherwise, they will be excluded. The default value is [false](#).

`allowUniqueColumns` [bool](#)

A value indicating whether columns with unique constraints are allowed to be written. If [true](#), unique columns will be included in the write operation; otherwise, they will be excluded. The default value is [false](#).

`allowAutoDateColumns` [bool](#)

A value indicating whether columns with automatic date constraints (e.g., timestamps) are allowed to be written. If [true](#), such columns will be included in the write operation; otherwise, they will be excluded. The default value is [false](#).

Returns

[int](#)

The number of records successfully written to the database.

Remarks

This method performs a bulk write operation, which can improve performance when writing large amounts of data. Ensure that the provided `realmContext` is properly configured and that the database schema matches the structure of the data being written. The behavior of the write operation can be customized using the provided options.

WriteToDatabase(RelmContextOptionsBuilder, int, bool, bool, bool, bool)

Writes the current object to the database using the table specified in the `RelmTable` attribute.

```
public int WriteToDatabase(RelmContextOptionsBuilder realmContextOptions, int batchSize = 100, bool allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool allowUniqueColumns = false, bool allowAutoDateColumns = false)
```

Parameters

`realmContextOptions` [RealmContextOptionsBuilder](#)

The options used to configure the database context.

`batchSize` [int](#)

The number of records to process in each batch. Defaults to 100.

`allowAutoIncrementColumns` [bool](#)

A value indicating whether columns with auto-increment constraints are allowed to be written. Defaults to [false](#).

`allowPrimaryKeyColumns` [bool](#)

A value indicating whether primary key columns are allowed to be written. Defaults to [false](#).

`allowUniqueColumns` [bool](#)

A value indicating whether columns with unique constraints are allowed to be written. Defaults to [false](#).

`allowAutoDateColumns` [bool](#)

A value indicating whether columns with automatic date generation (e.g., timestamps) are allowed to be written. Defaults to [false](#).

Returns

[int](#)

The number of records successfully written to the database.

Remarks

This method performs a bulk write operation, which can improve performance when writing large datasets. Ensure that the specified options and constraints align with the database schema to avoid runtime errors.

WriteToDatabase(Enum, int, bool, bool, bool, bool)

Writes the current object to the database using the table specified in the `RealmTable` attribute.

```
public int WriteToDatabase(Enum connectionStringType, int batchSize = 100, bool
allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool
allowUniqueColumns = false, bool allowAutoDateColumns = false)
```

Parameters

connectionStringType [Enum](#)

The type of connection to use for the database operation.

batchSize [int](#)

The number of items to write to the database per batch. Must be a positive integer. Defaults to 100.

allowAutoIncrementColumns [bool](#)

A value indicating whether columns with auto-increment constraints are allowed to be written. Set to [true](#) to allow writing to such columns; otherwise, [false](#).

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns are allowed to be written. Set to [true](#) to allow writing to primary key columns; otherwise, [false](#).

allowUniqueColumns [bool](#)

A value indicating whether unique constraint columns are allowed to be written. Set to [true](#) to allow writing to such columns; otherwise, [false](#).

allowAutoDateColumns [bool](#)

A value indicating whether columns with automatic date generation (e.g., timestamps) are allowed to be written. Set to [true](#) to allow writing to such columns; otherwise, [false](#).

Returns

[int](#)

The number of rows successfully written to the database.

Remarks

This method performs a bulk write operation to the database. The table to which the data is written is determined by the `RealmTable` attribute applied to the current object's type. Ensure that the database

schema matches the structure of the object being written.

Events

DtoTypeProcessor

Occurs when a DTO (Data Transfer Object) is processed.

```
public event EventHandler<DtoEventArgs> DtoTypeProcessor
```

Event Type

[EventHandler](#)  [<DtoEventArgs>](#)

Remarks

This event is triggered after a DTO has been processed, providing the processed DTO as part of the event data. Subscribers can use this event to perform additional actions or handle the processed DTO as needed.

Class RelmModelApartment

Namespace: [SimpleRelm.Models](#)

Assembly: SimpleRelm.dll

```
public class RelmModelApartment : RelmModel, IRelmModel, IRelmModelApartment
```

Inheritance

[object](#)  ← [RelmModel](#) ← RelmModelApartment

Implements

[IRelmModel](#), [IRelmModelApartment](#)

Inherited Members

[RelmModel.DtoTypeProcessor](#) , [RelmModel.Id](#) , [RelmModel.Active](#) , [RelmModel.InternalId](#) ,
[RelmModel.CreateDate](#) , [RelmModel.LastUpdated](#) , [RelmModel.ResetCoreAttributes\(bool, bool\)](#) ,
[RelmModel.ResetWithData\(DataRow, string\)](#) , [RelmModel.GetUnderscoreProperties\(bool\)](#) ,
[RelmModel.WriteToDatabase\(Enum, int, bool, bool, bool, bool\)](#) ,
[RelmModel.WriteToDatabase\(MySqlConnection, MySqlTransaction, int, bool, bool, bool, bool\)](#) ,
[RelmModel.WriteToDatabase\(IRelmContext, int, bool, bool, bool, bool\)](#) ,
[RelmModel.WriteToDatabase\(IRelmQuickContext, int, bool, bool, bool, bool\)](#) ,
[RelmModel.WriteToDatabase\(RelmContextOptionsBuilder, int, bool, bool, bool, bool\)](#) ,
[RelmModel.CopyFromSource<T>\(T\)](#) ,
[RelmModel.GenerateDTO\(IEnumerable<string>, IEnumerable<string>, string, Func<IRelmModel, Dictionary<string, object>>, int\)](#) ,
[RelmModel.Duplicate\(\)](#) , [object.ToString\(\)](#)  , [object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  ,
[object.ReferenceEquals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  , [object.GetType\(\)](#)  ,
[object.MemberwiseClone\(\)](#) 

Extension Methods

[ModelExtensions.LoadDataLoaderField<T, S>\(T, IRelmContext, Expression<Func<T, S>>\)](#) ,
[ModelExtensions.LoadDataLoaderField<T, S>\(T, IRelmQuickContext, Expression<Func<T, S>>\)](#) ,
[ModelExtensions.LoadDataLoaderField<T, S>\(T, RelmContextOptionsBuilder, Expression<Func<T, S>>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R>\(T, IRelmContext, Expression<Func<T, ICollection<R>>>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R>\(T, IRelmContext, Expression<Func<T, ICollection<R>>>, Expression<Func<R, object>>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R>\(T, IRelmContext, Expression<Func<T, R>>\)](#) ,
[ModelExtensions.LoadForeignKeyField<T, R>\(T, IRelmContext, Expression<Func<T, R>>, Expression<Func<R, object>>\)](#) ,

[illegible]

Constructors

RelmModelApartment()

```
public RelmModelApartment()
```

RelmModelApartment(IRelmModel)

```
public RelmModelApartment(IRelmModel fromModel)
```

Parameters

fromModel [IRelmModel](#)

RelmModelApartment(DataRow, string)

```
public RelmModelApartment(DataRow ModelData, string AlternateTableName = null)
```

Parameters

ModelData [DataRow](#)

AlternateTableName [string](#)

Properties

ApartmentId

```
[RelmColumn(null, -1, null, true, false, false, false, null, null, false, false, false)]  
public string ApartmentId { get; set; }
```

Property Value

[string](#)

Member

```
[RealmColumn(null, -1, null, true, false, false, false, null, null, false, false, false)]  
public IRealmMember Member { get; set; }
```

Property Value

[IRealmMember](#)

UserEmail

```
[RealmColumn(null, -1, null, true, false, false, false, null, null, false, false, false)]  
public string UserEmail { get; set; }
```

Property Value

[string](#)

UserId

```
[RealmColumn(null, -1, null, true, false, false, false, null, null, false, false, false)]  
public int UserId { get; set; }
```

Property Value

[int](#)

UserName

```
[RealmColumn(null, -1, null, true, false, false, false, null, null, false, false, false)]  
public string UserName { get; set; }
```

Property Value

[string](#)

Methods

SetMemberApartment(int, bool)

```
public IRealmModelApartment SetMemberApartment(int MemberId, bool UpdateCreate = true)
```

Parameters

MemberId [int](#)

UpdateCreate [bool](#)

Returns

[IRealmModelApartment](#)

Class RelmQuickContext

Namespace: [SimpleRelm.Models](#)

Assembly: SimpleRelm.dll

```
public class RelmQuickContext : IRelmQuickContext, IDisposable
```

Inheritance

[object](#) ← RelmQuickContext

Implements

[IRelmQuickContext](#), [IDisposable](#)

Inherited Members

[object.ToString\(\)](#), [object.Equals\(object\)](#), [object.Equals\(object, object\)](#),
[object.ReferenceEquals\(object, object\)](#), [object.GetHashCode\(\)](#), [object.GetType\(\)](#),
[object.MemberwiseClone\(\)](#)

Constructors

RelmQuickContext(MySqlConnection, MySqlConnection, bool, bool, bool, int)

```
public RelmQuickContext(MySqlConnection connection, MySqlConnection transaction, bool  
autoOpenConnection = true, bool allowUserVariables = false, bool convertZeroDateTime =  
false, int lockWaitTimeoutSeconds = 0)
```

Parameters

connection MySqlConnection

transaction MySqlConnection

autoOpenConnection [bool](#)

allowUserVariables [bool](#)

convertZeroDateTime [bool](#)

lockWaitTimeoutSeconds [int](#)

RealmQuickContext(MySqlConnection, bool, bool, bool, bool, int)

```
public RealmQuickContext(MySqlConnection connection, bool autoOpenConnection = true, bool autoOpenTransaction = false, bool allowUserVariables = false, bool convertZeroDateTime = false, int lockWaitTimeoutSeconds = 0)
```

Parameters

connection MySqlConnection

autoOpenConnection [bool](#)

autoOpenTransaction [bool](#)

allowUserVariables [bool](#)

convertZeroDateTime [bool](#)

lockWaitTimeoutSeconds [int](#)

RealmQuickContext(RealmContextOptionsBuilder, bool, bool, bool, bool, int)

```
public RealmQuickContext(RealmContextOptionsBuilder optionsBuilder, bool autoOpenConnection = true, bool autoOpenTransaction = false, bool allowUserVariables = false, bool convertZeroDateTime = false, int lockWaitTimeoutSeconds = 0)
```

Parameters

optionsBuilder [RealmContextOptionsBuilder](#)

autoOpenConnection [bool](#)

autoOpenTransaction [bool](#)

allowUserVariables [bool](#)

convertZeroDateTime [bool](#)

lockWaitTimeoutSeconds [int](#)

RelmQuickContext(Enum, bool, bool, bool, bool, int)

```
public RelmQuickContext(Enum connectionStringType, bool autoOpenConnection = true, bool autoOpenTransaction = false, bool allowUserVariables = false, bool convertZeroDateTime = false, int lockWaitTimeoutSeconds = 0)
```

Parameters

connectionStringType [Enum](#)

autoOpenConnection [bool](#)

autoOpenTransaction [bool](#)

allowUserVariables [bool](#)

convertZeroDateTime [bool](#)

lockWaitTimeoutSeconds [int](#)

RelmQuickContext(string, bool, bool, bool, bool, int)

```
public RelmQuickContext(string connectionDetails, bool autoOpenConnection = true, bool autoOpenTransaction = false, bool allowUserVariables = false, bool convertZeroDateTime = false, int lockWaitTimeoutSeconds = 0)
```

Parameters

connectionDetails [string](#)

autoOpenConnection [bool](#)

autoOpenTransaction [bool](#)

allowUserVariables [bool](#)

convertZeroDateTime [bool](#)

lockWaitTimeoutSeconds [int](#)

Properties

ContextOptions

Gets the builder used to configure options for the current Realm context.

```
public RealmContextOptionsBuilder ContextOptions { get; }
```

Property Value

[RealmContextOptionsBuilder](#)

Methods

BeginTransaction()

```
public MySqlTransaction BeginTransaction()
```

Returns

MySqlTransaction

BulkTableWrite<T>(T, string, MySqlTransaction, Type, int, bool, bool, bool)

Performs a bulk write operation to insert or update data in the specified database table.

```
public int BulkTableWrite<T>(T SourceData, string TableName = null, MySqlTransaction  
sqlTransaction = null, Type ForceType = null, int BatchSize = 100, bool  
allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool  
allowUniqueColumns = false)
```

Parameters

SourceData `T`

TableName [string](#)

sqlTransaction `MySqlTransaction`

An optional `MySql.Data.MySqlClient.MySqlTransaction` to associate the bulk write operation with an existing transaction. If null, the operation will execute without a transaction.

ForceType [Type](#)

BatchSize [int](#)

allowAutoIncrementColumns [bool](#)

Indicates whether auto-increment columns in the target table are allowed to be explicitly written. Defaults to [false](#).

allowPrimaryKeyColumns [bool](#)

Indicates whether primary key columns in the target table are allowed to be explicitly written. Defaults to [false](#).

allowUniqueColumns [bool](#)

Indicates whether unique columns in the target table are allowed to be explicitly written. Defaults to [false](#).

Returns

[int](#)

The number of rows successfully written to the database table.

Type Parameters

T

The type of the source data. This can be a collection or a single object representing the data to be written.

Remarks

This method is optimized for high-performance bulk operations and supports optional batching to handle large datasets efficiently. Ensure that the source data aligns with the schema of the target table

to avoid runtime errors.

CommitTransaction()

Commits the current transaction, making all changes permanent in the database.

```
public void CommitTransaction()
```

Dispose()

Performs application-defined tasks associated with freeing, releasing, or resetting unmanaged resources.

```
public void Dispose()
```

Dispose(bool)

```
protected virtual void Dispose(bool disposing)
```

Parameters

disposing [bool](#)

DoDatabaseWork(string, Dictionary<string, object>, bool, bool)

Executes a database operation using the specified query and parameters.

```
public void DoDatabaseWork(string QueryString, Dictionary<string, object> Parameters = null,
bool throwException = true, bool useTransaction = false)
```

Parameters

QueryString [string](#)

Parameters [Dictionary](#) <[string](#), [object](#)>

throwException [bool](#)

A value indicating whether an exception should be thrown if the operation fails. If [true](#), an exception is thrown on failure; otherwise, the failure is silently handled.

useTransaction [bool](#)

A value indicating whether the operation should be executed within a transaction. If [true](#), the operation is wrapped in a transaction; otherwise, it is executed without one.

Remarks

This method allows for executing parameterized SQL queries with optional transaction support. Use the **throwException** parameter to control error handling behavior.

DoDatabaseWork(string, Func<MySqlCommand, object>, bool, bool)

Executes a database operation using the specified query and callback function.

```
public void DoDatabaseWork(string QueryString, Func<MySqlCommand, object> ActionCallback,
bool throwException = true, bool useTransaction = false)
```

Parameters

QueryString [string](#)

ActionCallback [Func](#) <MySqlCommand, [object](#)>

throwException [bool](#)

A value indicating whether to throw an exception if an error occurs during the operation. If [true](#), exceptions will be thrown; otherwise, errors will be suppressed.

useTransaction [bool](#)

A value indicating whether the operation should be executed within a database transaction. If [true](#), the operation will be wrapped in a transaction; otherwise, it will not.

Remarks

This method provides a flexible way to execute database operations by allowing the caller to define custom logic through the `actionCallback` parameter. Ensure that the `query` is properly sanitized to prevent SQL injection attacks.

DoDatabaseWork<T>(string, Dictionary<string, object>, bool, bool)

Executes a database query and returns the result as the specified type.

```
public T DoDatabaseWork<T>(string QueryString, Dictionary<string, object> Parameters = null,
    bool throwException = true, bool useTransaction = false)
```

Parameters

`QueryString` [string](#)

`Parameters` [Dictionary](#) <[string](#), [object](#)>

`throwException` [bool](#)

Specifies whether an exception should be thrown if the query fails. If [true](#), an exception is thrown on failure; otherwise, the method returns the default value of `T`.

`useTransaction` [bool](#)

Specifies whether the query should be executed within a transaction. If [true](#), the query is executed in a transactional context; otherwise, it is executed without a transaction.

Returns

`T`

The result of the query as an instance of type `T`. Returns the default value of `T` if `throwException` is [false](#) and the query fails.

Type Parameters

`T`

The type of the result expected from the query.

Remarks

Use this method to execute queries that return a single result, such as scalar values or objects. Ensure that the type **T** matches the expected result of the query to avoid runtime errors.

DoDatabaseWork<T>(string, Func<MySQLCommand, object>, bool, bool)

Executes a database operation using the specified query and callback function.

```
public T DoDatabaseWork<T>(string QueryString, Func<MySQLCommand, object> ActionCallback,
    bool throwException = true, bool useTransaction = false)
```

Parameters

QueryString [string](#) 

ActionCallback [Func](#)  <MySQLCommand, [object](#)  >

throwException [bool](#) 

A value indicating whether an exception should be thrown if an error occurs during the operation. The default value is [true](#) .

useTransaction [bool](#) 

A value indicating whether the operation should be executed within a database transaction. The default value is [false](#) .

Returns

T

The result of the operation, as returned by the **actionCallback** function.

Type Parameters

T

The type of the result returned by the callback function.

Remarks

This method provides a flexible way to execute database operations by allowing the caller to define the specific action to perform using the provided `MySQL.Data.MySqlClient.MySqlCommand` object. If `useTransaction` is [true](#), the operation will be executed within a transaction, which will be committed or rolled back based on the success or failure of the operation.

EndConnection(bool)

Ends the current connection and optionally commits any active transaction.

```
public void EndConnection(bool commitTransaction = true)
```

Parameters

`commitTransaction` [bool](#)

A value indicating whether to commit the active transaction before ending the connection. [true](#) to commit the transaction; [false](#) to roll it back. The default is [true](#).

Remarks

Use this method to cleanly terminate a connection. If a transaction is active, you can specify whether to commit or roll it back before the connection is closed. Ensure that any necessary operations are completed before calling this method, as the connection will no longer be available afterward.

~RealmQuickContext()

```
protected ~RealmQuickContext()
```

FirstOrDefault<T>(Expression<Func<T, bool>>, bool)

Retrieves the first element of a sequence from the data source that satisfies the specified condition, or a default value if no such element is found.

```
public T FirstOrDefault<T>(Expression<Func<T, bool>> predicate, bool loadDefault = false) where T : IRealmModel, new()
```

Parameters

predicate [Expression](#) <[Func](#) <T, [bool](#)>>

An expression that defines the condition to test each element for.

loadDataLoaders [bool](#)

A boolean value indicating whether to load associated data loaders for the retrieved element. If [true](#), data loaders will be initialized; otherwise, they will not be loaded.

Returns

T

The first element of type T that satisfies the specified condition, or the default value of T if no such element is found.

Type Parameters

T

The type of the elements in the sequence. Must implement [IRelmModel](#) and have a parameterless constructor.

GetBulkTableWriter<T>(string, bool, bool, bool, bool, bool)

Creates and returns a [BulkTableWriter<T>](#) instance for performing bulk insert operations on a database table.

```
public BulkTableWriter<T> GetBulkTableWriter<T>(string InsertQuery = null, bool
useTransaction = false, bool throwException = true, bool allowAutoIncrementColumns = false,
bool allowPrimaryKeyColumns = false, bool allowUniqueColumns = false)
```

Parameters

InsertQuery [string](#)

useTransaction [bool](#)

Specifies whether the bulk operation should be performed within a transaction. If [true](#), the operation is transactional; otherwise, it is not.

throwException [bool](#)

Specifies whether exceptions should be thrown if an error occurs during the bulk operation. If [true](#), exceptions are thrown; otherwise, errors are suppressed.

allowAutoIncrementColumns [bool](#)

Indicates whether auto-increment columns in the database table are allowed to be included in the bulk operation. If [true](#), these columns are included; otherwise, they are excluded.

allowPrimaryKeyColumns [bool](#)

Indicates whether primary key columns in the database table are allowed to be included in the bulk operation. If [true](#), these columns are included; otherwise, they are excluded.

allowUniqueColumns [bool](#)

Indicates whether unique columns in the database table are allowed to be included in the bulk operation. If [true](#), these columns are included; otherwise, they are excluded.

Returns

[BulkTableWriter](#)<T>

A [BulkTableWriter](#)<T> instance configured for the specified bulk operation settings.

Type Parameters

T

The type of the objects to be written to the database table. Each object represents a row in the table.

Remarks

The [BulkTableWriter](#)<T> provides an efficient way to insert large amounts of data into a database table. Use the optional parameters to customize the behavior of the bulk operation, such as enabling transactions or allowing specific column types.

GetDataList<T>(string, Dictionary<string, object>, bool)

Executes the specified query and retrieves a collection of data mapped to the specified type.

```
public IEnumerable<T> GetDataList<T>(string QueryString, Dictionary<string, object>  
Parameters = null, bool throwException = true)
```

Parameters

QueryString [string](#)

Parameters [Dictionary](#) <[string](#), [object](#)>

throwException [bool](#)

A value indicating whether an exception should be thrown if the query fails. If [true](#), an exception will be thrown on failure; otherwise, the method will return an empty collection.

Returns

[IEnumerable](#) <T>

An [IEnumerable<T>](#) containing the results of the query mapped to the specified type. Returns an empty collection if no results are found or if `throwException` is [false](#) and the query fails.

Type Parameters

T

The type to which the query results will be mapped.

GetDataObject<T>(string, Dictionary<string, object>, bool)

Executes the specified query and retrieves a data object of the specified type.

```
public T GetDataObject<T>(string QueryString, Dictionary<string, object> Parameters = null,  
bool throwException = true) where T : IRelmModel, new()
```

Parameters

QueryString [string](#)

Parameters [Dictionary](#) <[string](#), [object](#)>

throwException [bool](#)

A value indicating whether an exception should be thrown if the query fails or no data is found. If [true](#), an exception is thrown; otherwise, [default](#) is returned.

Returns

T

An instance of the specified type **T** populated with the data retrieved by the query. Returns [default](#) if no data is found and `throwException` is [false](#).

Type Parameters

T

The type of the data object to retrieve. Must implement [IRelmModel](#) and have a parameterless constructor.

GetDataObjects<T>(string, Dictionary<string, object>, bool)

Executes a query and retrieves a collection of data objects of the specified type.

```
public IEnumerable<T> GetDataObjects<T>(string QueryString, Dictionary<string, object>
Parameters = null, bool throwException = true) where T : IRelmModel, new()
```

Parameters

QueryString [string](#)

Parameters [Dictionary](#) <[string](#), [object](#)>

throwException [bool](#)

A boolean value indicating whether an exception should be thrown if the query fails. If [true](#), an exception is thrown on failure; otherwise, the method returns an empty collection.

Returns

[IEnumerable](#) <**T**>

An [IEnumerable<T>](#) containing the data objects retrieved by the query. Returns an empty collection if no data is found or if `throwException` is [false](#) and the query fails.

Type Parameters

T

The type of data objects to retrieve. Must implement [IRelmModel](#) and have a parameterless constructor.

GetDataRow(string, Dictionary<string, object>, bool)

Executes the specified query and retrieves the first row of the result set as a [DataRow](#).

```
public DataRow GetDataRow(string query, Dictionary<string, object> parameters = null, bool  
throwException = true)
```

Parameters

query [string](#)

The SQL query to execute. Must be a valid SQL statement.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. If null, no parameters are applied.

throwException [bool](#)

A boolean value indicating whether an exception should be thrown if the query does not return any rows. If [true](#), an exception is thrown when no rows are found; otherwise, [null](#) is returned.

Returns

[DataRow](#)

A [DataRow](#) representing the first row of the result set, or [null](#) if no rows are found and **throwException** is set to [false](#).

GetDataSet(Type)

Retrieves an initialized instance of a dataset based on the specified type.


```
public IRealmDataSetBase GetDataSet(Type dataSetType)
```

Parameters

dataSetType [Type](#)

The [Type](#) of the dataset to retrieve. This must be a type that implements [IRelmDataSetBase](#).

Returns

[IRelmDataSetBase](#)

An instance of the dataset that matches the specified type. Returns [null](#) if no matching dataset is found.

GetDataSet(Type, bool)

Retrieves an initialized instance of a dataset of the specified type.

```
public IRealmDataSetBase GetDataSet(Type dataSetType, bool throwException)
```

Parameters

dataSetType [Type](#)

The [Type](#) of the dataset to retrieve. This must implement [IRelmDataSetBase](#).

throwException [bool](#)

A value indicating whether an exception should be thrown if the dataset cannot be found. If [true](#), an exception is thrown when the dataset is not found; otherwise, [null](#) is returned.

Returns

[IRelmDataSetBase](#)

An instance of [IRelmDataSetBase](#) representing the requested dataset, or [null](#) if the dataset is not found and **throwException** is [false](#).

GetDataSetType(Type)

Retrieves an uninitialized dataset of type specified by `dataSetType`.

```
public IRealmDataSetBase GetDataSetType(Type dataSetType)
```

Parameters

`dataSetType` [Type](#)↗

The [Type](#)↗ of the dataset to retrieve. This must implement [IRealmDataSetBase](#).

Returns

[IRealmDataSetBase](#)

An instance of [IRealmDataSetBase](#) that corresponds to the specified `dataSetType`.

GetDataSetType(Type, bool)

Gets the dataset of the given type.

```
public IRealmDataSetBase GetDataSetType(Type dataSetType, bool throwException)
```

Parameters

`dataSetType` [Type](#)↗

Type of the dataset.

`throwException` [bool](#)↗

Returns

[IRealmDataSetBase](#)

An IDALDataSetBase instance of the given type.

Exceptions

[InvalidOperationException](#)↗

Thrown when no matching dataset is found.

GetDataSetType<T>()

Retrieves an uninitialized dataset of the specified type.

```
public IReImDataSet<T> GetDataSetType<T>() where T : IReImModel, new()
```

Returns

[IReImDataSet<T>](#)

An instance of [IReImDataSet<T>](#) representing the dataset of the specified type.

Type Parameters

T

The type of the dataset to retrieve. Must implement [IReImModel](#) and have a parameterless constructor.

Remarks

This method is generic and allows retrieval of datasets for any type that satisfies the constraints.

GetDataSetType<T>(bool)

Gets the dataset of the given type.

```
public IReImDataSet<T> GetDataSetType<T>(bool throwException) where T : IReImModel, new()
```

Parameters

throwException [bool](#) 

Returns

[IReImDataSet<T>](#)

An instance of IDALDataSet of the specified type.

Type Parameters

T

The type of the dataset, which should inherit from CS_DbModel.

Exceptions

[InvalidOperationException](#) 

Thrown when no matching dataset is found.

GetDataSet<T>()

Retrieves an initialized instance of a dataset of the specified type.

```
public IReImDataSet<T> GetDataSet<T>() where T : IReImModel, new()
```

Returns

[IReImDataSet](#)<T>

An instance of [IReImDataSet<T>](#) containing the data for the specified type.

Type Parameters

T

The type of the dataset to retrieve. Must implement [IReImModel](#) and have a parameterless constructor.

Remarks

Use this method to access a dataset for a specific model type. The type parameter **T** must represent a model that conforms to the [IReImModel](#) interface.

GetDataSet<T>(bool)

Retrieves an initialized instance of a dataset of the specified type.

```
public IRealmDataSet<T> GetDataSet<T>(bool throwException) where T : IRealmModel, new()
```

Parameters

throwException [bool](#)

A value indicating whether an exception should be thrown if the dataset cannot be retrieved. If [true](#), an exception is thrown on failure; otherwise, [null](#) is returned.

Returns

[IRealmDataSet](#)<T>

An instance of [IRealmDataSet](#)<T> containing the dataset of type T. Returns [null](#) if the dataset cannot be retrieved and **throwException** is [false](#).

Type Parameters

T

The type of the dataset to retrieve. Must implement [IRealmModel](#) and have a parameterless constructor.

GetDataTable(string, Dictionary<string, object>, bool)

Executes the specified SQL query and returns the results as a [DataTable](#).

```
public DataTable GetDataTable(string query, Dictionary<string, object> parameters = null, bool throwException = true)
```

Parameters

query [string](#)

The SQL query to execute. This must be a valid SQL statement.

parameters [Dictionary](#)<[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. If provided, the parameters will be added to the query to prevent SQL injection. Defaults to [null](#).

throwException [bool](#)

A value indicating whether an exception should be thrown if an error occurs during query execution. If [true](#), exceptions will be propagated to the caller. If [false](#), the method will suppress exceptions and return [null](#) in case of an error. Defaults to [true](#).

Returns

[DataTable](#)

A [DataTable](#) containing the results of the query. Returns [null](#) if **throwException** is [false](#) and an error occurs during execution.

Remarks

This method is designed to execute read-only queries, such as SELECT statements. It is not intended for executing queries that modify data (e.g., INSERT, UPDATE, DELETE).

GetIdFromInternalId(string, string)

Converts an internal identifier to its corresponding row identifier for a specified table.

```
public string GetIdFromInternalId(string Table, string InternalId)
```

Parameters

Table [string](#)

InternalId [string](#)

The internal identifier to be converted. Cannot be null or empty.

Returns

[string](#)

The row identifier corresponding to the specified internal identifier and table.

GetLastInsertId()

Retrieves the row identifier of the most recently inserted record in the database.

```
public string GetLastInsertId()
```

Returns

[string](#) 

The identifier of the last inserted record as a string. The format and value depend on the database implementation.

Remarks

This method is typically used after an insert operation to obtain the unique identifier generated for the new record. Ensure that the database connection and context are properly configured before calling this method.

GetScalar<T>(string, Dictionary<string, object>, bool)

Executes the specified SQL query and retrieves a single scalar value of the specified type.

```
public T GetScalar<T>(string query, Dictionary<string, object> parameters = null, bool  
throwException = true)
```

Parameters

query [string](#) 

The SQL query to execute. Must not be null or empty.

parameters [Dictionary](#)  [<string](#) , [object](#)  >

An optional dictionary of parameter names and values to include in the query. If null, no parameters are added.

throwException [bool](#) 

A boolean value indicating whether an exception should be thrown if the query fails. If [true](#) , an exception is thrown on failure; otherwise, the default value of **T** is returned.

Returns

T

The scalar value of type **T** returned by the query. If the query does not return a result and `throwException` is [false](#), the default value of **T** is returned.

Type Parameters

T

The type of the scalar value to return.

Remarks

Use this method to retrieve a single value, such as a count or aggregate result, from a database query. Ensure that the query is written to return only one value; otherwise, an exception may occur.

Get<T>(bool)

Retrieves a collection of entities of type **T** from the data source.

```
public ICollection<T> Get<T>(bool loadDataLoaders = false) where T : IRealmModel, new()
```

Parameters

loadDataLoaders [bool](#)

A boolean value indicating whether to load associated data loaders. If [true](#), data loaders will be initialized; otherwise, they will not.

Returns

[ICollection](#)<T>

A collection of objects of type **T**. The collection may be empty if no objects are found.

Type Parameters

T

The type of objects to retrieve. Must implement [IRealmModel](#) and have a parameterless constructor.

Get<T>(Expression<Func<T, bool>>, bool)

Retrieves a collection of entities of type **T** from the data source that satisfy the specified predicate.

```
public ICollection<T> Get<T>(Expression<Func<T, bool>> predicate, bool loadDataLoaders = false) where T : IReImModel, new()
```

Parameters

predicate [Expression](#) <[Func](#) <T, [bool](#)>>

An expression that defines the conditions the entities must satisfy.

loadDataLoaders [bool](#)

A boolean value indicating whether to load associated data loaders for the retrieved entities. [true](#) to load data loaders; otherwise, [false](#).

Returns

[ICollection](#) <T>

A collection of entities of type **T** that match the specified predicate. Returns an empty collection if no entities match.

Type Parameters

T

The type of the entities to retrieve. Must implement [IReImModel](#) and have a parameterless constructor.

HasDataSet(Type, bool)

Checks if the DALDataSet of a specific type is attached to the current DALContext instance.

```
public bool HasDataSet(Type dataSetType, bool throwException = true)
```

Parameters

`dataSetType` [Type](#)

The System.Type of the dataset to check.

`throwException` [bool](#)

Returns

[bool](#)

True if the dataset exists, otherwise false.

HasDataSet<T>(bool)

Checks if the DALDataSet of a specific type is attached to the current DALContext instance.

```
public bool HasDataSet<T>(bool throwException = true) where T : IRelmModel, new()
```

Parameters

`throwException` [bool](#)

Returns

[bool](#)

True if the dataset exists, otherwise false.

Type Parameters

T

The type of the dataset, which should inherit from CS_DbModel.

RollbackTransaction()

Rolls back the current transaction, undoing any changes made since the transaction began.

```
public void RollbackTransaction()
```

Remarks

This method should be called to revert changes if an error occurs or if the transaction cannot be completed successfully. Ensure that a transaction is active before calling this method; otherwise, an exception may be thrown.

RollbackTransactions()

Rolls back the current transaction, undoing any changes made since the transaction began.

```
public void RollbackTransactions()
```

Remarks

This method should be called to revert changes if an error occurs or if the transaction cannot be completed successfully. Ensure that a transaction is active before calling this method; otherwise, an exception may be thrown.

Run<T>(string, Dictionary<string, object>)

Executes the specified query and returns a collection of results mapped to the specified type.

```
public ICollection<T> Run<T>(string query, Dictionary<string, object> parameters = null)
where T : IRealmModel, new()
```

Parameters

query [string](#)

The query string to execute. This string must be a valid query in the context of the underlying data source.

parameters [Dictionary](#) <[string](#), [object](#)>

An optional dictionary of parameter names and values to be used in the query. If null, no parameters are applied.

Returns

[ICollection](#) <T>

A collection of objects of type **T** representing the query results. The collection will be empty if no results are found.

Type Parameters

T

The type of the objects in the result collection. Must implement [IRelmModel](#) and have a parameterless constructor.

SetDataLoader<T>(IRelmDataLoader<T>)

Configures the data loader for the specified model type.

```
public void SetDataLoader<T>(IRelmDataLoader<T> dataLoader) where T : IRelmModel, new()
```

Parameters

dataLoader [IRelmDataLoader](#)<T>

The data loader instance to associate with the specified model type. Cannot be [null](#)[↗].

Type Parameters

T

The type of the model that the data loader will handle. Must inherit from [RelmModel](#) and have a parameterless constructor.

StartConnection(bool, int)

Starts a connection to the database.

```
public void StartConnection(bool autoOpenTransaction = false, int lockWaitTimeoutSeconds = 0)
```

Parameters

autoOpenTransaction [bool](#)[↗]

Specifies whether a transaction should be automatically opened after the connection is established. Pass [true](#) to open a transaction automatically; otherwise, [false](#).

lockWaitTimeoutSeconds [int](#)

The lock wait timeout in seconds. A value of 0 indicates the default timeout for the database. Specify a positive integer to set a custom timeout duration.

Remarks

If **autoOpenTransaction** is set to [true](#), ensure that the transaction is committed or rolled back to avoid leaving it open. This method must be called before performing any database operations.

Where<T>(Expression<Func<T, bool>>)

Retrieves data from the data source, filtered based on the specified predicate.

```
public IRealmDataSet<T> Where<T>(Expression<Func<T, bool>> predicate) where T :  
    IRealmModel, new()
```

Parameters

predicate [Expression](#) <[Func](#) <T, [bool](#)>>

An expression that defines the conditions for filtering the dataset.

Returns

[IRelmDataSet](#) <T>

A new dataset containing only the elements that satisfy the specified predicate.

Type Parameters

T

The type of the model in the dataset. Must implement [IRelmModel](#) and have a parameterless constructor.

Remarks

The predicate is evaluated for each element in the dataset, and only those elements for which the predicate returns [true](#) are included in the result.

WriteToDatabase(IRelmModel, int, bool, bool, bool, bool)

Writes the specified [IRelmModel](#) to the database in batches.

```
public int WriteToDatabase(IRelmModel relmModel, int batchSize = 100, bool
allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool
allowUniqueColumns = false, bool allowAutoDateColumns = false)
```

Parameters

relmModel [IRelmModel](#)

The model containing the data to be written to the database. Cannot be [null](#).

batchSize [int](#)

The number of records to write in each batch. Must be greater than 0. The default value is 100.

allowAutoIncrementColumns [bool](#)

A value indicating whether columns with auto-increment constraints are allowed to be written. If [true](#), auto-increment columns will be included in the write operation; otherwise, they will be excluded.

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns are allowed to be written. If [true](#), primary key columns will be included in the write operation; otherwise, they will be excluded.

allowUniqueColumns [bool](#)

A value indicating whether columns with unique constraints are allowed to be written. If [true](#), unique columns will be included in the write operation; otherwise, they will be excluded.

allowAutoDateColumns [bool](#)

A value indicating whether columns with automatic date generation constraints are allowed to be written. If [true](#), auto-date columns will be included in the write operation; otherwise, they will be excluded.

Returns

[int](#)

The total number of records successfully written to the database.

Remarks

This method writes data to the database in batches to optimize performance. The behavior of the write operation can be customized using the boolean parameters to control the inclusion of specific column types.

WriteToDatabase(IEnumerable<IRelmModel>, int, bool, bool, bool, bool)

Writes a collection of Relm models to the database in batches.

```
public int WriteToDatabase(IEnumerable<IRelmModel> relmModels, int batchSize = 100, bool allowAutoIncrementColumns = false, bool allowPrimaryKeyColumns = false, bool allowUniqueColumns = false, bool allowAutoDateColumns = false)
```

Parameters

relmModels [IEnumerable](#) <[IRelmModel](#)>

The collection of models to be written to the database. Each model must implement the [IRelmModel](#) interface.

batchSize [int](#)

The number of models to include in each batch. Must be a positive integer. The default value is 100.

allowAutoIncrementColumns [bool](#)

A value indicating whether columns with auto-increment constraints are allowed to be written. If [true](#), auto-increment columns will be included; otherwise, they will be excluded. The default value is [false](#).

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns are allowed to be written. If [true](#), primary key columns will be included; otherwise, they will be excluded. The default value is [false](#).

allowUniqueColumns [bool](#)

A value indicating whether columns with unique constraints are allowed to be written. If [true](#), unique columns will be included; otherwise, they will be excluded. The default value is [false](#).

allowAutoDateColumns [bool](#)

A value indicating whether columns with automatic date generation constraints are allowed to be written. If [true](#), auto-date columns will be included; otherwise, they will be excluded. The default value is [false](#).

Returns

[int](#)

The total number of models successfully written to the database.

Remarks

This method processes the provided models in batches to optimize database writes. The behavior of the write operation can be customized using the optional parameters to control which types of columns are included.

Class RelmTrigger<T>

Namespace: [SimpleRelm.Models](#)

Assembly: SimpleRelm.dll

Represents a database trigger associated with a specific table and operation type.

```
public class RelmTrigger<T>
```

Type Parameters

T

The type representing the database table. The type must have a [RelmTable](#) attribute to define the table name.

Inheritance

[object](#)  ← RelmTrigger<T>

Inherited Members

[object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  , [object.ReferenceEquals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  , [object.GetType\(\)](#)  , [object.MemberwiseClone\(\)](#) 

Remarks

The [RelmTrigger<T>](#) class is used to define and manage database triggers for a table represented by the type **T**. It provides properties to configure the trigger's behavior, such as the trigger type, body, and associated database details. The table name is derived from the [RelmTable](#) attribute applied to the type.

Properties

DatabaseName

Gets or sets the name of the database.

```
public string DatabaseName { get; set; }
```

Property Value

[string](#)

DefinerUser

Gets or sets the name of the user who defined the current entity or operation.

```
public string DefinerUser { get; set; }
```

Property Value

[string](#)

StatementDelimiter

Gets or sets the delimiter used to separate individual statements in a batch.

```
public string StatementDelimiter { get; set; }
```

Property Value

[string](#)

Remarks

This property is typically used in scenarios where multiple statements are processed together, such as in database scripts or command batches. Ensure the delimiter matches the expected syntax of the target system.

TableName

Gets the name of the database table associated with this instance.

```
public string TableName { get; }
```

Property Value

[string](#)

TriggerBody

Gets or sets the body of the trigger event.

```
public string TriggerBody { get; set; }
```

Property Value

[string](#)

TriggerType

Gets the type of trigger associated with the current operation.

```
public Triggers.TriggerTypes TriggerType { get; }
```

Property Value

[Triggers.TriggerTypes](#)

Methods

ToString()

Generates a string representation of the SQL statement required to create a database trigger.

```
public override string ToString()
```

Returns

[string](#)

A string containing the complete SQL script to create the database trigger.

Remarks

The generated SQL includes the necessary statements to drop an existing trigger, set the delimiter, specify the definer, and create the trigger with the provided body and configuration. The output string is formatted to include the database name (if specified), the trigger name, and the trigger body. This method is useful for dynamically generating SQL scripts for database triggers.

Namespace SimpleReIm.Models.Event

Arguments

Classes

[DtoEventArgs](#)

Class DtoEventArgs

Namespace: [SimpleRealm.Models.EventArguments](#)

Assembly: SimpleRealm.dll

```
public class DtoEventArgs : EventArgs
```

Inheritance

[object](#) ← [EventArgs](#) ← DtoEventArgs

Inherited Members

[EventArgs.Empty](#), [object.ToString\(\)](#), [object.Equals\(object\)](#), [object.Equals\(object, object\)](#), [object.ReferenceEquals\(object, object\)](#), [object.GetHashCode\(\)](#), [object.GetType\(\)](#), [object.MemberwiseClone\(\)](#)

Properties

AdditionalObjectProperties

```
public Dictionary<string, object> AdditionalObjectProperties { get; set; }
```

Property Value

[Dictionary](#) <[string](#), [object](#)>

Namespace SimpleRealm.Options

Classes

[RealmContextOptionsBuilder](#)

Enums

[RealmContextOptionsBuilder.OptionsBuilderTypes](#)

Class RealmContextOptionsBuilder

Namespace: [SimpleRealm.Options](#)

Assembly: SimpleRealm.dll

```
public class RealmContextOptionsBuilder
```

Inheritance

[object](#)  ← RealmContextOptionsBuilder

Inherited Members

[object.ToString\(\)](#)  , [object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  ,
[object.ReferenceEquals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  , [object.GetType\(\)](#)  ,
[object.MemberwiseClone\(\)](#) 

Constructors

RealmContextOptionsBuilder()

```
public RealmContextOptionsBuilder()
```

RealmContextOptionsBuilder(MySqlConnection)

```
public RealmContextOptionsBuilder(MySqlConnection connection)
```

Parameters

connection MySqlConnection

RealmContextOptionsBuilder(MySqlConnection, MySqlConnectionTransaction)

```
public RealmContextOptionsBuilder(MySqlConnection connection, MySqlConnectionTransaction transaction)
```


Parameters

connection MySqlConnection

transaction MySqlTransaction

RealmContextOptionsBuilder(Enum)

```
public RealmContextOptionsBuilder(Enum connectionStringType)
```

Parameters

connectionStringType [Enum](#)

RealmContextOptionsBuilder(string)

```
public RealmContextOptionsBuilder(string connectionString)
```

Parameters

connectionString [string](#)

RealmContextOptionsBuilder(string, string, string, string)

```
public RealmContextOptionsBuilder(string databaseServer, string databaseName, string databaseUser, string databasePassword)
```

Parameters

databaseServer [string](#)

databaseName [string](#)

databaseUser [string](#)

databasePassword [string](#)

Properties

ConnectionStringType

```
public Enum ConnectionStringType { get; }
```

Property Value

[Enum](#)

DatabaseConnection

```
public MySqlConnection DatabaseConnection { get; }
```

Property Value

MySqlConnection

DatabaseConnectionString

```
public string DatabaseConnectionString { get; }
```

Property Value

[string](#)

DatabaseName

```
public string DatabaseName { get; }
```

Property Value

[string](#)

DatabasePassword

```
public string DatabasePassword { get; }
```

Property Value

[string](#)

DatabaseServer

```
public string DatabaseServer { get; }
```

Property Value

[string](#)

DatabaseTransaction

```
public MySqlTransaction DatabaseTransaction { get; }
```

Property Value

MySqlTransaction

DatabaseUser

```
public string DatabaseUser { get; }
```

Property Value

[string](#)

NamedConnection

```
public string NamedConnection { get; set; }
```

Property Value

[string](#) 

OptionsBuilderType

```
public RealmContextOptionsBuilder.OptionsBuilderTypes OptionsBuilderType { get; }
```

Property Value

[RealmContextOptionsBuilder.OptionsBuilderTypes](#)

Methods

ParseConnectionDetails(string)

```
public void ParseConnectionDetails(string connectionDetails)
```

Parameters

connectionDetails [string](#) 

SetConnectionStringType(Enum)

```
public void SetConnectionStringType(Enum connectionStringType)
```

Parameters

connectionStringType [Enum](#) 

SetConnectionStringType(Type, Enum)

```
public void SetConnectionStringType(Type enumType, Enum connectionStringType)
```

Parameters

enumType [Type](#)↗

connectionStringType [Enum](#)↗

SetDatabaseConnection(MySqlConnection)

```
public void SetDatabaseConnection(MySqlConnection connection)
```

Parameters

connection MySqlConnection

SetDatabaseConnectionString(string)

```
public void SetDatabaseConnectionString(string DatabaseConnectionString)
```

Parameters

DatabaseConnectionString [string](#)↗

SetDatabaseName(string)

```
public void SetDatabaseName(string databaseName)
```

Parameters

databaseName [string](#)↗

SetDatabasePassword(string)

```
public void SetDatabasePassword(string databasePassword)
```

Parameters

databasePassword [string](#) 

SetDatabaseServer(string)

```
public void SetDatabaseServer(string databaseServer)
```

Parameters

databaseServer [string](#) 

SetDatabaseTransaction(MySqlTransaction)

```
public void SetDatabaseTransaction(MySqlTransaction transaction)
```

Parameters

transaction `MySqlTransaction`

SetDatabaseUser(string)

```
public void SetDatabaseUser(string databaseUser)
```

Parameters

databaseUser [string](#) 

SetNamedConnection(string)

```
public void SetNamedConnection(string namedConnection)
```

Parameters

namedConnection [string](#) 

ValidateAllSettings(bool)

```
public bool ValidateAllSettings(bool throwExceptions = true)
```

Parameters

throwExceptions [bool](#) 

Returns

[bool](#) 

Enum

RealmContextOptionsBuilder.OptionsBuilderTypes

Namespace: [SimpleRealm.Options](#)

Assembly: SimpleRealm.dll

```
public enum RealmContextOptionsBuilder.OptionsBuilderTypes
```

Fields

```
ConnectionString = 0
```

```
NamedConnectionString = 1
```

```
OpenConnection = 2
```


Namespace SimpleRelm.Persistence

Classes

[BulkTableWriter<T>](#)

Class BulkTableWriter<T>

Namespace: [SimpleRealm.Persistence](#)

Assembly: SimpleRealm.dll

```
public class BulkTableWriter<T>
```

Type Parameters

T

Inheritance

[object](#)  ← BulkTableWriter<T>

Inherited Members

[object.ToString\(\)](#) , [object.Equals\(object\)](#) , [object.Equals\(object, object\)](#) ,
[object.ReferenceEquals\(object, object\)](#) , [object.GetHashCode\(\)](#) , [object.GetType\(\)](#) ,
[object.MemberwiseClone\(\)](#) 

Methods

AddColumn(string, MySqlDbType, int, string, string)

Adds a column definition to the bulk table writer.

```
public BulkTableWriter<T> AddColumn(string columnName, MySqlDbType dbType, int size, string  
    alternatePropertyName = null, string columnDefault = null)
```

Parameters

columnName [string](#) 

The name of the column to add. This value cannot be null or empty.

dbType [MySqlDbType](#)

The MySQL data type of the column.

size [int](#) 

The maximum size of the column, in bytes. Must be a non-negative value.

alternatePropertyName [string](#)

An optional alternate property name to map to this column. If null, the column will use the default property mapping.

columnDefault [string](#)

An optional default value for the column. If null, no default value will be applied.

Returns

[BulkTableWriter](#)<T>

The current [BulkTableWriter](#)<T> instance, allowing for method chaining.

AddColumns(IEnumerable<Tuple<string, MySqlDbType, int, string, string>>)

Adds the specified columns to the current table schema for bulk writing operations.

```
public BulkTableWriter<T> AddColumns(IEnumerable<Tuple<string, MySqlDbType, int, string, string>> columns)
```

Parameters

columns [IEnumerable](#)<[Tuple](#)<[string](#), [MySqlDbType](#), [int](#), [string](#), [string](#)>>>

A collection of tuples representing the columns to add. Each tuple contains the following elements:

- The column name ([string](#)).
- The MySQL data type of the column (MySql.Data.MySqlClient.MySqlDbType).
- The column size ([int](#)).
- The column collation ([string](#)).
- The column default value ([string](#)).

Returns

[BulkTableWriter](#)<T>

The current instance of [BulkTableWriter](#)<T>, allowing for method chaining.

Remarks

Columns with a null data type (`MySQL.Data.MySqlClient.MySqlDbType`) are ignored. If the `columns` parameter is null, no columns are added.

AddColumns(IEnumerable<Tuple<string, MySqlDbType, int>>)

Adds a collection of columns to the bulk table writer.

```
public BulkTableWriter<T> AddColumns(IEnumerable<Tuple<string, MySqlDbType, int>> columns)
```

Parameters

`columns` [IEnumerable](#) <[Tuple](#) <[string](#), `MySqlDbType`, [int](#)>>

A collection of tuples, where each tuple specifies the column name, the MySQL data type, and the column size.

Returns

[BulkTableWriter](#) <T>

The current instance of [BulkTableWriter](#) <T> with the specified columns added.

Remarks

This method allows you to define columns for the bulk table writer by providing their names, data types, and sizes. The additional metadata for each column, such as default values or constraints, is not specified in this overload.

AllowAutoDateColumns(bool)

Enables or disables the automatic inclusion of date columns in the bulk table writer.

```
public BulkTableWriter<T> AllowAutoDateColumns(bool allowAutoDateColumns)
```

Parameters

`allowAutoDateColumns` [bool](#)

A value indicating whether automatic date columns should be included. [true](#) to enable automatic date columns; otherwise, [false](#).

Returns

[BulkTableWriter](#)<T>

The current instance of [BulkTableWriter](#)<T>, allowing for method chaining.

AllowAutoIncrementColumns(bool)

Configures whether auto-increment columns are allowed during bulk table writing.

```
public BulkTableWriter<T> AllowAutoIncrementColumns(bool allowAutoIncrementColumns)
```

Parameters

allowAutoIncrementColumns [bool](#)

A value indicating whether auto-increment columns should be included. Specify [true](#) to allow auto-increment columns; otherwise, [false](#).

Returns

[BulkTableWriter](#)<T>

The current [BulkTableWriter](#)<T> instance, enabling method chaining.

AllowPrimaryKeyColumns(bool)

Configures whether primary key columns are allowed to be included in bulk write operations.

```
public BulkTableWriter<T> AllowPrimaryKeyColumns(bool allowPrimaryKeyColumns)
```

Parameters

allowPrimaryKeyColumns [bool](#)

A value indicating whether primary key columns should be included. [true](#) to allow primary key columns; otherwise, [false](#).

Returns

[BulkTableWriter](#)<T>

The current [BulkTableWriter](#)<T> instance, enabling method chaining.

Remarks

By default, primary key columns are typically excluded from bulk write operations to prevent unintended modifications to primary keys. Use this method to explicitly allow their inclusion if required.

AllowUniqueColumns(bool)

Configures whether unique columns are allowed during bulk table writing.

```
public BulkTableWriter<T> AllowUniqueColumns(bool allowUniqueColumns)
```

Parameters

allowUniqueColumns [bool](#)

A value indicating whether unique columns should be allowed. [true](#) to allow unique columns; otherwise, [false](#).

Returns

[BulkTableWriter](#)<T>

The current [BulkTableWriter](#)<T> instance, enabling method chaining.

AllowUserVariables(bool)

Enables or disables the use of user-defined variables in the bulk table writer.

```
public BulkTableWriter<T> AllowUserVariables(bool allowUserVariables)
```

Parameters

`allowUserVariables` [bool](#)

A value indicating whether user-defined variables are allowed. [true](#) to allow user-defined variables; otherwise, [false](#).

Returns

[BulkTableWriter](#)<T>

The current instance of [BulkTableWriter](#)<T>, allowing for method chaining.

RemoveColumn(string)

Removes the specified column from the table writer.

```
public BulkTableWriter<T> RemoveColumn(string columnName)
```

Parameters

`columnName` [string](#)

The name of the column to remove. This parameter is case-sensitive.

Returns

[BulkTableWriter](#)<T>

The current [BulkTableWriter](#)<T> instance, allowing for method chaining.

Remarks

If the specified column does not exist in the table, the method performs no action.

ResetBatchSize()

Resets the batch size to its default value.

```
public BulkTableWriter<T> ResetBatchSize()
```

Returns

[BulkTableWriter](#)<T>

The current [BulkTableWriter<T>](#) instance with the batch size reset.

Remarks

This method sets the batch size to the default value defined by the implementation. It can be used to revert any custom batch size previously set.

SetBatchSize(int)

Sets the batch size for bulk write operations.

```
public BulkTableWriter<T> SetBatchSize(int batchSize)
```

Parameters

batchSize [int](#)

The number of items to include in each batch. Must be a positive integer.

Returns

[BulkTableWriter](#)<T>

The current [BulkTableWriter<T>](#) instance, allowing for method chaining.

Remarks

The batch size determines how many items are processed together during a bulk write operation. Setting an appropriate batch size can help optimize performance based on the workload and system resources.

SetDatabaseName(string)

Sets the name of the database to be used for bulk table operations.

```
public BulkTableWriter<T> SetDatabaseName(string databaseName)
```


Parameters

databaseName [string](#) 

The name of the database. Cannot be null or empty.

Returns

[BulkTableWriter](#)<T>

The current instance of [BulkTableWriter<T>](#) to allow method chaining.

SetInsertQuery(string)

Sets the SQL insert query to be used for bulk data operations.

```
public BulkTableWriter<T> SetInsertQuery(string insertQuery)
```

Parameters

insertQuery [string](#) 

The SQL insert query string to execute during bulk operations. This query should be properly formatted and compatible with the target database.

Returns

[BulkTableWriter](#)<T>

The current instance of [BulkTableWriter<T>](#), allowing for method chaining.

SetSourceData(IEnumerable<T>)

Sets the source data to be written in bulk operations.

```
public BulkTableWriter<T> SetSourceData(IEnumerable<T> sourceData)
```

Parameters

sourceData [IEnumerable](#) <T>

The collection of data items to be used as the source for bulk writing. Cannot be null.

Returns

[BulkTableWriter](#) <T>

The current instance of [BulkTableWriter<T>](#) to allow method chaining.

SetSourceData(T)

Sets the source data for the bulk table writer.

```
public BulkTableWriter<T> SetSourceData(T sourceData)
```

Parameters

sourceData T

The source data to be written, represented as an instance of type T.

Returns

[BulkTableWriter](#) <T>

The current instance of [BulkTableWriter<T>](#), allowing for method chaining.

SetTableName(string)

Sets the name of the database table to which data will be written.

```
public BulkTableWriter<T> SetTableName(string tableName)
```

Parameters

tableName [string](#)

The name of the table. Cannot be null or empty.

Returns

[BulkTableWriter](#)<T>

The current [BulkTableWriter<T>](#) instance, allowing for method chaining.

SetTransaction(MySqlTransaction)

Sets the transaction to be used for the bulk table write operation.

```
public BulkTableWriter<T> SetTransaction(MySqlTransaction sqlTransaction)
```

Parameters

sqlTransaction MySqlTransaction

The `MySql.Data.MySqlClient.MySqlTransaction` instance to associate with the bulk table writer. This transaction will be used to execute the database operations.

Returns

[BulkTableWriter](#)<T>

The current [BulkTableWriter<T>](#) instance, allowing for method chaining.

ThrowException(bool)

Configures whether the writer should throw an exception when an error occurs during bulk writing.

```
public BulkTableWriter<T> ThrowException(bool throwException)
```

Parameters

throwException [bool](#) 

A value indicating whether exceptions should be thrown. [true](#)  to throw exceptions on errors; otherwise, [false](#) .

Returns

[BulkTableWriter<T>](#)

The current instance of [BulkTableWriter<T>](#), allowing for method chaining.

UseTransaction(bool)

Configures whether the bulk table writer should use a transaction during its operations.

```
public BulkTableWriter<T> UseTransaction(bool useTransaction)
```

Parameters

useTransaction [bool](#)

A value indicating whether to enable transaction usage. [true](#) to use a transaction; otherwise, [false](#).

Returns

[BulkTableWriter<T>](#)

The current instance of [BulkTableWriter<T>](#), allowing for method chaining.

Write()

Writes data to the underlying output stream.

```
public int Write()
```

Returns

[int](#)

The result of the write operation, as returned by the Write(object?) method.

Remarks

This overload calls the Write(object?) method with a [null](#) argument.

Write(Func<string, T, object>)

Executes a batch operation to process and insert data into a database using the specified function to populate a data table.

```
public int Write(Func<string, T, object> DataTableFunction)
```

Parameters

DataTableFunction [Func](#)<[string](#), T, [object](#)>

A function that takes a column name and a data item of type **T** and returns the value to be inserted into the data table.

Returns

[int](#)

The total number of records successfully inserted into the database. Returns 0 if there is no source data to process.

Remarks

This method processes the source data in batches, determined by the configured batch size, and inserts the data into the database. The method supports multiple database contexts and connections, and it uses the appropriate one based on the current configuration.

Namespace SimpleRelm.RelmInternal.Models

Classes

[ForeignKeyNavigationOptions](#)

Class to hold foreign key navigation options, used internally by SimpleRelm to manage relationships between models.

Class ForeignKeyNavigationOptions

Namespace: [SimpleRealm.RelmInternal.Models](#)

Assembly: SimpleRealm.dll

Class to hold foreign key navigation options, used internally by SimpleRealm to manage relationships between models.

```
public class ForeignKeyNavigationOptions
```

Inheritance

[object](#)  ← ForeignKeyNavigationOptions

Inherited Members

[object.ToString\(\)](#)  , [object.Equals\(object\)](#)  , [object.Equals\(object, object\)](#)  ,
[object.ReferenceEquals\(object, object\)](#)  , [object.GetHashCode\(\)](#)  , [object.GetType\(\)](#)  ,
[object.MemberwiseClone\(\)](#) 