

Removal of gDNA out of totalRNA

iGEM Dusseldorf1

¹Heinrich-Heine Universität Düsseldorf



dx.doi.org/10.17504/protocols.io.77bhrin



🔔 iGEM Dusseldorf 🕜



ABSTRACT

Start

Calculate the volume required for 1 µg RNA

Digestion of DNA

Component	amount
DNasel buffer	1 µl
total RNA	1 µg
DNasel	1 µl
H2O	to 10 µl

pipet components into a RNase-free 1.5 ml tube (following order: H₂O, buffer, total RNA, DNasel) incubate reaction at 37°C for 30 min

Extraction of DNasel-digested RNA

add 1 µl 50 mM EDTA and incubate at 65°C for 10 min add 1/10 Volume NaOAc and 3 Volumes 100% EtOH freeze at -20°C over night or at -80°C for at least 1h centrifuge at 13000 rpm for 10 min at 4°C Discard supernatant (RNA pellet could be not visible, important to know where it should be; it is definetly there) add 500 µl 70% EtOH centrifuge at 13000 rpm for 10 min at 4°C discard supernatant, remove as much ethanol as possible dry tubes at RT under the hood (~5min), do not overdry! resuspend pellet in 20 µl RNase-free water measure concentration

Quality control:

perform PCR on your DNA-free RNA (using primers 538/747; 57°C, 653 bp). Include a positive control using gDNA as a template. There should be no visible bands!

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited