

Version 3

Oct 10, 2018

Working

Scanning Electron Microscopy imaging for Opaline Silica Single Cell Skeletons (Polycystines Radiolaria) Version 3

Miguel Mendez Sandin¹

¹Station Blologique de Roscoff

dx.doi.org/10.17504/protocols.io.ug9etz6

Roscoff Plankton Group



Miguel Mendez Sandin Station Blologique de Roscoff



PROTOCOL STATUS

Working

We use this protocol in our group and it is working

Recovering skeletons

1 After DNA extraction, recover skeleton from the eluted pellet under binoculars or inverted microscope.

Note: During DNA extraction: dilute waste from the extraction procedure (i.e. pellet debris, containing the skeleton) in milliQ water and store skeletons at -20°C.

Protocol adapted from Biard et al. (2015).

Biard, T., Pillet, L., Decelle, J., Poirier, C., Suzuki, N., Not, F., 2015. Towards an Integrative Morpho-molecular Classification of the Collodaria (Polycystinea, Radiolaria). Protist 166, 374–388. doi:10.1016/j.protis.2015.05.002

Rinsing

? Rinse skeleton several times in milli-Q water to decrease the concentration of SDS and other lysis and DNA precipitation reagents.

Cleaning

- 3 Transfer skeleton into 1.5 ml Eppendorf tubes containing 50 μ l of hydrogen peroxide (H₂O₂).
- 4 Heat at 70°C for 10 min to remove residual organic matter.

Diluting

5 Add 1 ml of milli-Q water.

Rinsing

6 Handpick skeleton under binoculars or inverted microscope and repeat several rinsing steps.

Preparing for imaging

7 Transfer skeleton in a glued SEM pin stub mount with the less water as possible.

Note: no polycarbonate membrane, place the skeleton directly in the glue of the pin stub.

Drying

8 Let dry 30 minutes / 1 hour.

Imaging

9 Skeleton ready to be imaged.

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited