

2019

Working

UC Davis - Hydrogen Peroxide 👄

Peter Havel¹

¹University of California, Davis

dx.doi.org/10.17504/protocols.io.ypqfvmw

Mouse Metabolic Phenotyping Centers Tech. support email: info@mmpc.org



🔔 Lili Liang 🕜

ABSTRACT

Summary:

Hydrogen peroxide (H₂O₂) is a ubiquitous, toxic, metabolic by-product of aerobic respiration, oxidative stress, and oxidative injury. Cayman's Hydrogen Peroxide Assay Kit utilizes the well established xylenol orange detection method of quantifying the oxidation of ferrous ions (Fe2+) to ferric ions (Fe3+) by hydrogen peroxide. A unique feature of Cayman's assay is the inclusion of catalase as an H_2O_2 scavenger for the purpose of confirming the specificity of the reaction for H_2O_2 . The sensitivity and the specificity of the assay make it well suited to accurately measure urinary levels H_2O_2 in a 96 well plate format. Each kit contains hydrogen peroxide, reagent 1, reagent 2, catalase, a 96 well plate, plate cover, and complete instructions.

EXTERNAL LINK

https://mmpc.org/shared/document.aspx?id=128&docType=Protocol

MATERIALS


NAME ~	CATALOG # \	VENDOR ~	CAS NUMBER \vee RRID \vee
Assay Kit	706011	Cayman Chemical Company	
Reagent 1&2			
Standard			
Catalase			

MATERIALS TEXT

Note:

Cayman Chemical RRID:SCR_008945

H₂O₂ Standard Wells - add 20 μl of standard (tubes A-G) and 10 μl of HPLC-grade water per well in the designated wells on the plate (see Sample Plate Format, Figure 1, page 7).



SA-SG - Standards A-G 1-20 - Samples C1-20 - Samples + Catalase X - Extra Wells

Figure 1. Sample plate format

- 2 Sample Wells Each sample should have at least two wells that will not contain catalase and two wells that will contain catalase. Add 20 μl of sample to the sample and sample + catalase wells. Then add 10 μl of catalase to the catalase wells and 10 μl of HPLC-grade water to the non-catalase wells
- 3 Add 200 µl of Working Reagent to each well. Cover the plate with the plate cover and incubate on a shaker for one hour at room temperature.
- A Remove the plate cover and read the absorbance at 595 nm using a plate reader.

5 Calculation

- 1. Calculate the average absorbance of each standard, sample, and sample + catalase.
- 2. Substract the average absorbance of standard A from itself and from all other standards and samples including the catalase containing samples.
- 3. Plot the corrected absorbance of standards (from step 2 above) as a function of the final H_2O_2 concentration (μM) from Table 1. See Figure 2 (on page 13) for a typical standard curve.

Tube	Stock H ₂ O ₂ (µI)	HPLC-grade water (μ l)	Final Concentration (μΜ)	
Α	0	1,000	0	
В	25	975	11	
C	50	950	22	
D	75	925	33	
E	100	900	44	
F	125	875	55	
G	150	850	66	

Table 1. H₂O₂ standards




Figure 2. H₂O₂ Standard curve

- 4. Subtract the catalase sample absorbance from the non-catalase sample absprbance to yield the corrected sample absorbance.
- 5. Calculate the H_2O_2 concentration of the samples using the equation obtained from the linear regression of the standard curve substituting corrected absorbance values for each sample.

$$H_2O_2 \; (\mu M) = \left[\begin{array}{c} \frac{(\text{Corrected sample absorbance - (y-intercept)})}{\text{Slope}} \end{array} \right] \; x \; \text{Dilution}$$

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited