

Sep 24, 2019

Hornwort sporophyte induction -OXF V.1

Eftychis Frangedakis¹

¹University of Cambridge





- To induce sporophytes, plants were grown for one month in petri dishes on Lorbeer's medium.
- 2 Afterwards, plants were transferred to Magenta pots on 1/10 Knop medium (2.5 g/L K2HPO4, 2.5 g/L KH2PO4, 2.5 g/L KCL, 2.5 g/L MgSO4.7H2O, 10 g/L Ca(NO3)2.4H2O, 37 mg/L FeSO4.7H2O) at pH 6.2 and containing 0.7% (w/v) agar.
- 3 Pots were then placed in a Panasonic MLR-352 Versatile Environmental Test Chamber (16oC, 16 h of light and 8 h of dark, 1500 lux light intensity).
- 4 After approximately one month, antheridia started to appear and after one more month sporophytes emerged.

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited