



A protocol of molecular detection of phytoplasmas and Xylella spp. in post-entry quarantine for plants.

# Version 6

Takao Ito<sup>1</sup>, Ryoji Nakaune<sup>2</sup>

<sup>1</sup>Division of Grape and Persimmon Research, Institute of Fruit Tree and Tea Science, National Agriculture and Food Research Organization (NARO), Higashihiroshima, Hiroshima, Japan, <sup>2</sup>Institute of Fruit Tree and Tea Science, NARO, Tsukuba, Ibaraki, Japan

dx.doi.org/10.17504/protocols.io.vvme646

## Plantae



Takao Ito Ø



## ABSTRACT

In the STEPS, we describe TaqMan multiplex real-time PCR to universally detect phytoplasmas (PP) and Xylella spp. (XL) with plant internal control (IC) from crude extracts. A protocol file [Protocol-JpEnXX.pdf] shows further details of the protocol in Japanese and English.

THIS PROTOCOL ACCOMPANIES THE FOLLOWING PUBLICATION

Ito, T. & Suzaki, K. Universal detection of phytoplasmas and Xylella spp. by TaqMan singleplex and multiplex real-time PCR with dual priming oligonucleotides. PLoS ONE 12(9):e0185427. https://doi.org/10.1371/journal.pone.0185427 (2017)



Protocol-JpEn13.pdf

PROTOCOL STATUS

## Working

We use this protocol in our group and it is working

- 1. Extraction
  - 1.1. Crude extraction
  - 1.1.1. Put leaf petioles (§50mg), a metal beads, and 1mL extraction buffer into a tube.
  - 1.1.2.2,500 rpm 60 sec. (the Multi-beads shocker)
  - 1.1.3. 9.000 x a 10min 4C
  - 1.1.4. Transfer the supernatant to a new tube. Next steps, or keep it in a freezer.
- 1.2. Isopropanol precipitation
  - 1.2.1. NAdd an equal volume of cold isopropanol to the crude extract and mix.
  - 1.2.2.120,000 x g 5 min 4C
  - 1.2.3. Discard supernatants and dry pellets.
  - 1.2.4. Suspend the pellet in one-fifth volume of TE. Next steps, or keep it in a freezer.

3

## 2. Real-time PCR

## 2.1. Reagent mixture

Reagents	1 reaction	10 reactions
Sterile water	2.5	25
TaqMan FAST Advanced Master Mix	5	50
Primer mixture	1	10
Probe mixture	1	10
Total (µL)	9.5	95

- 2.2.MDispense  $9.5\,\mu L$  of the reagent mixture to PCR tubes
- $2.3.\mathbb{N}Add~0.5~\mu L$  of the extract (1.2.4) to the tube.
- 2.4. Set the tubes and run the StepOnePlus with the following parameters:

50C 2 min.  $\rightarrow$  95C 20 sec.  $\rightarrow$ 

95C 1 sec.  $\rightarrow$  60C 20 sec. 150 cycles 150

\* Targets®Reporter/Quencher®PP®FAM/NFQ-MGB®, XL®VIC/NFQ-MGB®, IC®TAMRA/None®

See the next step.

- ▲ 3. NData analysis
  - 3.1. Export data
  - 3.2. MConsider positives of PP/XL at Ct<45 and IC at Ct<40.
  - 3.3.MRefer the PDF file (a protocol in Japanese and English) in the Absract for detail.

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited