

Aug 20, 2019

96-well Plate Growth Curve Setup 👄

Norman van Rhijn¹, Panagiotis Papastamoulis², Takanori Furukawa¹, Magnus Rattray¹, Elaine Bignell¹, Mike Bromley¹

¹University of Manchester, ²Athens University of Economics and Business, Greece





ABSTRACT

Generally, growth assays for filamentous fungi have been performed on solid media, either as dilution series or spot tests. However, the solid media environment does not accurately mimic the environment encountered during infection (ie the mammalian lung). Previously, we have developed a methodology to perform liquid growth assays in time for *A. fumigatus* and other filamentous fungi including analysis via mathematical modelling.

This protocol is designed for *Aspergillus* species (and other filamentous fungi) to generate growth curves in liquid media in a 96-well plate. This can be done in high-throughput to generate 96 growth curves per run.

EXTERNAL LINK

https://www.ncbi.nlm.nih.gov/pubmed/31343979

THIS PROTOCOL ACCOMPANIES THE FOLLOWING PUBLICATION

Papastamoulis P, Furukawa T, van Rhijn N, Bromley M, Bignell E, Rattray M (2019). Bayesian detection of piecewise linear trends in replicated time-series with application to growth data modelling. The International Journal Of Biostatistics. DOI: 10.1515/ijb-2018-0052

SAFETY WARNINGS

Spores need to be handled within a Class II cabinet.

Plate preparation 30m

- 1 Harvest and dilute spores in PBS+0.01% Tween to 4*10⁵ spores/mL.
- 1.1 Aliquot 5 uL of this spore stock per well of a CytoOne 96-well plate (Starlab) non-coated, this will be overlayed with 195 uL of liquid media to a total volume of 200 uL.

This equals to 2000 spores (absolute) per well. 1000 spores or 500 spores are possible to use, but result in more variance within replicates.

2 Fill the space between the wells with either media or H₂0. This will avoid an "edge effect", where the wells around the edge of the plate show increased growth compared to other wells.

5m

20m

Machine setup 5m

4 In the Manchester Fungal Infection Group we either use a Powerwave X-2 with KC software or a BioTek platereader. Set this up to run for

3 48:00:00 at 3 37 °C to measure OD₆₀₀ every 10 minutes. Take a blank reading before running the plate and preheat the machine.

Run your experiment.

This will result in a "growth curve".

Extract or manipulate the data to look like attached (txt file format).

Analysis

3

5 See our next protocol for analysis.

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited