



Making low peptone NGM for imaging plates

Priota Islam¹

¹Imperial College London

dx.doi.org/10.17504/protocols.io.uxgexjw

Behavioural Genomics



PROTOCOL STATUS

Working

We use this protocol in our group and it is working

MATERIALS TEXT

Reagents:

For 500ml

A) Pre-Autoclave

- Sodium Chloride- 1.5g
- Difco Agar- 10g
- Difco Bactopeptone- 0.065g
- Cholesterol (5mg/ml in EtOH)- 0.5ml
- Deionized water- 482.5ml

B) Post-Autoclave

- 1M Cacl₂- 0.5ml
- 1M MgSO₄- 0.5ml
- 1M K₂HPO₄ (pH 6.0)- 12.5ml

Pre-Autoclave:

- Book the autoclave (notebook on top of the machine).
 - Take clean flasks from the glass kitchen.
 - Measure all the pre-autoclave reagents and add to the flask (Use a new weighing boat and spatula for each reagent. Also, the cholesterol is kept in the fridge.)
 - Once water is added mix thoroughly and label with autoclave tape ('Low peptone NGM Rm 5020').

Using the autoclave:

- 2 Turn ON the autoclave
 - Make sure that the autoclave's probe bottle is the same size as the largest bottle you use and fill it with water.
 - Place the temperature probe in it.
 - Fill up the autoclave with water until it reaches the grill.
 - Place the bottles in the autoclave and make sure that the cap is not screwed completely.
 - Check the waste flask is not too full
 - Use 'media' program.
 - Press START.
 - It will take about 2 hours for 500ml to autoclave

Post autoclave:

- When autoclave is complete, remove the probe flask
 - Make sure to wear gloves as the flask will be hot
 - Let the agar to cool to around 55°C and add the post autoclave reagents
 - Mix it well and start pouring onto small imaging plates (3.5ml in each) using a 3mm tube (See Protocol for plate pouring)

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited