



Oct 19, 2019

Starch Concentration Protocol

Victor Rodriguez¹

¹Independent Researcher



dx.doi.org/10.17504/protocols.io.8gbhtsn



ARSTRACT

The aim of this protocol is to extract and analyze the starch content of a plant in order to gain data into its metabolism and photosynthetic properties.

GUIDELINES

For proper extraction and spectroscopy of starch concentration you must be able to measure and transfer liquids within a hundred micro-liters ensure that samples are separated and free of contaminants.

MATERIALS

NAME ~	CATALOG # ~	VENDOR ~	
Acetone	AC1200.SIZE.1L	Bio Basic Inc.	
lodine Solution 0.9% Aldon Corporation	IS18019		
STEPS MATERIALS			
NAME ~	CATALOG #	VENDOR ~	
Acetone	AC1200.SIZE.1L	Bio Basic Inc.	
Acetone	AC1200.SIZE.1L	Bio Basic Inc.	
Acetone	AC1200.SIZE.1L	Bio Basic Inc.	
Acetone	AC1200.SIZE.1L	Bio Basic Inc.	
Acetone	AC1200.SIZE.1L	Bio Basic Inc.	

SAFETY WARNINGS

This protocol requires the use of flammable solvents, and require the extraction of pigments that may stain clothing. Proper lab coat, eye protection, gloves in ventilation are required to conduct this starch extraction and concentration protocol. Also, care must be taken to ensure that all materials used are disposed properly, as many of the chemicals may be hazardous to health and environment.

BEFORE STARTING

In order to perform this starch extraction protocol you will need the following materials and chemicals:

the materials listed are based on one single sample, in must be multiplied based on the number of samples you would like to test

One 20 ml (minimum) test tube

200 ml beaker

Two 200 micro-liters PCR tubes (although more may be needed based on the accuracy necessary for the procedures performed)

A 100 to 1000 micro-liter adjustable pipette

A 0.5 to 10 micro-liter adjustable pipette

- 5 disposable 1000 micro-liter pipette tips (Number varies based on need and mistakes)
- 5 disposable 10 micro-liter pipette tips (Number varies based on need and mistakes)

1200 g Centrifuge

Mortar and Pestle

Transfer Pipettes (as needed for contamination prevention)

50 ml Graduated Cylinder

Test tube stirrers

Approximate protocol time: 3 hours total

As needed Distilled water

15 ml Acetone

0.25g of sample

Spectrometer

Autoclave

Pigment Extraction

Weigh out **0.25** g of plant sample to be tested and add it to a 200ml beaker.

1m

1m

2 Add **⊒20 ml** of



Acetone

by Bio Basic Inc.

Catalog #: AC1200.SIZE.1L

to the test tube.

3 Let the sample/acetone suspension sit in a 200 ml beaker filled with distilled water and heat water until the of

10m



Acetone

by Bio Basic Inc.

Catalog #: AC1200.SIZE.1L

starts to boil.

4 Let test tube cool for **© 00:30:00** minutes to extract the pigments of the plant.

30m

5	Drain the	1m
	Acetone by Bio Basic Inc. Catalog #: AC1200.SIZE.1L	
	and add ⊒20 ml more	
	Acetone by Bio Basic Inc. Catalog #: AC1200.SIZE.1L	
	and put it back into the beaker heat water until the of	
	Acetone by Bio Basic Inc. Catalog #: AC1200.SIZE.1L	
	starts to boil.	
6	Let test tube cool for $© 00:30:00$ minutes more to finish extracting the pigments.	30m
7	Drain the test tube and transfer the sample to an autoclave for heating for \bigcirc 01:00:00 hour at \bigcirc 135 °C . This will loos up the starch for extraction.	1h sen

1m Remove the sample from the autoclave.

5m

Grind the sample with a mortar and pestle until a paste.

10 Add 35 ml of distilled water to the pestle and wash around to dissolve the sample into a suspension and clean the pestle. Ensure all of the sample is in the suspension.

Funnel the suspension into a test tube and add an additional **35 ml** of distilled water to the test tube using the same funnel as to wash out the funnel of stuck on sample particles.

1m Let stand for an hour covered. 12

To two labeled PCR tubes, add 200μ from each vial and centrifuge for 00:01:00 at $1200 \times g$.

15 Take 100 μl from each PCR tube and transfer it to clean PCR tubes labeled. Ensure that the sample is removed from the top to prevent sucking up settled particulates.

- 16 Add ■100 µl of distilled water to a PCR tube and calibrate the Spectrometer with it.
- 17 Insert each sample into the spectrometer.

The Absorbance of the samples are to be taken at the 610nm wavelength and the log base 10 of the absorbance percentage is noted.

19 Use the following function to determine the concentration...

$$C_{st} = (A_{610}*692.7_{g/mol}*V_{ml})/(2594*M_{sm})$$

With C_{st} being the starch concentration in mg/g, A_{610} is the absorbance at 610 nm, V_{ml} is the volume in ml of the water added to the sample for extraction, and M_{sm} is the mass in grams of the original sample taken.

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

5m

5m