

Immunohistochemistry-mounted slides

John Tompkins¹, Don Hoover², Jeffrey Ardell¹, Kalyanam Shivkumar¹

¹University of California, Los Angeles, ²ETSU

Works for me dx.doi.org/10.17504/protocols.io.2pagdie



Day 1

- Ø Using the PAP Pen, carefully draw a water barrier circle around the tissue sections on the slide allow this circle to dry for several seconds or up to approx. one min.
- Ø Rinse slides with PBS (pH 7.3-7.4): 4 x 5 min each
- Ø Rinse slides with 0.5% BSA + 0.4% Triton X-100 in PBS): 1 x 10 min
- Ø Remove slides one at a time and using a clean Kimwipe, carefully wipe around the tissue sections to dry the slide.
- Ø Place the slides into a black, covered slide incubation box/humidity box
- Ø Cover the tissue sections with blocking buffer (10% normal donkey serum in 1.0% BSA + 0.4% Triton X-100 + PBS)
- Ø Allow the sections to remain in blocking buffer for 1.5-2 hrs. at RT
- Ø Pour off the blocking buffer
- Ø Replace with primary antibody solution (antibody of choice diluted in 1.0% BSA + 0.4% Triton X-100 + PBS)
- Ø Incubate tissue with primary antibody overnight in incubation box.

2 Day 2

Ø Rinse slides with PBS: 4 x 5 min

- Ø Rinse slides with 0.5% BSA + 0.4% Triton X-100 + PBS: 1 x 10 min
- Ø Prepare fluorescent secondary antibody (secondary antibody should be diluted in 1.0% BSA + 0.4% Triton X-100 + PBS) (use Biotin-SP for the antibody that will later add Streptavidin to; if there is a second primary then use the normal secondary for it).
- Ø Cover the tissue with the secondary antibody solution and incubate for 2 hrs. at RT in the incubation box. *From this point on, use low light and/or cover tissues.*
- Ø Rinse slides with PBS: 4 x 5 min
- Ø Remove excess PBS with a Kimwipe.
- Ø Prepare fluorescent Streptavidin secondary antibody (should be diluted in 1.0% BSA + 0.4% Triton X-100 + PBS)
- Ø Cover the tissue with the fluorescent Streptavidin antibody solution and incubate for 2 hrs. at RT in the incubation box.
- Ø Rinse slides with PBS: 4 x 5 min
- Ø Remove excess PBS with a Kimwipe.
- Ø Carefully add a drop of Citifluor (or equivalent) mounting medium to the center of the tissue and apply cover glass.
- Ø Seal cover glass with clear nail polish. For thicker tissue, add a weight before sealing.

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited