

May 03, 2019

Working

Protocol for sampling and transport of nose- and thoratsamples in the Fit Futures study

Version 2

Dina Stensen¹, Anne-Sofie Furberg², Karina Olsen³, Gunnar Skov Simonsen³, Johanna UE Sollid⁴, Lars Småbrekke⁵, Guri Grimnes⁶, Cristopher Sievert Nielsen⁷

¹University hospital of North Norway, ²Department of Community Medicine, Faculty of Health Sciences, UiT The Arctic University of Norway, ³Department of Microbiology and Infection Control, University Hospital of North Norway, ⁴Research Group for Host-Microbe Interaction, Department of Medical Biology, ⁵Department of Pharmacy, Faculty of Health Sciences, UiT The Arctic University of Norway, ⁶Endocrinology Research Group, Department of Clinical Medicine, Faculty of Health Sciences, UiT The Arctic University of Norway, ⁷Division of Ageing and Health, Norwegian Institute of Public Health

dx.doi.org/10.17504/protocols.io.2j5gcq6



ABSTRACT

The aim of the study is to evaluate prevalence of *Staphylococcus aureus* in a youth population. This samples will be connected to other possible riskfactors for *Staphylococcus aureus* carriage.

MATERIALS

NAME V	CATALOG #	VENDOR V	CAS NUMBER $ imes$ RRID $ imes$
Sterile NaCl 9 mg/ml (0.9%)	View	B.Braun Medical Inc	
Sterile rayon-tipped swab	View	Puritan	
Transport medium - Amies Copan	View		
Tongue spatula - wood	View		
Hand disinfection	View	Antibac	

MATERIALS TEXT

4 Sterile rayon-tipped swabs for each participant

BEFORE STARTING

Wash hands with soap and water or use hand disinfection to prevent contamination of the samples. The examiner should use facemask to protect the participant if necessary. If the participant has secreation from the nasal cavity, the participant should blow ones nose before sampling.

Nasal samples

- 1 Moisture the rayon-tipped swab in 2-3 drops of sterile NaCl 0,9 mg/ml. There should be two samples from the nasal cavity.
- 2 Lead the rayon-tipped swab carefully into the nasal cavity approximately 1-2 cm and rotate with delicate pressure 3 times in both nasal cavity. The same swab should be used for both anterior nares.
- 3 Place both swabs in the Coban transport medium.
- 4 Label the transport medium with testnumber and nasal swab 1 and 2. Nasal swab 1 is used for detection of bacterial analysis, and swab 2 for microbiome analysis.

5 Wash hands with soap and water or use hand disinfection after procedure

Throat samples

- 6 Moisture the rayon-tipped swab in 2-3 drops of sterile NaCl 0,9 mg/ml. There should be two samples from the throat.
- 7 Ask the participant to open his/her mouth. Press the tongue spatula against the tongue and ask the participant to say "aaa". This will simplify the sampling because this will better the view of the tonsil region.
- 8 Lead the rayon-tipped swab into the oral cavity and swab with moderate pressure on both tonsil regions (palatine tonsils). If the participants has had a former tonsillectomy/tonsillotomy the swab should be taken from the area of the removed tonsils. Use the same swab on both tonsils.
- Q Place both swabs in the Coban transport medium.
- 10 Label the transport medium with testnumber and throat swab 1 and 2. Throat swab 1 is used for detection of bacterial analysis, and swab 2 for microbiome analysis.
- 11 Wash hands with soap and water or use hand disinfection after procedure

Transport

12 The swabs should be placed in a suitable rack. If not picked up immediately, the samples should be placed in refrigerator awating pickup.

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited