

Laura Armero H1

¹Universidad Complutense de Madrid

Structuralization and Incubation



dx.doi.org/10.17504/protocols.io.8hpht5n

AEGIS - Madrid iGEM 2019





ABSTRACT

The interaction between an aptamer and his target depends on the tertiary structure of the aptamer, to attempt to always have the same structure for all the rounds, we forced the aptamer population to achieve the most thermodynamic stable structure. Once all the sequences are structuralized, we can incubate the library with our target.

MATERIALS TEXT

- Aptamer library (order to IDT).
 - G TTG CTC GTA TTT AGG GAA TG N_{10} ACA CCA GTC TTC ATC CGC TTT $_6$
- -Thermoblock with agitation.
- Eppendorf tubes 1.5 mL.
- Bacteria strand (DHalfa5).
- Binding Buffer (pH=7,6):
 - 10 mM Tris-HCl
 - 150 mM NaCl
 - 5 mM MgCl₂

SAFETY WARNINGS

Be careful when using the thermoblock as the working temperature id dangerous.

BEFORE STARTING

Turn on the thermoblock at 95°C 15 min before start.

Check all working surfaces and materials are clean before start.

Day 0

- Preparation of the inoculum
- In 1mL of LB liquid medium, resuspend the E. coli cells. 1.1

Incubate it at 37 °C overnight with constant shaking at 180 rpm in a Incubator-shaker

2 Growing and harvesting cells

- 2.1 With the spectrophotometer set at λ = 600 nm, measure the growth of the inoculum. It should be \geq 1. If it's lower, it should be left growing until it reaches this value.
- 2.2 Take 250 μ L of bacteria and inoculate it in 25 ml LB media. (use 1% 0.D. as an inoculum for subculturing)
- 2.3 Incubate at 37°C, 180 rpm for 1.5h (until the culture reaches an O.D. between 0.5 0.6, which will indicate that the culture is in log-phase)
- 2.4 Centrifuge the tube at 3000 X g for 10 minutes
- 2.5 Remove supernatant and then wash the cells x3 with PBS (10 mM, pH 7.4). This will remove residual components from the previous step.
- 2.6 Measure the O.D. at λ =600 nm using a spectrophotometer at λ = 600 nm. The optical density (O.D.) should be \geq 1. This corresponds approximately to 1 x 10⁸ *E. coli* cells (diluted in PBS). Further dilutions can be done by adding PBS to tubes.
- 3 Add 10 μ L of 100 uM ssDNA library to 190 ul of binding buffer.

Incubate it at 95 °C for 10 min. After that, transfer immediately to ice-bath to prevent rehybridization of the single stranded DNA library. If the transfer is poor performed, you can reheat again for another 10 min and repeat.

4 Strcuturalization

5

4.1 Add 10 μ L of 100 uM ssDNA library to 190 ul of binding buffer.

Incubate it at 95 °C for 10 min. After that, transfer immediately to ice-bath to prevent rehybridization of the single-stranded DNA library. If the transfer is poor performed, you can reheat again for another 10 min and repeat.

Incubated at 4°C for 10 min. Then you attempered the library at room temperature for 10 min.

5.1 Resuspend 100 μ L of 1 x 10³ cells and add your library aptamer into a 1.5 ml Eppendorf tube. Place the tube into the thermoblock set and 40 °C and incubate with agitation for 1h.

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited