

Ligation Independent Cloning 👄

Addgene the nonprofit plasmid repository¹

¹Addgene

Works for me

dx.doi.org/10.17504/protocols.io.43tgynn



Addgene the nonprofit plasmid repository



ABSTRACT

This protocol describes Ligation Independent Cloning (LIC). To see the full abstract and additional resources, please visit the Addgene protocol page.

EXTERNAL LINK

https://www.addgene.org/protocols/lic/

GUIDELINES

General Overview

Empty vectors for LIC typically employ type II restriction enzymes (e.g. BsaI), which cut at a specified distance from their recognition sequence. This can create multiple distinct overhangs with a single enzyme, and remove the restriction sites from the final product (no "cloning scars"). A "stuffer" sequence allows for electrophoretic separation of linearized vector from the reaction mixture, and may provide counter-selection for negative clones as in the example shown here. The manufacturer of an LIC-specific vector will provide the homologous sequence which must be built into the 5' end of the respective primers. Below we use pNIC28-Bsa4 as an example of LIC experimental design.




figure 1: plasmid map diagram of pNIC28-Bsa4


Search Addgene's collection of empty LIC cloning vectors

SAFETY WARNINGS

See SDS (Safety Data Sheet) for safety warnings and hazards.

1 Design Your Primers

Primer design for LIC is often as simple as using the backbone manufacturer's suggested leader sequence fused to your gene of interest, in frame with the start codon or tag sequences (where appropriate). The primer length is dependent on the T4 Pol "chew back" reaction, in which a single dNTP is included to stop the exonuclease function of the enzyme and shift its activity back to polymerase. In our case, dGTP will be used in the reaction, meaning that T4 Pol will remove bases from the 3' end of the cut site until the first G is reached (shown in blue), at which point it will add back the G and become stalled. Therefore, the primer must begin with the following T, so that there are no gaps in the final assembly. In this case, 15 bp of homologous sequence is used, plus a minimum of 18 bp of your template sequence. 5' and 3' primers will have different leader sequences, but operate on the same principle (homologous to the first G on 3'-5' strand from cut site). For simplicity, only the 5' primer is shown here.





Use web-based primer design software to ensure a melting temperature between 50-60°C for your PCR primers.

2 Linearize Vector

In this example, the vector is cut at two points by the enzyme Bsal, removing the stuffer sequence and sacB counter-selection marker (see our <u>restriction digest protocol</u>). After the digest is complete, you will need to separate the linearized vector from the reaction mixture by <u>gel electrophoresis</u> followed by <u>gel purification</u>. The cut vector end will now look like this:





Elute your purified digestion and PCR products with sterile water (instead of TE buffer) to ensure optimal salt concentrations in subsequent reactions.

3 Create Vector Overhangs

Treat the linearized vector with T4 DNA polymerase to "chew back" the free 3' ends, following the manufacturer's instructions. In this case, we will include the free nucleotide dGTP in the reaction (exclude all other nucleotides from standard polymerase protocol), causing the enzyme to perform exonuclease activity until the first "G" in the sequence. Because the polymerase reaction is favored over the exonuclease reaction, the polymerase will add back the guanosine residue and become stalled.



A typical T4 Pol reaction is shown below. Mix the components (add the T4 last) and incubate at Room temperature for © 00:30:00. Inactivate T4 Pol by heating to 8 75 °C for © 00:20:00.

Volume (μl)	Reagent	Final concentration
4	10X Buffer	1X
20-30	Eluted DNA	10-50 ng/μl
1	dGTP (100 mM)	2.5 mM
2	DTT (100 mM)	5 mM
1	BSA (10 μg/μl)	0.25 μg/μl
1	T4 DNA Polymerase	0.075 units/μl
	Sterile dH20 to 40 µl	

Table 1: An example of a single T4 Pol reaction ($\boxed{40}$ μ l total)

4 Amplify Insert by PCR

Perform PCR amplification of your insert following the instructions provided by your polymerase manufacturer. It is very important to remove all free nucleotides from your PCR product before proceeding, as they will interfere with the exonuclease activity of T4 Pol in the following step. This may be accomplished by gel purification.



5 Create Insert Overhangs

Treat your purified PCR product with T4 Pol in the presence of dCTP (not dGTP), corresponding to the first base removed by the restriction digest to create the free 5' end of the cut vector (shown in blue here). The T4 reaction may be stopped by heating to \$75°C for \$\infty\$ 00:20:00 .



6 Anneal and Transform

§ Room temperature, then add □1 µl of 25 mM EDTA, followed by another ⊙ 00:05:00 at § Room temperature.

The reaction is now ready for transformation. Use $\boxed{1} \mu I - \boxed{2} \mu I$ of annealing reaction for each transformation, following a standard protocol.



This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited