

Measurement of XylE (Catechol 2,3-Dioxygenase) enzyme activity by microplate reader

Ji Gao¹


¹Tsinghua University





ABSTRACT

Simple measurement of XylE (Catechol 2,3-Dioxygenase) enzyme activity by microplate reader. Catechol 2,3-Dioxygenase can catalyze catechol (1,2-Dihydroxybenzene) to 2-HMS, which has a high absorbance at 377 nm, so we may use photometric mode of microplate reader to measure the concentration of 2-HMS, product of the enzyme.



GUIDELINES

This is part of a tryout for our iGEM project.

The microplate we used is listed here.



Perform the measurement at & Room temperature or & 25 °C .

MATERIALS

NAME V	CATALOG # ~	VENDOR ~
double distilled water (ddH20)		
12-Dihydroxybenzene	17253	Adamas-beta
Corning™ 96-Well Clear Bottom Black or White Polystyrene Microplates	07-200-565	Fisher Scientific

SAFETY WARNINGS

Catechol can be hazardous if not properly operated.

Please refer to https://pubchem.ncbi.nlm.nih.gov/compound/catechol#section=Safety-and-Hazards

BEFORE STARTING

Use [M]100 Milimolar (mM) catechol water solution as stock, and use [M]10 Milimolar (mM) as working solution.

We use LB cell culture (BL21 strain in our project) to perform measurement.

Add cell culture of a good state (logarithm phase) to 96-well plate.

Manual	stens
iviaiiuai	otcho

1 Add 100 μl cell culture per well.



It is recommanded to use replicates and controls to avoid mistakes or deviation.

2 Turn on the microplate reader and computer. Run the software to set the protocol and plate layout.

Protocol for the instrument

3 Shake the plate for **© 00:00:05** at **@ 600 rpm**.

- 4 Measure the absorbance of cell culture at 600 nm as the estimation of cell amounts.
- 5 Measure the absorbance of cell culture at 377 nm as the baseline of A377 before the reaction.
- 6 Plate out and add 2.5 μl catechol ([M]10 Milimolar (mM)) to every well, then plate in immediately.



The working concentration of substrate is [M]0.25 Milimolar (mM) here. Other working concentration could also work.

- 7 Shake the plate for \bigcirc **00:00:05** at \bigcirc **600 rpm** .
- Measure the absorbance of cell culture at 377 nm, continuously (like © 00:00:10 per reading) or after a certain period of time (like © 00:01:30).


9 Export the data from the software.




Properly dispose of the contaminated cell culture and microplates!

Normalize the A337 value by optical density at 600 nm.

Make a Time-A377 plot like this:



Or simply substract the absorbance before the reaction from the value after a specifc period of time:



This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited