# invertedClampFISH ligation

## **Benjamin Emert**

#### **Abstract**

Protocol for making invertedClampFISH probes.

Citation: Benjamin Emert invertedClampFISH ligation. protocols.io

dx.doi.org/10.17504/protocols.io.qnjdvcn

Published: 01 Jun 2018

#### **Materials**

T7 DNA Ligase - 750,000 units M0318L by New England Biolabs

T4 PNK M0201L by New England Biolabs

#### **Protocol**

## Probe backbone phosphorylation

#### Step 1.

Reconstitute invertedClampFISH arms, backbones and adaptors to 400uM in nuclease free water.

#### NOTES

## Benjamin Emert 01 Jun 2018

If the quantity of backbone oligos is very low, can reconstitute to 200uM and use twice as much for subsequent reactions.

#### Probe backbone phosphorylation

#### Step 2.

combine reaction components to phosphorylate unmodified backbone oligos

AMOUNT

10 μl Additional info: 2x T7 DNA ligase buffer

AMOUNT

1 μl Additional info: 400uM backbone oligo

AMOUNT

0.5 µl Additional info: T4 polynucleotide kinase

**■** AMOUNT

2 μl Additional info: nuclease free water

**■ TEMPERATURE** 

50 °C Additional info: thermal cycler lid

**▮** TEMPERATURE

37 °C Additional info: thermal cycler

#### NOTES

## Benjamin Emert 01 Jun 2018

If you plan to add the same invertedClampFISH arms to each backbone oligo, the phosphorylation and subsequent ligation can be done with multiple backbone oligos simultaneously. I have ligated 30 backbone probes at once, scaling up the reaction 2x-3x.

## Benjamin Emert 01 Jun 2018

You probably can incubate for a shorter duration. Overnight incubation is fine too.

#### invertedClampFISH probe ligation

#### Step 3.

Combine reaction components

**■** AMOUNT

1.5 μl Additional info: 400μM left arm

**■** AMOUNT

1.5 µl Additional info: 400µM right arm

AMOUNT

1.5 μl Additional info: 400μM left adapter

**■** AMOUNT

1.5 μl Additional info: 400μM right adapter

#### invertedClampFISH probe ligation

## Step 4.

Heat reaction components to 95°C for 5 minutes then cool slowly to 12°C.

**▮** TEMPERATURE

95 °C Additional info:

**▮** TEMPERATURE

12 °C Additional info: cool slowly (0.1ºC/sec)

#### invertedClampFISH probe ligation

#### Step 5.

Bring to room temperature then add T7 DNA ligase.

**■** AMOUNT

0.5 μl Additional info: T7 DNA ligase

**▮** TEMPERATURE

25 °C Additional info: Bring to room temperature

#### invertedClampFISH probe ligation

#### Step 6.

Mix reaction then centrifuge. Incubate at room temperature overnight.

#### **■ TEMPERATURE**

25 °C Additional info:

#### NOTES

Benjamin Emert 01 Jun 2018

If any of the oligos contain a dye, incubate in the dark.

#### Column purify invertedClampFISH probes

#### Step 7.

Column purify using NEB Monarch PCR and DNA cleanup kit according to the manufacturer's instructions. Use 1 column per 10µL ligation reactions.

#### Column purify invertedClampFISH probes

#### Step 8.

Add 30 µL nuclease free water to ligation reaction.

#### **■** AMOUNT

30 µl Additional info: nuclease free water

#### NOTES

Benjamin Emert 01 Jun 2018

Can be scaled up or down as long as 7x volume of binding buffer is added before loading column. I like to scale the volume such that 200  $\mu$ L can be loaded on each column.

#### Column purify invertedClampFISH probes

#### Step 9.

Add 350 µL binding buffer

## **■** AMOUNT

350 µl Additional info: binding buffer Column purify invertedClampFISH probes

#### **Step 10.**

Apply to monarch column then spin down for 1 minute.

## Column purify invertedClampFISH probes

#### **Step 11.**

Remove flow-through then apply 200 µL wash buffer to column and spin down.

## **■** AMOUNT

200 µl Additional info: Monarch DNA wash buffer

## Column purify invertedClampFISH probes

#### **Step 12.**

Repeat wash with 200 µL wash buffer and spin down.

**■** AMOUNT

200 µl Additional info: Monarch DNA wash buffer

NOTES

Benjamin Emert 01 Jun 2018

You do not need to remove flow through in between washes.

#### Column purify invertedClampFISH probes

**Step 13.** 

Transfer column to clean centrifuge tube then spin down to remove residual wash buffer.

#### Column purify invertedClampFISH probes

**Step 14.** 

Rotate column 180º then centrifuge again.

NOTES

Benjamin Emert 01 Jun 2018

Probably carry-over superstition from using Qiagen columns.

#### Column purify invertedClampFISH probes

Step 15.

Transfer to clean centrifuge tube for elution. Apply 30uL nuclease-free water to column.

**AMOUNT** 

30 µl Additional info:

NOTES

Benjamin Emert 01 Jun 2018

Can scale up or down volume to adjust final concentration. With 30  $\mu$ L elution, my final concentration tends to be between 50-80ng/ $\mu$ L (using an absorbance constant of 33 on the nanodrop).

#### Column purify invertedClampFISH probes

**Step 16.** 

Incubate at room temperature for 5 minutes.

#### Column purify invertedClampFISH probes

**Step 17.** 

Elute probes.

## Column purify invertedClampFISH probes

## **Step 18.**

Measure concentration by nanodrop.

## NOTES

Benjamin Emert 01 Jun 2018

I set the absorbance constant to 33 for ssDNA.