### Module creation

Solve the following exercises and upload your solutions to Moodle (unless specified otherwise) until the specified due date. Make sure to use the *exact filenames* that are specified for each individual exercise. Unless explicitly stated otherwise, you can assume correct user input and correct arguments. You are allowed to write additional functions, classes, etc. to improve readability and code quality.

## Exercise 1 – Submission: a4\_ex1.py

40 Points

Write a class SimpleNetwork that extends torch.nn.Module and represents a basic neural network that is able to handle batches of 1-dimensional samples. This neural network should only use five fully-connected layers: one input, three hidden, and one output layer, whose numbers of neurons are specified upon creation of the network as a list input. Implement the following two methods:

```
• __init__(
    self,
    input_neurons: int,
    hidden_neurons: list,
    output_neurons: int,
    use_bias: bool,
    activation_function: torch.nn.Module = torch.nn.ReLU()
)
```

- input\_neurons specifies the number of neurons in the fully-connected input layer of the neural network.
- hidden\_neurons specifies the number of neurons in each single fully-connected hidden layer of the neural network. The input is a list, where the first, second and third elements specify the number of neurons in the first, second, and third hidden layers, respectively.
- output\_neurons specifies the number of output neurons of the last fully-connected layer of the neural network.
- use\_bias controls whether bias is applied or not.
- activation\_function specifies which non-linear activation function is used after all nonoutput layers of the network. By default, the network should use the torch.nn.ReLU (module) function.

• forward(self, x: torch.Tensor) -> torch.Tensor

This method is used for forward passes through the neural network. It should work as follows:

- x is a 2D tensor of samples with shape (N, F), where N is the minibatch size and F is the number of features per sample.
- In the function, a full forward pass through all four layers and activations should be performed.
- The function should return the result of the output layer, which should be a 2D tensor of shape (N, output\_neurons).

Example program execution:

```
if __name__ == "__main__":
    torch.random.manual_seed(1234)
    simple_network = SimpleNetwork(40, [10, 20, 30], 5, True)
    input = torch.randn(1, 40, requires_grad = False)
    output = simple_network(input)
    print(output)
```

Example output (might differ due to PyTorch version differences):

```
tensor([[-0.0208, 0.1605, -0.2080, 0.0140, 0.0723]],
grad_fn=<AddmmBackward0>)
```

#### Hints:

- Although we will not train the network in this assignment, all trainable layers need to be registered for training.
- Do not apply an activation function to the output of the network.
- You can assume that only vectors of appropriate shape, i.e., F = input\_neurons, are fed into the network.

# Exercise 2 – Submission: a4\_ex2.py

60 Points

Write a class SimpleCNN that extends torch.nn.Module and represents a simple neural network that utilizes convolutional layers with 2-dimensional kernels. Do not use any fully-connected layers in this network apart from the output layer. Implement the following two methods:

```
• __init__(
    self,
    input_channels: int,
    hidden_channels: list,
    use_batchnormalization: bool,
    num_classes: int,
    kernel_size: list,
    activation_function: torch.nn.Module = torch.nn.ReLU()
)
```

- input\_channels specifies the number of channels (e.g. color-channels) in the input to the neural network.
- hidden\_channels specifies the number of feature channels that are computed by the convolutional layers. The input is a list, where the first, second and third elements specify the number of output features in the first, second, and third hidden layers, respectively.
- use\_batch\_normalization controls whether 2-dimensional batch normalization is used after every convolutional layer.
- num\_classes specifies the number of output neurons of the fully-connected output layer of the neural network.
- kernel\_size specifies the size of kernels in each hidden layer of the neural network. The input is a list, where the first, second and third elements specify the size of the kernel in the first, second, and third hidden layers, respectively.
- activation\_function specifies which non-linear activation function is used after all non-output layers of the network. By default, the network should use the torch.nn.ReLU (module) function.

• forward(self, input\_images: torch.Tensor)

This method is used for forward passes through the neural network. It should work as follows:

- input\_images is a 4D tensor of stacked images with a separate brightness channel. Its shape is (N, C, H, W), where N is the minibatch size, C is the number of channels (e.g., color channels), and H and W are the height and width of the images, respectively. In this exercise 2, both H and W are supposed to be 70 and 100, respectively.
- The function should return the result of the output layer, which should be of shape (N, output\_neurons). In all convolutional layers, the inputs should be padded with zeros to keep their height and width from changing.

Example program execution:

```
if __name__ == "__main__":
    torch.random.manual_seed(1234)
    network = SimpleCNN(3, [32, 64, 128], True, 10, [3, 5, 7], activation_function=nn.ELU())
    input = torch.randn(1, 3, 70, 100, requires_grad = False)
    output = network(input)
    print(output)

Every le output (might differ due to DyTarch version differences)
```

Example output (might differ due to PyTorch version differences):

```
tensor([[ 0.3947, -0.0590, -0.1163, 0.3177, 0.5822, -0.0843, 0.1405, -0.1179, 0.5871, 0.9223]], grad_fn=<AddmmBackward0>)
```

### Hints:

- Although we will not train the network in this assignment, all trainable layers need to be registered for training.
- To convert the output of the convolutional layers to a suitable shape for the fully-connected output layer, you can, e.g, use Tensor.view or Tensor.flatten. Remember that the height and width of the input can be assumed to be 70 and 100, respectively, and these remain the same even after all convolutional layers, since you must use padding. This means that the flattened representation has a size of (hidden\_channels × 70 × 100), where hidden\_channels is the number of channels of the last convolutional layer.
- You should make heavy use of PyTorch's modules and functions, do not implement everything yourself.
- For batch normalization, refer to https://pytorch.org/docs/stable/generated/torch.nn. BatchNorm2d.html.