MIPS Pseudo Instructions and Functions

Philipp Koehn

-16 March 2016-30 Sept 2019 Midderm review on Wednesday (10/2) -> come with questions Midderm on Friday 10/4





pseudo instruction

Assembler



- Assembler convert readable instructions into machine code
 - assembly language: add \$t0, \$s1, \$s2
 - machine code: 00000010 00110010 01000000 00100000

Assembler



- Assembler convert readable instructions into machine code
 - assembly language: add \$t0, \$s1, \$s2
 - machine code: 00000010 00110010 01000000 00100000

• Make life easier with address labels

```
Address Instruction
loop ...
j loop
```

Pseudo Instructions



- Some instructions would be nice to have
- For instance: load 32 bit value into register

li \$s0, 32648278h

• Requires 2 instructions

lui \$s0, 3264h ori \$s0, \$s0, 8278h

- Pseudo instruction
 - available in assembly
 - gets compiled into 2 machine code instructions

Syntactic Sugar



Move

• Compiled into add instruction

Reserved Register



• Example: load word from arbitrary memory address

lw \$s0, 32648278h

• Memory address 32648278h has to be stored in register

Reserved Register



• Example: load word from arbitrary memory address

lw \$s0, 32648278h

• Memory address 32648278h has to be stored in register

• Solution: use reserved register (\$at)

(sat) "assembler temporary

lui \$at, 3264h
ori \$at, \$s0, 8278h
lw \$s0, 0(\$at)

Another Example



• Branch if less than

blt \$t0, \$t1, address

• Compiled into add instruction

slt \$at, \$t0, \$t1
bne \$at, \$zero, address

(slt = set if less than)



code example

Factorial



• Compute $n! = n \times n - 1 \times n - 2 \times ... \times 2 \times 1$

- Iterative loop
 - initialize sum with n
 - loop through n-1, n-2, ..., 1
 - multiple sum with loop variable



• Registers

- \$a0: n (loop variable)

- \$v0: sum



• Registers

- \$a0: n (loop variable)

- \$v0: sum

• Initialize

move \$v0, \$a0

initialize sum with n



```
Registers- $a0: n (loop variable)- $v0: sum
```

• Initialize

```
move $v0, $a0  # initialize sum with n

• Loop setup
    loop:
        addi $a0, $a0, -1  # decrement n
        beq $a0, $zero, exit # = 0? then done
        ...
        j loop
```



• Registers

- \$a0: n (loop variable)

- \$v0: sum

• Initialize

move \$v0, \$a0 # initialize sum with n

• Loop setup

```
loop:
```

```
addi a0, a0,
```

j loop

• Multiplication

mul \$v0, \$v0, \$a0 # sum = sum * n

Code



```
.text
     main:
          li $a0, 5
                                 # compute 5!
          move $v0, $a0
                                 # initialize sum with n
     loop:
          addi $a0, $a0, -1 # decrement n
          beq a0, zero, exit # = 0? then done
          mul $v0, $v0, $a0 # sum = sum * n
          j loop
     exit:
          jr $ra
                                 # done
```



jumps and subroutines

Jump



• MIPS instruction

j address

• Only 26 bits available for address (6 bits of op-code)

Jump



• MIPS instruction

j address

- Only 26 bits available for address (6 bits of op-code)
- \Rightarrow 32 bit address constructed by concatenating
 - upper 4 bits from current program counter
 - 26 bits as specified
 - 2 bits with value "0"

Jump



• MIPS instruction

j address

- Only 26 bits available for address (6 bits of op-code)
- \Rightarrow 32 bit address constructed by concatenating
 - upper 4 bits from current program counter
 - 26 bits as specified
 - 2 bits with value "0"
 - Proper 32 bit addressing available with

jr \$register

Jump and Link: Subroutines



• MIPS instructions

jal address
jalr \$register

- Address handling as before
- Stores return address in register \$ra (31st register)
- Return from subroutine

jr \$ra

Register Conventions



- Arguments to subroutine: registers \$a0, \$a1, \$a2, \$a3 } args on stack
- Return values from subroutine: registers \$v0, \$v1, \$\frac{\$\frac{1}{2}}{2}, \$\frac{1}{2}\frac{1}{2}}
- Conceptually

$$(\$v0, \$v1, \$v2, \$v3) = f(\$a0, \$a1, \$a2, \$a3)$$

Example



• Subroutine to add three numbers

```
main:
    li $a0, 10
    li $a1, 21
    li $a2, 33
    jal add3

add3:
    add $v0, $a0, $a1
    add $v0, $v0, $a2
    jr $ra
```

Another Example



```
• Subroutine for a + b - c
     main:
          li $a0, 10
          li $a1, 21
          li $a2, 33
          jal add-and-sub
      add-and-sub:
          add $a0, $a0, $a1
         move $a1, $a2
                       ) clobbers fra!
         jal my-sub
          jr $ra
     my-sub:
          sub $v0, $a0, $a1
          jr $ra
```

What could go wrong?

Safekeeping



• Recursive calls: must keep return address \$ra in safe place

Safekeeping



- Recursive calls: must keep return address \$ra in safe place
- May also want to preserve other registers
- Temporary registers \$t0-\$t9 may be overwritten by subroutine
- Saved registers \$s0-\$s7 must be preserved by subroutine

Safekeeping



- Recursive calls: must keep return address \$ra in safe place
- May also want to preserve other registers
- Temporary registers \$t0-\$t9 may be overwritten by subroutine
- Saved registers \$s0-\$s7 must be preserved by subroutine
- Note
 - all this is by convention
 - you have to do this yourself



stack

Stack



- Recall: 6502
 - JSR stored return address on stack
 - RTS retrieved return address from stack
 - special instructions to store accumulator, status register

- MIPS: software stack
- By convention: stack pointer register (\$sp)(29th register)
- Why not always use the stack? It's slow

Alternate Idea



• Store return address in saved register \$s0

Alternate Idea



• Store return address in saved register \$s0

• But: now have to preserve \$s0 on stack

Store Return Address on Stack



• Decrease stack pointer

addi \$sp, \$sp, -4

32-bit address has 4 bytes

Store Return Address on Stack



• Decrease stack pointer

32-bit address has 4 bytes

• Store return address

sw = store word

• Stack pointer points to last used address

Retrieve Return Address from Stack



• Load return address

lw = store word

• Increase stack pointer


addi \$sp, \$sp, 4

Multiple Registers



• Store multiple registers

• Load



Frame Pointer



- What if we want to consult values stored on the stack?
- Example
 - subroutine stores return address and some save registers on stack
 - some code does something
 (maybe even store more things on stack)
 - subroutine wants to consult stored return address

Frame Pointer



- What if we want to consult values stored on the stack?
- Example
 - subroutine stores return address and some save registers on stack
 - some code does something
 (maybe even store more things on stack)
 - subroutine wants to consult stored return address
- Stack pointer has changed
 - \rightarrow may be difficult to track down

Frame Pointer



- What if we want to consult values stored on the stack?
- Example
 - subroutine stores return address and some save registers on stack
 - some code does something
 (maybe even store more things on stack)
 - subroutine wants to consult stored return address
- Stack pointer has changed
 - \rightarrow may be difficult to track down
- Solution
 - store entry stack pointer in frame pointer (\$fp)(30th register)
 move \$fp, \$sp



example

Recall: Factorial



```
.text
```

Implemented as a Function



• Subroutine call (function argument in \$a0)

main:

• Return from subroutine (return value is in \$v0)

exit:

jr \$ra # done

Scaffolding



Complete Code



```
.text
```

```
li $a0, 5 والمالية المالية ال
main:
                                                                                                                                                                                                                                                           # call function
                                                                                                                                                                                                                                                            # done
                                             jr $ra
  fact:
                                           move $v0, $a0
                                                                                                                                                                                                                                                            # initialize sum with n
 loop:
                                             addi $a0, $a0, -1 # decrement n
                                            beq a0, zero, exit # = 0? then done
                                           mul $v0, $v0, $a0 # sum = sum * n
                                            j loop
 exit:
                                             jr $ra
                                                                                                                                                                                                                                                             # done
```

Recursive Implementation



• Idea:
$$f(n) = f(n-1) * n$$

 $f(o) = 1 - base const$

- Recursive call needs to preserve
 - return address
 - argument (n)

Termination Condition



• Check if argument is 0

```
fact:
    beq $a0, $zero, final # = 0? then done
    (common case)

final:
    li $v0, 1
    jr $ra # done
```

• Note: no need to preserve registers

Core Recursion



• Recursive call f(n-1)

```
addi $a0, $a0, -1 # decrement n
jal fact # recursive call -> $v0 is f(n-1)
```

• Multiply with argument

```
mul $v0, $v0, $a0 # f(n-1) * n
```

Save and Restore Registers



• Save registers

```
addi $sp, $sp, -8

sw $ra,0($sp)  # return address on stack

sw $a0,4($sp)  # argument on stack
```

• Restore registers

```
lw $ra,0($sp)  # return address from stack
lw $a0,4($sp)  # argument from stack
addi $sp, $sp, 8
```

Complete Code



fact:

```
beq a0, zero, final # = 0? then done
     addi $sp, $sp, -8
     sw $ra,0($sp)
                              # return address on stack
     sw $a0, 4($sp)
                              # argument on stack
     addi $a0, $a0, -1
                              # decrement n
     jal fact
                              # recursive call -> $v0 is f(n-1)
     lw $ra,0($sp)
                              # return address from stack
     lw $a0,4($sp)
                              # argument from stack
     addi $sp, $sp, 8
                              \# f(n-1) * n
    mul $v0, $v0, $a0
     jr $ra
                              # done
final:
     li $v0, 1
     jr $ra
                              # done
```