Transport Layer Protocols

EE4204: Computer Networks
Mehul Motani
motani@nus.edu.sg

Outline

- Principles underlying transport-layer services
  - (De)multiplexing
  - Detecting corruption
  - Reliable delivery
  - Flow control & Congestion control
- Transport-layer protocols in the Internet
  - User Datagram Protocol (UDP)
  - Transmission Control Protocol (TCP)

Note: Some slides & graphics adapted from Kurose & Ross, Computer Networking

Role of Transport Layer

- Application layer
  - Communication for specific applications
  - E.g., HyperText Transfer Protocol (HTTP), File Transfer Protocol (FTP), Network News Transfer Protocol (NNTP)
- Transport layer
  - Communication between processes (e.g., socket)
  - Relies on network layer and serves the application layer
  - E.g., TCP and UDP
- Network layer
  - Logical communication between nodes
  - Hides details of the link technology
  - E.g., IP

Transport Protocols

- Provide *logical communication* between application processes running on different hosts
- Run on end hosts
  - Sender: breaks application messages into segments, and passes to network layer
  - Receiver: reassembles segments into messages, passes to application layer
- Multiple transport protocol available to applications
  - Internet: TCP and UDP



Internet Transport Protocols

- Datagram messaging service (UDP)
  - No-frills extension of "best-effort" IP
- Reliable, in-order delivery (TCP)
  - Connection set-up
  - Discarding of corrupted packets
  - Retransmission of lost packets
  - Flow control
  - Congestion control
- Other services not available
  - Delay guarantees
  - Bandwidth guarantees

Multiplexing and Demultiplexing

- Host receives IP datagrams
  - Each datagram has source and destination IP address,
  - Each datagram carries one transport-layer segment
  - Each segment has source and destination port number
- Host uses IP addresses and port numbers to direct the segment to appropriate socket



TCP/UDP segment format

Unreliable Message Delivery Service

- Lightweight communication between processes
  - Avoid overhead and delays of ordered, reliable delivery
  - Send messages to and receive them from a socket
- User Datagram Protocol (UDP)
  - IP plus port numbers to support (de)multiplexing
  - Optional error checking on the packet contents



Why Would Anyone Use UDP?

- Finer control over what data is sent and when
  - As soon as an application process writes into the socket
  - … UDP will package the data and send the packet
- No delay for connection establishment
  - UDP just blasts away without any formal preliminaries
  - … which avoids introducing any unnecessary delays
- No connection state
  - No allocation of buffers, parameters, sequence #s, etc.
  - … making it easier to handle many active clients at once
- Small packet header overhead
  - UDP header is only eight-bytes long

Popular Applications That Use UDP

- Multimedia streaming
  - Retransmitting lost/corrupted packets is not worthwhile
  - By the time the packet is retransmitted, it's too late
  - E.g., telephone calls, video conferencing, gaming
- Simple query protocols like Domain Name System
  - Overhead of connection establishment is overkill
  - Easier to have application retransmit if needed



Transmission Control Protocol (TCP)

- Connection oriented
  - Explicit set-up and tear-down of TCP session
- Stream-of-bytes service
  - Sends and receives a stream of bytes, not messages
- Reliable, in-order delivery
  - Checksums to detect corrupted data
  - Acknowledgments & retransmissions for reliable delivery
  - Sequence numbers to detect losses and reorder data
- Flow control
  - Prevent overflow of the receiver's buffer space
- Congestion control
  - Adapt to network congestion for the greater good

An Analogy: Talking on a Cell Phone

- Alice and Bob on their cell phones
  - Both Alice and Bob are talking
- What if Alice couldn't understand Bob?
  - Bob asks Alice to repeat what she said
- What if Bob hasn't heard Alice for a while?
  - Is Alice just being quiet?
  - Or, have Bob and Alice lost reception?
  - How long should Bob just keep on talking?
  - Maybe Alice should periodically say "uh huh"
  - … or Bob should ask "Can you hear me now?" ☺

Some Reflections on the Example

- Acknowledgments from receiver
  - Positive: "okay" or "ACK"
  - Negative: "please repeat that" or "NACK"
- Timeout by the sender ("stop and wait")
  - Don't wait indefinitely without receiving some response
  - … whether a positive or a negative acknowledgment
- Retransmission by the sender
  - After receiving a "NACK" from the receiver
  - After receiving no feedback from the receiver

Challenges of Reliable Data Transfer

- Over a perfectly reliable channel
  - All of the data arrives in order, just as it was sent
  - Simple: sender sends data, and receiver receives data
- Over a channel with bit errors
  - All of the data arrives in order, but some bits corrupted
  - Receiver detects errors and says “please repeat that”
  - Sender retransmits the data that were corrupted
- Over a lossy channel with bit errors
  - Some data are missing, and some bits are corrupted
  - Receiver detects errors but cannot always detect loss
  - Sender must wait for acknowledgment (“ACK” or “OK”)
  - … and retransmit data after some time if no ACK arrives

TCP Support for Reliable Delivery

- Checksum
  - Used to detect corrupted data at the receiver
  - …leading the receiver to drop the packet
- Sequence numbers
  - Used to detect missing data
  - ... and for putting the data back in order
- Retransmission
  - Sender retransmits lost or corrupted data
  - Timeout based on estimates of round-trip time
  - Fast retransmit algorithm for rapid retransmission

TCP Segments

TCP "Stream of Bytes" Service

Host A



Host B



…Emulated Using TCP "Segments"



TCP Segment



- IP packet
  - No bigger than Maximum Transmission Unit (MTU)
  - E.g., up to 1500 bytes on an Ethernet
- TCP packet
  - IP packet with a TCP header and data inside
  - TCP header is typically 20 bytes long
- TCP segment
  - No more than Maximum Segment Size (MSS) bytes
  - E.g., up to 1460 consecutive bytes from the stream

Sequence Numbers



Initial Sequence Number (ISN)

- Sequence number for the very first byte
  - E.g., Why not a de facto ISN of 0?
- Practical issue
  - IP addresses and port #s uniquely identify a connection
  - Eventually, though, these port #s do get used again
  - … and there is a chance an old packet is still in flight
  - … and might be associated with the new connection
- So, TCP requires changing the ISN over time
  - Set from a 32-bit clock that ticks every 4 microseconds
  - … which only wraps around once every 4.55 hours!
- But, this means the hosts need to exchange ISNs

TCP Three-Way Handshake

Establishing a TCP Connection



Each host tells its ISN to the other host.

- Three-way handshake to establish connection
  - Host A sends a **SYN** (open) to the host B
  - Host B returns a SYN acknowledgment (**SYN ACK**)
  - Host A sends an **ACK** to acknowledge the SYN ACK

TCP Header



Step 1: A's Initial SYN Packet



A tells B it wants to open a connection…

Step 2: B's SYN-ACK Packet

Flags: SYN
FIN
RST
PSH
URG
ACK

B's port	A's port
B's Initial Sequence Number	
A's ISN plus 1	
20 | 0 | Flags	Advertised window
Checksum	Urgent pointer
Options (variable)	

B tells A it accepts, and is ready to hear the next byte…

… upon receiving this packet, A can start sending data

Step 3: A's ACK of the SYN-ACK

Flags: SYN
FIN
RST
PSH
URG
ACK

A's port	B's port
Sequence number	
B's ISN plus 1	
20 | 0 | Flags	Advertised window
Checksum	Urgent pointer
Options (variable)	

A tells B it wants is okay to start sending

… upon receiving this packet, B can start sending data

What if the SYN Packet Gets Lost?

- Suppose the SYN packet gets lost
  - Packet is lost inside the network, or
  - Server rejects the packet (e.g., listen queue is full)
- Eventually, no SYN-ACK arrives
  - Sender sets a timer and wait for the SYN-ACK
  - … and retransmits the SYN if needed
- How should the TCP sender set the timer?
  - Sender has no idea how far away the receiver is
  - Hard to guess a reasonable length of time to wait
  - Some TCPs use a default of 3 or 6 seconds

SYN Loss and Web Downloads

- User clicks on a hypertext link
  - Browser creates a socket and does a “connect”
  - The “connect” triggers the OS to transmit a SYN
- If the SYN is lost…
  - The 3-6 seconds of delay may be very long
  - The user may get impatient
  - … and click the hyperlink again, or click “reload”
- User triggers an “abort” of the “connect”
  - Browser creates a new socket and does a “connect”
  - Essentially, forces a faster send of a new SYN packet!
  - Sometimes very effective, and the page comes fast

Tearing Down the Connection



- Closing the connection
  - Finish (FIN) to close and receive remaining bytes
  - And other host sends a FIN ACK to acknowledge
  - Reset (RST) to close and not receive remaining bytes

TCP Retransmissions

Automatic Repeat reQuest (ARQ)

- Automatic Repeat Request
  - Receiver sends acknowledgment (ACK) when it receives packet
  - Sender waits for ACK and timeouts if it does not arrive within some time period
- Simplest ARQ protocol
  - Stop and wait
  - Send a packet, stop and wait until ACK arrives



Reasons for Retransmission



Packet lost



ACK lost
DUPLICATE PACKET



Early timeout
DUPLICATE PACKETS

How Long Should Sender Wait?

- Sender sets a timeout to wait for an ACK
  - Too short: wasted retransmissions
  - Too long: excessive delays when packet lost
- TCP sets timeout as a function of the RTT
  - Expect ACK to arrive after an RTT
  - … plus a fudge factor to account for queuing
- But, how does the sender know the RTT?
  - Can estimate the RTT by watching the ACKs
  - Smooth estimate: keep a running average of the RTT
    - EstimatedRTT = a * EstimatedRTT + (1 –a) * SampleRTT
  - Compute timeout: TimeOut = 2 * EstimatedRTT

Example RTT Estimation



A Flaw in This Approach

- An ACK doesn't really acknowledge a transmission
  - Rather, it acknowledges receipt of the data
- Consider a retransmission of a lost packet
  - If you assume the ACK goes with the 1st transmission
  - … the SampleRTT comes out way too large
- Consider a duplicate packet
  - If you assume the ACK goes with the 2nd transmission
  - … the Sample RTT comes out way too small
- Simple solution in the Karn/Partridge algorithm
  - Only collect samples for segments sent one single time

Yet Another Limitation…

- Doesn't consider variance in the RTT
  - If variance is small, the EstimatedRTT is pretty accurate
  - … but, if variance is large, the estimate isn't all that good
- Better to directly consider the variance
  - Consider difference: SampleRTT – EstimatedRTT
  - Boost the estimate based on the difference
- Jacobson/Karels algorithm
  - See Section 5.2 of the Peterson/Davie book for details

TCP Sliding Window

Motivation for Sliding Window

- Stop-and-wait is inefficient
  - Only one TCP segment is "in flight" at a time
  - Especially bad when delay-bandwidth product is high
- Numerical example
  - 1.5 Mbps link with a 45 msec round-trip time (RTT)
    - Delay-bandwidth product is 67.5 Kbits (or 8 KBytes)
  - But, sender can send at most one packet per RTT
    - Assuming a segment size of 1 KB (8 Kbits)
    - … leads to 8 Kbits/segment / 45 msec/segment ➔ 182 Kbps
    - That's just one-eighth of the 1.5 Mbps link capacity

Sliding Window

- Allow a larger amount of data "in flight"
  - Allow sender to get ahead of the receiver
  - … though not *too far* ahead



Receiver Buffering

- Window size
  - Amount that can be sent without acknowledgment
  - Receiver needs to be able to store this amount of data
- Receiver advertises the window to the receiver
  - Tells the receiver the amount of free space left
  - … and the sender agrees not to exceed this amount



TCP Header for Receiver Buffering

Flags: SYN
FIN
RST
PSH
URG
ACK

Source port			Destination port
Sequence number			
Acknowledgment			
HdrLen	0	Flags	**Advertised window**
Checksum			Urgent pointer
Options (variable)			
Data			

Fast Retransmission

Timeout is Inefficient

- Timeout-based retransmission
  - Sender transmits a packet and waits until timer expires
  - … and then retransmits from the lost packet onward



Fast Retransmission

- Better solution possible under sliding window
  - Although packet n might have been lost
  - … packets n+1, n+2, and so on might get through
- Idea: have the receiver send ACK packets
  - ACK says that receiver is still awaiting n^{th} packet
    - And *repeated* ACKs suggest later packets have arrived
  - Sender can view the "duplicate ACKs" as an early hint
    - … that the n^{th} packet must have been lost
    - … and perform the retransmission early
- Fast retransmission
  - Sender retransmits data after the triple duplicate ACK

Effectiveness of Fast Retransmit

- When does Fast Retransmit work best?
  - Long data transfers
    - High likelihood of many packets in flight
  - High window size
    - High likelihood of many packets in flight
  - Low burstiness in packet losses
    - Higher likelihood that later packets arrive successfully
- Implications for Web traffic
  - Most Web transfers are short (e.g., 10 packets)
    - Short HTML files or small images
  - So, often there aren't many packets in flight
  - … making fast retransmit less likely to "kick in"
  - Forcing users to like "reload" more often…

TCP Congestion Control

TCP Congestion Control

- Flow control addresses congestion at receiver, not in middle of network (for example, at intermediate routers)
- Suppose you initially send up to the size of flow control window (FW)
  - Intermediate routers may not be able to handle so much traffic
  - Congestion overflows router buffers causing lost packets causing retransmissions causing more congestion … → congestion collapse
- Idea behind TCP Congestion Control:
  - Send only enough packets into the network that the network has the capacity to handle without loss
- Define a congestion window (CW) that can be used to respond to network congestion
  - Distinct from flow control window FW
  - Actual window size W = min (CW, FW)
    - # of data bytes that can be on the link
    - Send no more data than the bottleneck can handle

TCP Congestion Control

- How does sender set CW?
  - Adaptively probe the network with data segments
  - Keep expanding CW until a segment is lost, then contract CW.
  - Continue with expand/contract cycle throughout connection – "sawtooth" behavior'
- Additive Increase / Multiplicative Decrease (AIMD)
  - Increment CW by one packet per RTT (*linear increase*)
  - Divide CW by two whenever a timeout occurs (*multiplicative decrease*)



TCP Slow Start

- The rate at which new packets should be injected into network is the rate at which ACKs are returned by other end
  - Use ACK's to pace transmission of packets: "self-clocking"
  - Start by setting CW = 1 segment (in bytes)
    - Initial segment size set by receiver
  - For each ACK that returns, increment CW by one.
    - Send 1 packet. When ACK returns, increment CW, CW=2
    - Send 2 packets. When 1st ACK returns, increment CW to CW=3, when 2nd ACK returns, increment CW to CW=4
    - Can send 4 packets. After 4 ACKs return, CW will be up to 8
  - Exponential increase – not "slow", quickly reach window size that the network can accommodate

TCP Slow Start



TCP Additive Increase/ Multiplicative Decrease

- How does a sender detect that CW is too large?
  - It starts to see timeouts, which are interpreted as packet loss due to congestion
- After a timeout:
  - TCP drastically resets CW=1 and slow starts again
  - TCP remembers that congestion occurred near CW by storing CW/2 in *ssthresh* = CW/2
    - ssthresh = Slow Start Threshold
  - But TCP exponentially increases only to ssthresh, halfway to old congestion mark
    - After CW>ssthresh, *additively increase* CW
    - Rationale: Be cautious about sending new data packets once you get near old mark that caused timeouts/congestion

TCP Additive Increase

- If entire window's worth (CW) of packets in a RTT is ACKed w/o error, then increment CW by one
- In practice, TCP adds α/CW to CW as each ACK returns, rather than waiting for a full CW of ACKs to return



Rationale behind AIMD

- Why not just slow start exclusively (exponential increase) after timeout, instead of additive increase?
  - Be more cautious about adding new packets once you're near old congestion point.
- Each time a timeout occurs, divide CW by half and store in ssthresh: multiplicative decrease
  - Minimum ssthresh and minimum CW is one
- Why not additive decrease instead of multiplicative decrease after congestion?
  - Consequences of having a too-large congestion window are worse than having a too-small CW
  - Additive decrease can keep CW too large for too long compared to multiplicative decrease

More on TCP AIMD

- What happens if the amount of unacknowledged data is greater than CW?
  - Can't send new data
  - Retransmit unacknowledged data
  - Wait for ACKs for unacknowledged data to increase CW above size of unacknowledged data, then can send new data
- After a timeout, TCP slows down in two ways:
  - Congestion window collapses, restricting new data
  - RTO backs off exponentially, slowing down retransmission of old unacknowledged data

TCP Saw Tooth Behavior (TCP Reno)



Diagram courtesy of Srini Seshan

Variants of TCP

- TCP Reno & TCP Tahoe
  - Both handle Timeouts in the same way
  - TCP Tahoe handles Triple duplicate acks in the same way a Timeout
  - TCP Reno handles Triple duplicate acks differently (by cutting CW by half)

Visualizing behavior of competing TCP connections over time



Visualizing TCP's AIMD



Q: Is Additive Increase / Multiplicative Decrease fair?

Q: What if we had used MIMD? Or AIAD?

Congestion Avoidance

- Congestion control:
  - Cycle of actively probing, transmitting more than the network can handle, then backing off
- Congestion avoidance:
  - Back off before there are packet losses
  - How can you tell that congestion is increasing?
    - Look at RTT – is it expanding?
    - Implicit: Random Early Dropping (RED) of packets by intermediate routers
    - Explicit: Intermediate routers indicate that there is congestion by setting a bit in the packet and receiver send that information back in the ACK (DECbit)

Summary of TCP

Transport Layer Services

- Connection-oriented communication
- Multiplexing
- Byte orientation
- In-order delivery
- Reliability: Error Detection & Re-transmissions
- Flow control
- Congestion control and congestion avoidance

TCP Socket



TCP Header



TCP Finite State Machine Diagram



Conclusion

- Transport protocols
  - Multiplexing and demultiplexing
  - Sequence numbers
  - Window-based flow control
  - Timer-based retransmission
  - Checksum-based error detection
  - Congestion control
- TCP – provides end-to-end reliability
  - TCP also encompasses congestion control
  - AIMD: Additive Increase Multiplicative Decrease
- References for transport layer protocols
  - Chapter 6/7 of Peterson & Davie
  - Chapter 3 of Kurose & Ross