

# TTS 11.0 COOKBOOK

(NSD RDBMS2 DAY01)

版本编号 11.0

2019-06 达内 IT 培训集团



# **NSD RDBMS2 DAY01**

# 1. 案例 1: MySQL 一主一从

#### 问题

- 数据库服务器 192.168.4.51 配置为主数据库服务器
- 数据库服务器 192.168.4.52 配置为从数据库服务器
- 客户端 192.168.4.50 测试配置

## 方案

使用 2 台虚拟机,如图-1 所示。其中 192.168.4.51 是主服务器,另一台 192.168.4.52 作为从服务器,通过调取主服务器上的 binlog 日志,在本地重做对应的库、表,实现与主服务器的数据同步。



图 - 1

主机 51 和主机 52 分别运行 MySQL 数据库服务,且管理员 root 用户可以本机登录; 主机 50 作为客户机 只需有命令行连接命令 mysql 即可。

# ・・・歩骤

实现此案例需要按照如下步骤进行。

步骤一: 配置主服务器 192.168.4.51

1) 启用 binlog 日志

```
]# vim /etc/my.cnf
[mysqld]
server_id=51 //server_id
log-bin=master51 //日志名
:wq
]# systemctl restart mysqld
```



# 2) 用户授权

用户名自定义、客户端地址使用%或 只指定 从服务器的地址 都可以、只给复制数据的权限即可。

```
]# mysql -uroot -p 密碼
mysql> grant replication slave on *.* to repluser@"%" identified by "123qqq...A";
mysql>quit;
```

3) 查看 binlog 日志信息

查看日志文件名 和 偏移量位置。

#### 步骤二:配置从服务器 192.168.4.52

1) 指定 server id

Server\_id 值可以自定义,但不可以与主服务器相同。

```
]# vim /etc/my.cnf

[mysqld]

server_id=52 //server_id值

:wq

]# systemctl restart mysqld //重启服务
```

2) 确保与主服务器数据一致(如果是使用 2 台新部署的数据库服务器配置主从同步, 此操作可以忽略)

```
|# mysqldump -uroot -p 密码 --master-data 数据库名 > /allbak.sql //在主服务器上备份数据
|# scp /allbak.sql root@192.168.4.52:/root/ //将备份文件拷贝给从服务器

mysql> create database 数据库名 ; //在从服务器上创建与主服务器同名的数据库
|# mysql -uroot -p 密码 数据库名 < /root/allbak.sql //从服务器使用备份文件恢复数据
|# vim /root/allbak.sql //在从服务器查看备份文件中的 binlog 日志信息
......

CHANGE MASTER TO MASTER_LOG_FILE='master51.0000001', MASTER_LOG_POS=441; //日志名与偏移量
```

3) 指定主服务器信息

数据库管理员 root 本机登录, 指定主服务器信息, 其中日志文件名和偏移量 写



#### allbak.sql 文件记录的。

```
]# mysql -uroot -p 密码 //管理员 root 本机登录
mysql> show slave status; //查看状态信息, 还不是从服务器
Empty set (0.00 sec)
mysql> change master to //指定主服务器
   -> master host= "192.168.4.51" ,
   -> master_user= "repluser" ,
   -> master_password= "123qqq...A" ,
   -> master_log_file= "master51-bin.000001" ,//主服务器日志文件
   -> master_log_pos=441;
mysql> show slave status\G; //查看状态信息
Slave_IO_State: Waiting for master to send event
               Master Host: 192.168.4.51 //主服务器 ip 地址
               Master_User: repluser
               Master_Port: 3306
             Connect_Retry: 60
           Master_Log_File: master51.000001
        Read_Master_Log_Pos: 437
            Relay_Log_File: host52relay-bin.000002
             Relay_Log_Pos: 604
      Relay_Master_Log_File: master51.000001
          Slave_IO_Running: Yes
                                 //I0 线程 yes 状态
          Slave SQL Running: Yes
           Replicate_Do_DB:
        Replicate_Ignore_DB:
         Replicate Do Table:
     Replicate_Ignore_Table:
     Replicate_Wild_Do_Table:
 Replicate_Wild_Ignore_Table:
                Last_Errno: 0
                Last_Error:
              Skip_Counter: 0
        Exec_Master_Log_Pos: 437
           Relay Log Space: 812
           Until_Condition: None
            Until_Log_File:
            Until_Log_Pos: 0
         Master_SSL_Allowed: No
         Master_SSL_CA_File:
         Master_SSL_CA_Path:
           Master_SSL_Cert:
          Master SSL Cipher:
            Master_SSL_Key:
      Seconds_Behind_Master: 0
Master_SSL_Verify_Server_Cert: No
             Last_IO_Errno: 0
             Last_IO_Error:
            Last_SQL_Errno: 0
            Last_SQL_Error:
 Replicate_Ignore_Server_Ids:
          Master_Server_Id: 50
               Master UUID: 4881ee4b-8800-11e9-830a-525400001e32
          Master_Info_File: /var/lib/mysql/master.info
```



```
SQL Delay: 0
         SQL_Remaining_Delay: NULL
     Slave_SQL_Running_State: Slave has read all relay log; waiting for more updates
          Master_Retry_Count: 86400
                Master_Bind:
     Last_IO_Error_Timestamp:
    Last_SQL_Error_Timestamp:
             Master_SSL_Crl:
          Master SSL Crlpath:
          Retrieved Gtid Set:
           Executed Gtid Set:
              Auto Position: 0
        Replicate Rewrite DB:
               Channel Name:
          Master_TLS_Version:
1 row in set (0.00 sec)
```

# 步骤三: 客户端测试配置

 在主服务器添加访问数据的连接用户 授权用户对所有数据有增删改查的权限即可

```
]# mysql -uroot -p 密码
mysql> grant select,insert,update,delete on *.* to admin@"%" identified by
"123qqq...A";
Query OK, 0 rows affected, 1 warning (0.03 sec)
mysql> quit
```

2) 客户端连接主服务器访问数据在 50 主机 使用主服务器 51 的授权用户连接

```
]# mysql -h192.168.4.51-uadmin -p123qqq...A
mysql> show grants;
Grants for admin@%
GRANT SELECT, INSERT, UPDATE, DELETE ON *.* TO 'admin'@'%' |
1 row in set (0.00 sec)
mysql> insert into db3.user(name,uid) values("lili",288); //db3 库和 user 表是主从同
Query OK, 1 row affected (0.05 sec)
mysql> insert into db3.user(name,uid) values("lili",288);
Query OK, 1 row affected (0.28 sec)
mysql> insert into db3.user(name,uid) values("lili",288);
Query OK, 1 row affected (0.05 sec)
mysql> select name,uid from db3.user where name="lili";
| name | uid |
 lili | 288
 lili | 288
| lili | 288 |
3 rows in set (0.00 sec)
```



#### 3) 客户端连接从服务器访问数据

客户端 50 主机使用授权用户连接从服务器可以看到和主服务器同样的数据

```
]# mysql -h192.168.4.52 -uadmin -p123qqq...A
mysql> select name,uid from db3.user where name="lili";
+----+
| name | uid |
+----+
| lili | 288 |
| lili | 288 |
| lili | 288 |
+----+
3 rows in set (0.00 sec)
```

# 2. 案例 2: 配置一主多从结构

#### 问题

- 配置 192.168.4.53 数据库服务器为主机 192.168.4.51 的从服务器
- 客户端测试配置。

## 方案

创建 1 台新虚拟机,配置 ip 地址为 192.168.4.53、运行数据库服务,且数据库管理员 root 用户可以本机登录。具体结构,如图-1 所示。




图 - 1

#### • 步骤

实现此案例需要按照如下步骤进行。



#### 步骤一: 配置从服务器 192.168.4.53

1) 启用 binlog 日志

```
]# vim /etc/my.cnf
[mysqld]
  server_id=53 //server_id
:wq
]# systemctl restart mysqld
```

2) 确保与主服务器数据一致

在主服务器 51 备份所有数据 并把备份文件拷贝给 53 服务器。

```
]# mysqldump -uroot -p123qqq...A --master-data -B db4 db3 > /root/twodb.sql
]# scp /root/twodb.sql root@192.168.4.53:/root/
```

在 53 主机使用备份文件恢复数据,并查看备份文件记录的日志名和偏移量

```
]# mysql -uroot -p123qqq..A < /root/twodb.sql
]# grep mater51 /root/twodb.sql
CHANGE MASTER TO MASTER_LOG_FILE='master51.000001', MASTER_LOG_POS=1098; //日志名
与偏移量
```

3) 指定主服务器信息

填写备份文件里显示的日志文件名 和 偏移量位置。

```
mysql> change master to //指定主服务器
-> master_host= "192.168.4.51" , //主服务器 ip 地址
-> master_user= "repluser" , //主服务器授权用户
-> master_password= "123qqq...A" , //主服务器授权用户密码
-> master_log_file= "master51-bin.000001" ,//主服务器日志文件
-> master_log_pos=1098; //主服务器日志偏移量
mysql> start slave;
```

#### 查看状态信息

```
|# mysql -uroot -p123qqq...A -e "show slave status\G" | grep -i yes
Slave_IO_Running: Yes //IO 线程 yes 状态
Slave_SQL_Running: Yes //SQL 线程 yes 状态
|# mysql -uroot -p123qqq...A -e "show slave status\G" | grep -i 192
Master_Host: 192.168.4.51 //主服务器 ip 地址
```

#### 步骤二: 客户端测试 (192.168.4.50)

1) 连接主服务器插入新记录

```
]# mysql -h192.168.4.51-uadmin -p123qqq...A
mysql> insert into db3.user(name,uid) values("lucy",888); //db3 库和 user 表是主从同步之前主服务器已有的。
Query OK, 1 row affected (0.05 sec)
```

2) 在从服务器本机 53 可以查询到新插入的数据



```
]# mysql -uroot -p123qqq..A
mysql> select name,uid from db3.user;
+----+
| name | uid |
+----+
| lili | 288 |
| lucy | 888 |
+----+
2 rows in set (0.00 sec)
```

# 3. 案例 3: 配置主从从结构

# 问题

- 配置主机 192.168.4.53 为主服务器
- 配置主机 192.168.4.54 为 53 主机的从服务器
- 配置主机 192.168.4.55 为 54 主机的从服务器
- 客户端测试配置。

# 方案

使用 3 台虚拟机,分别运行 mysql 数据库服务, 且管理员 root 可以本机登录; 主机 192.168.4.53 为主服务器; 主机 192.168.4.54 为从服务器; 主机 192.168.4.55 为从服务器。如图-2 所示。




图 - 2

#### 步骤

实现此案例需要按照如下步骤进行。



#### 步骤一: 环境准备

为了在启用 binlog 日志及同步之前保持主、从库的一致性,主从同步未配置之前,要保证从库上要有主库上的数据,禁用 selinux,关闭防火墙服务,保证物理连接正常

1) 关闭防火墙,禁用 selinux,已关可忽略:

```
]# systemctl stop firewalld
]# setenforce 0
```

#### 步骤二:配置主服务器 192.168.4.53

1) 用户授权

```
]# mysql -uroot -p123456
  mysql> grant replication slave on *.* to yaya@"%" identified by
"123qqq...A";
  Query OK, 0 rows affected, 1 warning (0.03 sec)
```

2) 启用 binlog 日志,修改/etc/my.cnf 配置,重新启动 MySQL 服务程序 指定服务器 ID 号、允许日志同步:

```
]# vim /etc/my.cnf
[mysqld]
log_bin=db53 //启用 binlog 日志,并指定文件名前缀
server_id=53 //指定服务器 ID 号
```

#### 重启 mysql 服务:

```
]# systemctl restart mysqld
```

确保/var/lib/mysql下面有两个文件:

```
]# ls /var/lib/mysql/db51.*
/var/lib/mysql/db53.000001 /var/lib/mysql/db53.index
```

#### 查看主服务正在使用的日志信息

查看主服务器状态,记录下当前的日志文件名、偏移的位置(下面 SLAVE 发起复制时需要用到):

#### 步骤三: 配置从服务器 192.168.4.54

1) 在服务器 192.168.4.53 上做用户授权(数据同步使用的连接用户

```
]# mysql -u root -p123456
mysql> grant replication slave on *.* to user55@"%" identified by "654321";
```

2) 修改/etc/my.cnf 配置, 启用 binlog 日志, 指定 server\_id 和 允许级联复制

```
]# vim /etc/my.cnf
```



[mysqld]
server\_id=54
log-bin=db54
log\_slave\_updates

//允许级联复制

3) 配置完成后, 重启 mysql 服务:

]# systemctl restart mysqld

4) 确保/var/lib/mysal 下面有两个文件:

```
]# ls /var/lib/mysql/db52.*
/var/lib/mysql/db54.000001 /var/lib/mysql/db54.index
```

5) 查看正在使用的日志信息

6) 验证主服务器的的授权用户

```
|# mysql -h192.168.4.53 -uyaya -p123456
mysql: [Warning] Using a password on the command line interface can be insecure.
Welcome to the MySQL monitor. Commands end with; or \g.
Your MySQL connection id is 4
Server version: 5.7.17-log MySQL Community Server (GPL)

Copyright (c) 2000, 2016, Oracle and/or its affiliates. All rights reserved.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

Type 'help;' or '\h' for help. Type '\c' to clear the current input statement.

mysql>

//验证成功
```

7) 通过 change master 语句指定 master 服务器的 IP 地址、同步用户名/密码、起始日志文件、偏移位置(参考 master 上的状态输出):

```
]# mysql -uroot -p123456
mysql> change master to
    -> master_host="192.168.4.53";
    -> master_user="yaya",
    -> master_password="123456",
    -> master_log_file="db53.000001";
    -> master_log_pos=437;
Query OK, 0 rows affected, 2 warnings (0.43 sec)
```

8) 启动 slave 进程

```
mysql> start slave;
Query OK, 0 rows affected (0.03 sec)
```



9) 查看进程状态信息,通过 show slave status 语句可查看从服务器状态,确认其中的 IO 线程、SQL 线程正常运行,才能成功同步,IO 线程和 SQL 线程必须是 Yes

```
mysql> show slave status \G;
                   ****** 1. row *****************
             Slave IO State: Waiting for master to send event
                Master_Host: 192.168.4.53 //主服务器 IP 地址
                Master_User: yaya
                Master_Port: 3306
              Connect_Retry: 60
            Master_Log_File: db53.000001
         Read_Master_Log_Pos: 437
             Relay_Log_File: db54-relay-bin.000001
              Relay_Log_Pos: 315
       Relay_Master_Log_File: db54.000001
           Slave_IO_Running: Yes //IO 线程状态 YES
           Slave SQL Running: Yes //SQL 线程状态 YES
            Replicate Do DB:
         Replicate Ignore DB:
          Replicate_Do_Table:
      Replicate_Ignore_Table:
     Replicate_Wild_Do_Table:
 Replicate_Wild_Ignore_Table:
                 Last Errno: 0
                 Last Error:
               Skip_Counter: 0
         Exec Master Log Pos: 437
             Relay Log Space: 521
            Until_Condition: None
             Until_Log_File:
              Until_Log_Pos: 0
          Master_SSL_Allowed: No
          Master_SSL_CA_File:
          Master_SSL_CA_Path:
            Master_SSL_Cert:
           Master SSL Cipher:
             Master_SSL_Key:
       Seconds_Behind_Master: 0
Master_SSL_Verify_Server_Cert: No
              Last_IO_Errno: 0
              Last_IO_Error:
             Last_SQL_Errno: 0
             Last_SQL_Error:
 Replicate Ignore Server Ids:
           Master_Server_Id: 51
                Master_UUID: 81a13101-aa66-11e8-ad11-525400019e62
           Master_Info_File: /var/lib/mysql/master.info
                  SQL_Delay: 0
         SQL_Remaining_Delay: NULL
     Slave_SQL_Running_State: Slave has read all relay log; waiting for more updates
          Master_Retry_Count: 86400
                Master Bind:
     Last_IO_Error_Timestamp:
    Last_SQL_Error_Timestamp:
             Master_SSL_Crl:
          Master_SSL_Crlpath:
          Retrieved Gtid Set:
           Executed Gtid Set:
              Auto_Position: 0
        Replicate_Rewrite_DB:
               Channel_Name:
          Master_TLS_Version:
1 row in set (0.00 sec)
```



#### 步骤四: 配置从服务器 192.168.4.55

1) 验证主库的授权用户

```
|# mysql -h192.168.4.54 -uuser54 -p654321
mysql: [Warning] Using a password on the command line interface can be insecure.
Welcome to the MySQL monitor. Commands end with; or \g.
Your MySQL connection id is 7
Server version: 5.7.17-log MySQL Community Server (GPL)

Copyright (c) 2000, 2016, Oracle and/or its affiliates. All rights reserved.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

Type 'help;' or '\h' for help. Type '\c' to clear the current input statement.

mysql>

//验证成功
```

2) 指定 server\_id

```
[mysqld]
server_id=55
```

3) 重新启动服务

]# systemctl restart mysqld

4) 管理员登录指定主库信息

```
]# mysql -uroot -p123456
mysql> change master to
    -> master_host="192.168.4.54";
    -> master_user="user55";
    -> master_password="654321",
    -> master_log_file=" db54.000001";
    -> master_log_pos=154;
Query OK, 0 rows affected, 2 warnings (0.37 sec)
```

5) 启动 slave 进程

```
mysql> start slave;
Query OK, 0 rows affected (0.04 sec)
```

6) 查看进程状态信息

步骤五: 客户端验证配置



在主库授权访问数据的连接用户;户端连接主库执行与权限匹配的 sql 操作; 授权用户连接第1台从库,可以看到主库的数据;权用户连接第2台从库,可以看到主库的数据

1) 在主服务器上在主库上授权访问 gamedb 库的用户

```
]# mysql -uroot -p123456
mysql> grant all on gamedb.* to dada@"%" identified by "123456";
Query OK, 0 rows affected, 1 warning (0.03 sec)
```

2) 客户端使用授权用户连接主库, 建库、表、插入记录

```
|# mysql -h192.168.4.53 -udada -p123456
Welcome to the MariaDB monitor. Commands end with; or \g.
Your MySQL connection id is 7
Server version: 5.7.17-log MySQL Community Server (GPL)

Copyright (c) 2000, 2017, Oracle, MariaDB Corporation Ab and others.

Type 'help;' or '\h' for help. Type '\c' to clear the current input statement.

MySQL [(none)]> //验证成功

MySQL [(none)]> create database gamedb; //创建测试库
Query OK, 1 row affected (0.04 sec)

MySQL [(none)]> create table gamedb.t1(id int); //在gamedb下创建t1表
Query OK, 0 rows affected (0.17 sec)

MySQL [(none)]> insert into gamedb.t1 values(8888); //在t1表中插入数值
Query OK, 1 row affected (0.22 sec)
```

3) 客户端使用授权用户连接 2 台从库时,也可以看到主库上新的库表记录

```
]# mysql -h192.168.4.54
                         -udada -p123456 //验证 54 主机的状态
Welcome to the MariaDB monitor. Commands end with ; or \g.
Your MySQL connection id is 10
Server version: 5.7.17-log MySQL Community Server (GPL)
Copyright (c) 2000, 2017, Oracle, MariaDB Corporation Ab and others.
Type 'help;' or '\h' for help. Type '\c' to clear the current input statement.
MySQL [(none)]> select * from gamedb.t1; //查询插入的表格
| id |
l 8888 l
1 row in set (0.00 sec)
MySQL [(none)]> exit
[root@room9pc01 ~]# mysql -h192.168.4.55 -udada -p123456 //验证 55 主机的状态
Welcome to the MariaDB monitor. Commands end with ; or \gray{g}.
Your MySOL connection id is 6
Server version: 5.7.17 MySQL Community Server (GPL)
Copyright (c) 2000, 2017, Oracle, MariaDB Corporation Ab and others.
Type 'help;' or '\h' for help. Type '\c' to clear the current input statement.
MySQL [(none)]> select * from gamedb.t1;
| id
```



```
| 8888 |
+----+
1 row in set (0.00 sec)
```

# 4. 配置半同步复制模式

#### 问题

- 开启案例 2 从服务器 192.168.4.54 半同步复制模式
- 查看半同步复制模式是否开启

#### 方案

以案例 2 从服务器 192.168.4.54 为例演示配置,54 主机既做主服务器又做从服务器,所以两种角色的半同步复制模块和功能都要启用。

# • 步骤

实现此案例需要按照如下步骤进行。

#### 步骤一: 查看是否允许动态加载模块,

1) 查看是否允许动态加载模块(默认允许)

#### 2) 命令行加载插件

```
mysql>install plugin rpl_semi_sync_master SONAME "semisync_master.so";//加载 master 模块
mysql> install plugin rpl_semi_sync_slave SONAME 'semisync_slave.so'; //加载 slave 模块
```

#### 查看模块是否安装成功:



#### 3) 启用半同步复制 (在安装完插件后,半同步复制默认是关闭的)

```
mysql> set global rpl_semi_sync_master_enabled = 1; //启用 master 半同步复制
Query OK, 0 rows affected (0.00 sec)
mysql> set global rpl_semi_sync_slave_enabled = 1; //启用 slave 半同步复制
Query OK, 0 rows affected (0.00 sec)
```

#### 查看半同步复制模式是否启用:

#### 4) 修改配置文件,永久启用半同步复制

```
[root@master51 ~]# vim /etc/my.cnf
[mysqld]
plugin-load="rpl_semi_sync_master=semisync_master.so;rpl_semi_sync_slave=semisyn
c_slave.so"
    rpl-semi-sync-master-enabled = 1
    rpl-semi-sync-slave-enabled = 1
    : wq
```

# 5) 重启数据库服务,并查看状态信息