# Simulation Workflow - Build system, meshes and visualization

Dominic Kempf

August 31, 2021

#### Goals of this lecture

At the end of this lecture/exercise session you should

- understand the modular structure of Dune.
- have realized that build systems are your friend!
- ▶ have an overview of available grid implementations in Dune
- ▶ have seen several concepts to construct grids
- be able to visualize PDE solutions in ParaView

Dune is distributed as a zoo of projects. They fall into the following categories:

- core modules: Basic infrastructure and data types, Grid interface, geometries, basis functions and linear algebra
- discretization modules: dune-pdelab, dune-fem, dune-fufem,
- ► Grid modules: Additional grid managers
- Extension modules: Mixed bag of additional functionalities
- User modules

#### Each module...

- ▶ is a git repository in itself
- ▶ has a file dune.module, which describes its dependencies
- uses the build system from dune-common

New modules are created with a shell script duneproject

# What is CMake anyway?

#### CMake...

- ... is an open source buildsystem tool developed at KITware.
- ... offers a one-tool-solution to all building tasks, like configuring, building, linking, testing and packaging.
- ... is a build system generator: It supports a set of backends called "generators"
- ... is portable
- ... is controlled by ONE rather simple language

We typically use the Unix Makefiles generator that generates Makefiles.

#### Where is the build system defined?

Each (sub)directory of the project contains a file CMakeLists.txt. This file

- is written in the CMake language
- is run during configure
- recursively runs CMakeLists.txt files from subdirectories.


# Some CMake commands everybody should know

- add\_subdirectory lets the configure script recurse into a subdirectory. A CMakeLists.txt file is expected in that directory.
- add\_executable adds build rules for a new executable.
- dune\_add\_test adds a test to the testing suite
- dune\_symlink\_to\_source\_files creates links from the source directory into the build directory

## An example CMakeLists.txt file

For a reference of end-user CMake commands, see the build system documentation on the Dune website (**DEMOTIME!**).

#### Simulation workflow



#### Reading configuration through ini files

```
outputfilename = myfile.vtu
[grid]
lowerleft = -1. -1.
upperright = 1. 1.
```

#### Dune style ini files support:

- Key/value pairs separated with a =
- Grouping of keys into sections to arbitrary depth

```
#include < dune / common / parameter tree . hh >
#include < dune / common / parameter tree parser . hh >
```


```
Dune::ParameterTree tree;
Dune::ParameterTreeParser::readINITree(filename, tree)
```

#### Selecting a grid manager

Dune offers a large variety of grid managers, which differ vastly in their feature set and their natural strengths. Here are some capabilities of grid implementations:

- structured vs. unstructured
- simplical vs. quadrilateral vs. multi-geometry
- conforming vs. non-conforming
- parallel vs. sequential
- adaptive vs. non-adaptive (also: different refinement algorithms)
- ▶ different world dimensions (1, 2, 3, n)
- Surface/manifold grids

Dune allows for implementations of all sorts of grids through one common interface!



# A selection of available Implementations of the Dune grid interface:

- YaspGrid (in dune-grid, structured, parallel, n-dimensional, tensorproduct grid)
- ▶ OneDGrid (in dune-grid, adaptive, parallel, 1D)
- ► GeometryGrid (in dune-grid, meta-grid, applies discrete mesh transformation)
- ▶ dune-uggrid (2D/3D, unstructured, parallel, multi-geometry)
- ▶ dune-alugrid (2D/3D, unstructured, parallel, simplex/cube)
- dune-multidomaingrid (meta-grid, partition grid into sub-domains)
- dune-subgrid (meta-grid, part of the grid hierarchy as grid in itself)
- opm-grid (3D, corner-point geometries)
- dune-foamgrid (1D/2D in 3D manifold grid)
- dune-prismgrid (meta-grid, extrudes surface mesh)
- dune-polygongrid (polygonal geometries)
- ...


#### **StructuredGridFactory**

There is a utility class, the StructuredGridFactory, which makes it easy to create structured grids (also for unstructured grid managers). It provides two static functions:

- createCubeGrid creates a grid with cubes with given domain size and number of elements in each direction.
- createSimplexGrid creates a grid with simplices which are generated by subdividing the cubes.

These return a unique\_ptr to a grid object.

# **Structured grids**



#### **GmshReader**


In DUNE there is a mesh reader interface, which can read meshes generated with Gmsh (available at http://www.geuz.org/gmsh/).

- Can only be used with grid managers that support unstructured grids (however, gmsh can generate structured grids, which are stored in an unstructured format)
- Supports simplex grids in 2D and 3D
- Gmsh can use geometries from CAD programs
- Gmsh supports a quadratic boundary approximation, which is translated into boundary segments by the reader.

#### An easy GmshReader Example

```
#include<dune/grid/uggrid.hh>
#include<dune/grid/io/file/gmshreader.hh>

typedef Dune::UGGrid<2> GridType;
auto grid = Dune::GmshReader<GridType>::read(mshfile);
```



#### Attaching data to the grid in gmsh

GMSH allows you to define physical entities for cells and boundary segments. The GmshReader can read those when parsing the msh file and store them in a std::vector<int>. The user takes responsibility of those data structures.

```
#include<dune/grid/uggrid.hh>
#include<dune/grid/io/file/gmshreader.hh>

typedef Dune::UGGrid<2> GridType;

std::vector<int> boundaryPhysicalEntities;
std::vector<int> elementPhysicalEntities;

auto grid = Dune::GmshReader<GridType>::
    read(mshfile, boundaryPhysicalEntities, elementPhysicalEntities);
);
```

## What is a tensor product grid?

A tensor product grid is a special kind of a non-equidistant structured cube grid. For each direction  $i \in \{0, \dots, d-1\}$  we define a monotonuous sequence of coordinates:

$$\left(x_j^i\right)_{j=0}^{N_i}$$

From those coordinates we define the set of grid vertices V as the tensor product of those coordinate sequences:

$$V = \left\{ (x_{i_0}^0, \dots, x_{i_{d-1}}^{d-1}) \middle| i_j \in \{0, \dots, N_j\} \forall j = 0, \dots, d-1 \right\}$$


The resulting grid has

$$N = \prod_{i=1}^{d-1} N_i$$

cells.

#### Tensorproduct grids in simulations

Tensorgrids combine the performance advantages of a structured grid with an unstructured grids capability to have different resolutions in different parts of the domain.



#### **TensorGridFactory**

YaspGrid provides a natural implementation of a tensor product grid. The coordinate sequences may be provided manually through std::vector<ctype>. TensorGridFactory provides convenient methods to fill such coordinate sequences:

```
void setStart(int d, ctype value)
```

- void fillIntervals(int d, int n, ctype h)
- void fillRange(int d, int n, ctype end)


void geometricFillIntervals(int d, int n, ctype ratio, ctype h0

- void geometricFillRange(int d, int n, ctype end, ctype h)
- **...**

The TensorGridFactory is compatible with all unstructured grid managers.

#### **Visualization**

- DUNE uses Paraview as a visualization program.
- Paraview uses the VTK (Visualization Toolkit) file format.
- Paraview can be obtained for free at http://www.paraview.org



#### **VTKWriter**

- To use the VTK-writer you have to #include<dune/grid/io/file/vtk/vtkwriter.hh>
- ► There are two different ways to use the VTKWriter:
  - Pass the data as a vector to the methods addCellData or addVertexData.
    - This is especially useful if your scheme already stores the solution in such a vector, i.e. cell- or vertex-centered Finite-Volume schemes.
  - Define your own VTKFunction and pass it to addCellData or addVertexData as appropriate.
    - This is the more general approach and usually done for Finite-Element or DG schemes.
- ► After attaching zero or more data fields the data file(s) can be written with the write method of the VTKWriter.

#### **VTK-Export** - **Elementdata**

```
template < class GridView >
void elementdata(const GridView& gridview)
    // allocate a vector for the data
    std::vector < double > solution(gridview.size(0));
    // iterate through all entities of codim 0
    for (const auto& e : elements(gridview))
        // get global coordinate of cell center
        auto global = e.geometry().center();
        // evaluate function and store value
        solution[gridview.indexSet().index(e)] = exp(global[0]*global[
    // generate a VTK file
    Dune::VTKWriter < GridView > vtkwriter (gridview);
    vtkwriter.addCellData(solution, "data");
    vtkwriter.write("elementdata", Dune::VTK::appendedraw);
```

#### VTK-Export - Vertexdata I

```
#include < dune / grid / io / file / vtk / vtkwriter.hh >
template < class GridView, class Functor >
void vertexdata(const GridView& gridview, const Functor& f) {
 // allocate a vector for the data
  std::vector<double> solution(gridview.size(GridView::dimension));
 // iterate through all entities of codim dim
 for (const auto& v : vertices(gridview))
      // evaluate functor and store value
      solution[gridview.indexSet().index(v)] = f(v.geometry().corner(0)
 // generate a VTK file
 Dune::VTKWriter < GridView > vtkwriter (gridview);
  vtkwriter.addVertexData(solution, "data");
  vtkwriter.write("vertexdata", Dune::VTK::appendedraw);
```

## **Defining a VTKFunction**

An output field can also be created by defining a VTKFunction object, e.g. MyVTKFunction<GridView>.

▶ It must be derived from

Dune::VTKWriter<GridView>::VTKFunction

- It has to provide the following functions:
  - ► the number of components (i.e. whether the plot value is scalar or e.g. a velocity vector):

```
virtual int ncomps() const;
```

➤ a function returning the value of the plot function for the component comp at position xi in entity e:

```
virtual double evaluate(int comp, const Entity& e,
    const Dune::FieldVector < ctype, Grid::dimension > & xi
    ) const;
```

▶ the name of the plot function to be written in the VTK-file:


```
virtual std::string name() const;
```

# VTK-Export - VTKFunction I


```
#include<dune/grid/io/file/vtk/vtkwriter.hh>
template < class GridView > class XY VTKFunction
  : public Dune::VTKWriter < GridView >:: VTKFunction
    dune_static_assert(GridView::dimension == 2,
                        "Illegal .. GridView .. dimension");
 public:
    typedef typename GridView::template Codim<0>::Entity Entity;
    typedef Dune::FieldVector < typename GridView::ctype,
            GridView::dimension> CoordType;
    virtual int ncomps() const { return 1; }
    virtual std::string name() const { return "xy_elementwise"; }
    virtual double evaluate(int comp, const Entity &e,
                             const CoordType &xi) const
        auto coord=e.geometry().global(xi);
        return coord[0]*coord[1];
};
```

#### **VTK-Export - VTKFunction II**

# VTKWriter vs. SubsamplingVTKWriter I



Regular VTKWriter



Subsampling VTKW riter

#### VTKWriter vs. SubsamplingVTKWriter II

To visualize more complex functions (higher order or mesh elements other than triangles or tetrahedra), a subsampling VTKWriter is needed.

Necessary Changes:

```
#include<dune/grid/io/file/vtk/subsamplingvtkwriter.hh>
Dune::SubsamplingVTKWriter<GridView> vtkwriter(gv, Dune::RefinementInt
```

This creates a subsampling VTKWriter and tells it to generate 2-times subrefined output. This happens "virtually", i.e. without modifying the grid.