

Lot Generation — Testing Document

Module: Inventory | QA Reference for Testers

 QA Reference

 Functional Testing

 Validation Testing

CONTENTS

- 1 Module Overview
- 2 Navigation & Access
- 3 Step 1 — Lot Configuration
- 4 Step 2 — Stock Selection Grids
- 5 Step 3 — Product Details
- 6 Weight Details & Calculations
- 7 Popups (Tare / Component / Stone)
- 8 Assignment & Add to Lot
- 9 Lot Details Table
- 10 Calculations Reference
- 11 Submit & Post-Submit
- 12 Table View (List)
- 13 Operating Modes & Flags
- 14 Custom Controls
- 15 Edge Cases
- 16 UI / UX & Visibility

1 Module Overview

Purpose: The Lot Generation form lets jewellery store operators create lots against inward stock, locker stock, or process stock (Hallmark, Certification, Remodel, Bandini) and assign each lot item to an employee. It supports three item types — **Metal**, **Brand**, and **Stone** — and on submission generates a unique lot number and triggers the corresponding stock ledger transactions.

Three-Step Wizard Flow

Step 1 · Lot Configuration → Step 2 · Stock Selection Grid →
Step 3 · Product & Weight Details → Add to Lot →
Lot Details Table → Submit · Lot No. Generated

Stock Source Paths

Inward / Process source

Stock is pulled from inward stock or, in Process Mode, from process stock. On submit, the lot weight is taken out of the stock you selected, and any remaining quantity stays available for future use.

Locker source

Stock is pulled from an employee's locker. On submit, the lot weight is taken out of that employee's locker only; other lockers are not affected.

User Roles & Locker Scope

Role	Locker Access Scope
Regular User	Sees only their own locker stock. The Employee field is fixed to the logged-in user and disabled.

Supervisor

Can view all employees' locker stock. The Employee dropdown lists all locker-mapped employees at the login location.

2 Navigation & Access

NAV-01 HIGH

Navigate to Lot Generation via menu

Inventory → Operations → Lot Generation

Lot Generation list view (Table View) loads with saved records for the current location and financial year.

NAV-02 HIGH

Open a new lot record

Click the "+" (Add) button in the list view

Form opens in "Add new record" mode. Step indicator shows Lot Configuration active; Product & Weight Details and Review & Submit are not yet reached.

NAV-03 HIGH

Add button respects role permission

Log in as a user without Add permission → open list view

The "+" Add button is hidden / inaccessible for users without Add permission in Roles and Rights.

NAV-04 MED

Step indicator navigation

Observe the top step indicator: Lot Configuration → Product & Weight Details → Review & Submit

Active step is highlighted in blue; completed steps show a filled dot; pending steps appear greyed.

NAV-05 MED

Keyboard Tab navigation

Press Tab through Step 1 fields

Focus moves in logical left-to-right order through visible, enabled fields; disabled / hidden fields are skipped.

NAV-06 HIGH

Role-based access (view / create / cancel / export)

Log in with different role configurations

Add, Cancel, Export, and Export All actions appear only for users granted the matching permission in Roles and Rights Configuration.

NAV-07 LOW

Back navigation from form

Click the back (↶) chevron beside the form title

User returns to the Lot Generation list view; unsaved entries are not persisted.

3 Step 1 — Lot Configuration

Cascading selection: Item Type must be chosen first — it enables Stock Source Type and all downstream controls. Changing Item Type or Stock Source Type resets every subsequent field and clears the lot table.

3.1 — Item Type

Description	Sets the type of jewellery item for the lot. This is the first choice the user makes; the rest of the fields turn on after it is selected.
Data Source	System Defined
Options	Metal, Brand, Stone
Filtration	▶ This is the first field on the form ▶ Must be filled in (mandatory)
Behaviour	▶ Selecting an Item Type turns on the Stock Source Type field. ▶ Changing the Item Type clears all the fields below it and empties the lot table. ▶ For a Locker source with Brand or Stone, the Stock Entity Type is set automatically and cannot be changed.
User Entry	Select from dropdown
Mandatory	Yes

BD-01 HIGH

Item Type options load

Dropdown lists exactly: Metal, Brand, Stone.

BD-02 HIGH

Item Type is mandatory

Leave Item Type empty and attempt to proceed

Field shows red border (as in the empty-state screen). Stock Source Type remains disabled until a value is chosen.

BD-03 HIGH

Selecting Item Type enables Stock Source Type

Select any Item Type

Stock Source Type dropdown becomes enabled.

BD-04 HIGH

Changing Item Type resets downstream

Configure a lot, then change Item Type

All later fields reset to empty and the lot table is cleared.

3.2 — Stock Source Type

Description	Sets where the stock comes from. Becomes active only after an Item Type is chosen. In Process Mode it is fixed to "Process".
Data Source	System Defined
Options	Normal Mode: Inward , Locker Process Mode: locked to Process (read-only)
Filtration	▶ Must be filled in (mandatory) ▶ Becomes active only after an Item Type is chosen ▶ In Process Mode it is fixed to "Process" and cannot be changed
Behaviour	▶ Inward → shows the From Transaction Type field and loads the inward stock grid. ▶ Locker → hides From Transaction Type, shows Employee and Locker Name, turns on Stock Entity Type and Stock Identity Type, and loads the locker stock grid. ▶ Process (Process Mode) → the field is locked; the pending stock grid loads from the login employee's mapped process.
User Entry	Select from dropdown

Mandatory Yes

BD-05 HIGH

Stock Source Type options (Normal Mode)

Dropdown lists Inward and Locker only.

BD-06 HIGH

Inward selection reveals From Transaction Type

Select Stock Source Type = Inward

From Transaction Type dropdown appears and the inward pending stock grid auto-loads.

BD-07 HIGH

Locker selection reveals locker fields

Select Stock Source Type = Locker

From Transaction Type is hidden; Employee, Locker Name, Stock Entity Type and Stock Identity Type appear.

BD-08 HIGH

Stock Source Type mandatory

Leave empty and attempt to proceed

Validation prevents proceeding; field flagged as required.

BD-09 HIGH

Process Mode locks the field

Enable Process Wise Maintenance in Settings

Stock Source Type displays "Process" as a read-only label and cannot be changed.

3.3 — From Transaction Type (Inward only)

Description	Filters the inward stock by the type of transaction it came from. Shown only when the source is Inward; hidden for Locker.
Data Source	Path: Admin > Control Panel > Transaction Type – Transaction Type
Options	Stock Inward — direct stock from vendor (Path: Procurement > Operations > Stock Inward — by Item Type: Stock Inward - Metal, Stock Inward - Brand, Stock Inward - Stone); Hallmark Receipt, Certification Receipt, Remodel Receipt ;

Bandini Receipt — stock returned after the respective process

Filtration	▸ Shows only when Stock Source Type = Inward; hidden for Locker ▸ Must be filled in when it is shown (mandatory) ▸ The list shows only the transaction types that have stock available for the chosen Item Type
Behaviour	▸ Picking a transaction type filters the Step 2 inward grid to show only stock received under that type.
User Entry	Select from dropdown
Mandatory	Yes (when shown)

BD-10 HIGH

From Transaction Type filters the grid

Select a transaction type

Inward pending stock grid re-renders to show only stock received under that transaction type.

BD-11 HIGH

Mandatory when visible

Inward selected, leave From Transaction Type empty

Treated as required; grid does not populate until a value is chosen.

BD-12 MED

Hidden for Locker

Switch Stock Source Type to Locker

From Transaction Type disappears completely.

3.4 — Vendor Filter (Inward)

Description	Narrows the inward stock grid to one or more vendors. Used only to filter the grid — it is not saved with the lot.
Data Source	Path: Procurement > Setup > Vendor > Vendor
Filtration	▸ Limited to the distinct vendors present in the current inward stock balance for the selected Item Type ▸ Multi-select, filter only — not a mandatory field ▸ Selecting one or more vendors re-renders the inward grid to matching records ▸ Visible when Stock Source Type = Inward; in

	Process Mode visible for Source From = Department or Process, hidden for Locker
User Entry	Select one or more from dropdown
Mandatory	No

BD-13 MED

Vendor filter narrows the grid

Select one or more vendors

Grid shows only stock belonging to the selected vendor(s). Clearing the filter restores all records.

BD-14 LOW

Vendor filter optional

Leaving Vendor empty shows all available inward stock; submission is not blocked by an empty Vendor filter.

3.5 — Brand Filter (Brand item type only)

Description	Narrows the inward stock grid to one or more brands. Shown only when Item Type = Brand. Used only to filter the grid — it is not saved with the lot.
Data Source	Path: Inventory > Product Definition > Article – Brand
Filtration	▸ Shows only the brands that have stock available to add to a lot ▸ Lets you pick more than one brand; it only filters the grid and is not saved on its own ▸ Appears only when Item Type = Brand ▸ Picking one or more brands refreshes the inward grid to show matching stock
User Entry	Select one or more from dropdown
Mandatory	No

BD-15 MED

Brand filter visible only for Brand

Select Item Type = Brand

Brand filter dropdown appears (as seen in the Brand UI screen). It is absent for Metal and Stone.

BD-16 MED

Brand filter narrows the grid

Select a brand

Grid shows only stock of the selected brand(s).

3.6 — Locker Extra Fields (Locker only)

Stock Entity Type — Description	Sets the kind of locker stock to work with. Only used for the Locker source. For Brand and Stone item types it is set automatically and cannot be changed.
Stock Entity Type — Data Source	System Defined
Stock Entity Type — Options	Item Type = Metal → Metal, Bullion ; Item Type = Stone → Stone (auto-set, disabled); Item Type = Brand → Brand (auto-set, disabled)
Stock Entity Type — Filtration	Mandatory; visible only when Stock Source Type = Locker. On selection, the locker grid is filtered to the chosen entity (Metal / Bullion / Brand / Stone) and the grid column set changes accordingly.
Stock Entity Type — User Entry	Select from dropdown (auto-set for Brand / Stone)
Stock Entity Type — Mandatory	Yes
Stock Identity Type — Description	Says whether the locker stock is regular stock or jobwork stock. Shown only for the Locker source.
Stock Identity Type — Data Source	System Defined
Stock Identity Type — Options	Stock, Jobwork Stock
Stock Identity Type — Filtration	Mandatory; visible only when Stock Source Type = Locker. Stock → locker grid loads standard stock records; Job ID column hidden. Jobwork Stock → locker grid loads jobwork records; Job ID column shown.
Stock Identity Type — User Entry	Select from dropdown
Stock Identity Type — Mandatory	Yes

BD-17 HIGH

Stock Entity Type options vary by Item Type

Locker selected → check options for Metal, Brand, Stone

Metal → Metal & Bullion; Brand → Brand only (disabled); Stone → Stone only (disabled).

BD-18 HIGH

Entity selection re-filters locker grid

Switch between Metal and Bullion

Locker grid columns and rows change to match the selected entity.

BD-19 HIGH

Stock Identity Type toggles Job ID column

Switch between Stock and Jobwork Stock

Job ID column appears only for Jobwork Stock; hidden for Stock.

BD-20 HIGH

Entity / Identity mandatory for Locker

Leave either empty

Locker grid does not load until both are set; treated as required.

3.7 — Process Mode Fields (Process Wise Maintenance = ON)

When Process Wise Maintenance is turned on (via the Settings gear icon), the Normal Mode fields are replaced. **Shown:** Item Type, Stock Source Type (locked, displays "Process"), Source From, Vendor filter, From Process, From Sub Process and From Transaction Type. **Hidden:** the normal Stock Source Type dropdown, Stock Entity Type, Stock Identity Type and the Inward version of From Transaction Type.

Source From — Description

Sets where the process-mode stock comes from. Decides which pending stock loads and which other fields appear. Used only to filter — not saved with the lot.

Source From — Data Source

System Defined

Source From — Options

Department, Locker, Process

Source From — Filtration

Multiple selections allowed; this is a filter only and is not mandatory. It decides which pending stock loads and

which other fields appear:

▸ **Department** → loads stock received from the procurement department. Shows the Vendor filter and From Transaction Type; hides From Process and From Sub Process.

▸ **Locker** → loads pending stock received from the locker. Shows the Vendor filter only; hides From Transaction Type, From Process and From Sub Process.

▸ **Process** → loads stock received from another process. Shows the Vendor filter, From Process, From Sub Process and From Transaction Type.

Source From — User Entry	Select one or more from dropdown
Source From — Mandatory	No (filter only)
From Process — Description	Picks the processing stage the non-barcoded stock comes from. Shown when Source From = Process.
From Process — Data Source	Path: HRM > Setup > Department > Process
From Process — Filtration	Not mandatory. Lists only the processes of the current department that are accessible at the login location. Shown when Source From = Process. Choosing a value loads its sub-processes into From Sub Process and filters the pending stock grid.
From Process — User Entry	Select from dropdown
From Process — Mandatory	No
From Sub Process — Description	Picks one or more sub-stages within the chosen From Process to narrow the stock further. Shown once a From Process is selected.
From Sub Process — Data Source	Path: HRM > Setup > Department > Sub Process
From Sub Process — Filtration	Multiple selections allowed; not mandatory. Lists the sub-processes of the selected From Process (only those that allow a sub-process). Shown once a From Process is selected; the selected sub-processes further filter the pending stock grid.

From Sub Process — User Entry	Select one or more from dropdown
From Sub Process — Mandatory	No

SPL-01 HIGH

Source From controls field visibility

Switch Source From between Department, Locker, Process

Department → Vendor filter + From Transaction Type. Locker → Vendor filter only. Process → Vendor filter + From Process + From Sub Process + From Transaction Type.

SPL-02 HIGH

Source From loads the right stock

Pick each Source From option

Department loads departmental stock; Locker loads locker stock; Process loads stock from another process.

SPL-03 HIGH

From Process populates Sub Process

Select a From Process value

From Sub Process fills with the sub-processes of the selected process.

SPL-04 HIGH

Process filters re-render pending grid

Choose From Process and one or more Sub Processes

Pending non-barcoded grid shows only stock matching the selected process / sub-process.

4 **Step 2 — Stock Selection Grids**

Grid columns change by Item Type, Stock Source Type, and (for Locker) Stock Entity Type. Selecting one grid row advances to Step 3 and populates Product Details. Only one row can be selected per "Add to lot" action.

4.1 — Inward Pending Stock Grid

Data Source

Current inward stock balance not yet consumed, filtered by Item Type, From Transaction Type, and the selected Vendor / Brand filters. Source by Item Type — Metal: Path **Procurement > Operations > Stock Inward - Metal**; Brand: Path **Procurement > Operations > Stock Inward - Brand**; Stone: Path **Procurement > Operations > Stock Inward - Stone**

Filtration

- ▶ Shown when Stock Source Type = Inward; hidden for Locker
- ▶ Metal grid for Item Type = Metal; Brand grid for Brand; Stone grid for Stone
- ▶ Only stock with a current available balance is listed

Metal — Inward Grid Columns

#	Column	Description
1	Checkbox	Select row to proceed to Product Details
2	Inward Number	Inward reference number
3	Group Category	Group category of the article
4	Category	Product category
5	Is Set Tag	Green "Yes" badge when the record is a Set Tag item
6	Article	Article name
7	Purity	Metal purity
8	No Of Pcs	Number of pieces
9	Gross Weight with Tare Weight	Total gross weight including tare
10	Tare Weight	Tare weight
11	Gross Weight	Gross weight
12	Component Weight	Component weight
13	Stone Weight	Stone weight
14	Net Weight	Net weight

Brand — Inward Grid Columns

#	Column	Description
1	Checkbox	Select row to proceed

2	Inward Number	Inward reference number
3	Brand	Brand name
4	Group Category	Group category
5	Category	Product category
6	Article	Article name
7	Purity	Metal purity
8	No Of Pcs	Number of pieces
9	Gross Weight	Gross weight
10	Stone Weight	Stone weight
11	Net Weight	Net weight
12	MRP (₹)	Maximum Retail Price per piece
13	Amount ₹	Auto-calculated: Pcs × MRP at grid render

Stone — Inward Grid Columns

#	Column	Description
1	Checkbox	Select row to proceed
2	Inward Number	Inward reference number
3	Stone Group	Stone group classification
4	Stone Category	Stone category
5	UOM	Gms or Cts
6	No Of Pcs	Number of pieces
7	Gross Weight with Tare Weight	Shown only when UOM = Gms; "—" for Cts records
8	Tare Weight	Shown only when UOM = Gms; "—" for Cts records
9	Stone Net Weight	Net stone weight

BI-01 HIGH

Inward grid auto-loads

Select Inward + From Transaction Type

Grid populates with pending inward stock and the correct column set for the chosen Item Type.

BI-02 HIGH

Row selection advances to Step 3

Tick one row's checkbox

Form moves to Product & Weight Details with the selected record's data pre-filled.

BI-03 HIGH

Set Tag record locks fields

Select a row flagged "Yes" under Is Set Tag

Article and all weight / tare / component / stone fields are locked; a red banner is shown.

BI-04 MED

Brand Amount column auto-calculates

Inspect Brand grid Amount column

Amount = Pcs × MRP for each row at grid render.

BI-05 MED

Stone UOM-dependent columns

Compare a Gms record and a Cts record

Gross Weight with Tare and Tare Weight show values for Gms; show "—" for Cts.

BI-06 MED

Grid search & records-per-page

Use the Search box and Records Per Page selector

Grid filters by search text; page size updates the visible row count.

4.2 — Locker Selection (Employee & Locker Name)

Employee — Data Source

Path: **HRM > Setup > Employee > Employee** — only employees mapped to a locker at the login location

Employee — Filtration

Mandatory for the locker flow; shown only when Stock Source Type = Locker. The Supervisor scope applies to employees whose Designation Type = Supervisor.

- **Regular User** (mapped to a locker) → the field is fixed to the logged-in user and disabled; locker stock loads automatically.
- **Supervisor** (Designation Type = Supervisor) → the dropdown lists all employees mapped to a locker at the

login location; locker stock loads after a selection is made.

Locker Name — Data Source

Path: **Inventory > Setup > Counter** (Counter Type = Locker) — the locker mapped to the selected employee at the login location

Locker Name — Filtration

Display only — always disabled; the user cannot change it.

- Auto-resolved from the locker mapped to the selected employee.
- For a Supervisor, it updates automatically when a different employee is chosen, but stays non-editable.

BI-07 HIGH

Regular User employee fixed & disabled

Regular User → Locker flow

Employee is set to the logged-in user and cannot be changed; their locker stock loads automatically.

BI-08 HIGH

Supervisor can pick any locker employee

Supervisor → open Employee dropdown

Lists all employees mapped to a locker at the login location.

BI-09 HIGH

Locker Name auto-resolves & is read-only

Select an employee

Locker Name fills with that employee's mapped locker; the field is always disabled.

BI-10 MED

Employee mandatory for locker flow

Supervisor leaves Employee empty

Locker grid does not load until an employee is selected.

4.3 — Locker Stock Grid

Data Source

Path: **Procurement > Operations > Locker Stock**
— locker stock balance of the selected employee's

auto-assigned locker, filtered by Stock Entity Type and Stock Identity Type

Filtration

- Shown when Stock Source Type = Locker; hidden for Inward
- Only the selected employee's own locker balance is shown — not all locker stock
- Column set varies by entity: Metal, Bullion, Brand, Stone
- From Transaction Type is hidden for all locker rows

Metal (Metal Entity) — Locker Grid Columns

#	Column	Description
1	Checkbox	Select row to proceed to Product Details
2	Job ID	Shown only when Stock Identity Type = Jobwork Stock
3	Item	Article
4	Purity	Metal purity
5	No Of Pcs	Number of pieces
6	Gross Weight	Gross weight

Metal (Bullion Entity) — Locker Grid Columns

#	Column	Description
1	Checkbox	Select row to proceed
2	Job ID	Shown only when Stock Identity Type = Jobwork Stock
3	Item	Article
4	Purity	Metal purity
5	Gross Weight	Gross weight
6	Net Weight	Net weight
7	Pure Weight	Pure weight

Brand — Locker Grid Columns

#	Column	Description
1	Checkbox	Select row to proceed

2	Inward Number	Inward reference number
3	Brand	Brand name
4	Item	Article
5	Purity	Metal purity
6	No Of Pcs	Number of pieces
7	Gross Weight	Gross weight
8	Stone Weight	Stone weight
9	Net Weight	Net weight
10	MRP (₹)	Maximum Retail Price per piece
11	Amount ₹	Total amount

Stone — Locker Grid Columns

#	Column	Description
1	Checkbox	Select row to proceed
2	Record ID	Stone stock record identifier
3	Stone Group	Stone group classification
4	Stone Category	Stone category classification
5	Stone Article	Stone article name
6	UOM	Gms or Cts
7	No Of Pcs	Number of pieces
8	Stone Gross Weight	Stone gross weight
9	Stone Net Weight	Stone net weight

BI-11 HIGH

Locker grid scoped to employee

Regular User opens Locker flow

Grid shows only the logged-in user's own locker balance.

BI-12 HIGH

Supervisor employee switch reloads grid

Supervisor selects a different employee

Locker Name re-resolves and grid reloads with that employee's locker balance.

BI-13 MED

Bullion entity shows Pure Weight

Metal + Bullion entity

Grid includes Gross Weight, Net Weight and Pure Weight columns.

BI-14 MED

Locker items have no design / sample / wastage

Select a locker row → inspect Step 3

Design Number is empty, Sample Weight = 0, wastage values are blank for locker items.

4.4 — Process Mode Pending Stock Grid

Data Source	Pending non-barcoded stock for the selected Source From (Department / Process / Locker), filtered by From Process / From Sub Process where applicable
Filtration	▸ Shown only when Process Wise Maintenance = ON ▸ Grid content changes with the selected Source From option ▸ Column structure mirrors the inward grid plus a Source column (Department / Process / Locker)

Metal — Process Grid Columns

#	Column	Description
1	Checkbox	Select row to proceed to Product Details
2	Reference Number	Inward / Process reference number
3	Source	Source of the stock (Department / Process / Locker)
4	Group Category	Group category of the article
5	Category	Product category
6	Article	Article name
7	Purity	Metal purity
8	No Of Pcs	Number of pieces
9	Gross Weight	Gross weight
10	Stone Weight	Stone weight
11	Net Weight	Net weight

Brand — Process Grid Columns

#	Column	Description
1	Checkbox	Select row to proceed
2	Reference Number	Inward / Process reference number
3	Source	Source of the stock (Department / Process / Locker)
4	Brand	Brand name
5	Group Category	Group category
6	Category	Product category
7	Article	Article name
8	Purity	Metal purity
9	No Of Pcs	Number of pieces
10	Gross Weight	Gross weight
11	Stone Weight	Stone weight
12	Net Weight	Net weight
13	MRP (₹)	Maximum Retail Price per piece
14	Amount ₹	Auto-calculated: Pcs × MRP at grid render

Stone — Process Grid Columns

#	Column	Description
1	Checkbox	Select row to proceed
2	Reference Number	Inward / Process reference number
3	Source	Source of the stock (Department / Process / Locker)
4	Stone Group	Stone group classification
5	Stone Category	Stone category
6	Stone Sub Category	Stone sub-category
7	Stone Article	Stone article name
8	UOM	Gms or Cts
9	No Of Pcs	Number of pieces
10	Stone Gross Weight	Shown only when UOM = Gms; "—" for Cts records

11	Tare Weight	Shown only when UOM = Gms; "—" for Cts records
12	Stone Net Weight	Net stone weight

BI-15 HIGH

Process grid shows Source column

Process Mode ON → load grid

Each row shows a Source value (Department / Process / Locker) plus a Reference Number.

BI-16 HIGH

Process grid respects Source From filter

Change Source From selection

Grid reloads to show only stock from the chosen source.

5 Step 3 — Product Details

Classification fields are locked by default. When "Change Article Name in Lot Generation" is OFF, Design Number, Category, Sub Category, Article and all Stone hierarchy fields are read-only and a yellow banner is shown: "Article fields are locked. Enable Change Article Name in Settings." Turning the setting ON unlocks them as editable dropdowns.

5.1 — Metal / Brand Classification Fields

Reference Type — Data Source System Defined

Reference Type — Options

Design Number, Combination

Reference Type — Filtration

Mandatory; shown for Metal, Brand and Bullion. Auto-set from the selected record (Design Number if the record has a design number, Combination otherwise) and read-only unless Change Article Name = ON. **Design Number** → the Design Number field is shown. **Combination** → the Design Number field is hidden.

Design Number — Data Source

Auto-filled from the selected stock record. When Change Article Name =

	ON → Path: Inventory > Setup > Design Master (filtered by Item Type and Group Category). Mandatory when visible; shown only when Reference Type = Design Number, hidden when Reference Type = Combination.
Group Category — Data Source	Auto-filled from the selected stock record (always read-only)
Category — Data Source	Auto-filled from the selected stock record. When Change Article Name = ON → Path: Inventory > Product Definition > Article > Category
Sub Category — Data Source	Auto-filled from the selected stock record. When Change Article Name = ON → Path: Inventory > Product Definition > Article > Category . Hidden for Brand item type.
Article — Data Source	Auto-filled from the selected stock record. When Change Article Name = ON → Path: Inventory > Product Definition > Article > Article
Filtration	Mandatory: Group Category, Article and Reference Type (and Design Number when visible). Optional: Category, Sub Category. When Change Article Name = ON and Reference Type = Design Number, changing the Design Number auto-populates Category, Sub Category and Article from the selected design number's article derivation. When Reference Type = Combination, Category, Sub Category and Article are selected manually (Article options are limited to articles linked to the selected Group Category / Category / Sub Category). The original article from the source record is always preserved separately.

BD-38 HIGH

Reference Type auto-sets & toggles Design Number

Select a record with a Design Number, then one with a Combination

Design Number record → Reference Type = Design Number and the Design Number field is shown. Combination record → Reference Type = Combination and the Design Number field is hidden.

BD-39 HIGH

Reference Type editable only when setting ON

Toggle Change Article Name

OFF → Reference Type is read-only. ON → it becomes a dropdown (Design Number / Combination); switching it shows or hides the Design Number field accordingly.

BD-21 HIGH

Classification auto-populates on row select

Select an inward / locker row

Group Category, Category, Sub Category, Article and Purity fill from the source record.

BD-22 HIGH

Fields locked when setting OFF

Change Article Name = OFF

All classification fields are read-only and the yellow lock banner is shown.

BD-23 HIGH

Fields editable when setting ON

Change Article Name = ON

Category, Sub Category, Article, Design Number become active dropdowns; Group Category and Purity stay read-only.

BD-24 HIGH

Article respects category hierarchy

Setting ON → change Category

Article dropdown lists only articles linked to the selected categories.

BD-25 HIGH

Group Category never editable

Setting ON → attempt to change Group Category

Group Category remains read-only regardless of the setting.

BD-26 MED

Sub Category hidden for Brand

Item Type = Brand

Sub Category field does not appear.

BD-40 HIGH

Changing Design Number cascades fields

Change Article Name = ON, Reference Type = Design Number → select a different Design Number

Category, Sub Category and Article auto-populate from the selected design number's article derivation.

5.2 — Pieces & Purity

Pieces — Data Source	Auto-filled from the selected stock record
Pieces — Filtration	Textbox; editable by the user. Mandatory. Positive integers only — decimals, negative signs and special characters are not allowed.
Purity — Data Source	Auto-filled from the selected stock record (always read-only)
Purity — Filtration	Read-only; cannot be changed. Mandatory when Item Type = Metal; not mandatory for Brand. If Purity is not resolved, "Add to lot" is blocked.

BD-27 HIGH

Pieces accepts positive integers only

Input: 5

Accepted. Decimals, negatives and special characters are rejected. Field is mandatory.

BD-28 HIGH

Purity read-only & mandatory (Metal)

Select a Metal row

Purity auto-populates and cannot be changed. If unresolved, "Add to lot" is blocked.

BD-29 MED

Purity not mandatory for Brand

Item Type = Brand without purity

Purity is not enforced as mandatory for Brand items.

5.3 — Brand Extra Fields (MRP & Amount)

Brand — Data Source	Auto-filled from the selected stock record
----------------------------	--

Brand — Filtration	Textbox; read-only — cannot be changed. Shown only when Item Type = Brand.
MRP (₹) — Data Source	Auto-filled from the selected stock record
MRP (₹) — Filtration	Textbox; editable. Optional. Shown only when Item Type = Brand. Positive decimal (up to 9 decimal places); zero and negative values are not allowed. Editing MRP recalculates Amount = Pieces × MRP.
Amount (₹) — Data Source	Auto-filled from the selected stock record
Amount (₹) — Filtration	Textbox; editable. Mandatory. Shown only when Item Type = Brand. Positive decimal (up to 9 decimal places); cannot exceed the source record's amount. Editing Amount recalculates $MRP = Amount \div Pieces$. On violation the border turns red with a "Max: ₹X" / "Exceeds max: ₹X" hint and "Add to lot" is blocked.

$$Amount = \frac{Pieces \times MRP}{MRP} \quad \text{when MRP edited}$$

$$MRP = \frac{Amount}{Pieces} \quad \text{when Amount edited}$$

BD-30 HIGH

MRP recalculates Amount

Pieces = 3, MRP = ₹5,000

Amount auto-updates to ₹15,000.

BD-31 HIGH

Amount back-calculates MRP

Pieces = 3, Amount = ₹12,000

MRP auto-updates to ₹4,000.

BD-32 HIGH

Amount cannot exceed record maximum

Record max = ₹10,000; enter Amount = ₹12,000

Border turns red, hint shows "Exceeds max: ₹10,000", and "Add to lot" is blocked.

BD-33 MED

MRP rejects zero / negative

MRP = 0 or -100

Rejected — only positive decimals accepted.

5.4 — Stone Classification Fields

Stone Group — Data Source	Auto-filled from the selected stock record. When Change Article Name = ON → Path: Inventory > Product Definition > Stone > Stone Group
Stone Category — Data Source	Auto-filled from the selected stock record. When ON → Path: Inventory > Product Definition > Stone > Stone Category
Sub Category — Data Source	Auto-filled from the selected stock record. When ON → Path: Inventory > Product Definition > Stone > Stone Sub Category
Stone Article — Data Source	Auto-filled from the selected stock record. When ON → Path: Inventory > Product Definition > Stone > Stone Article Catalog
UOM — Data Source	Auto-filled from the selected stock record (always read-only) — Gms or Cts
Filtration	Shown only when Item Type = Stone. When editable, Stone Article options are limited to articles linked to the selected Stone Group / Category / Sub Category; selecting a Stone Article auto-fills the hierarchy. The original article is preserved separately.

BD-34 HIGH

Stone hierarchy auto-populates

Select a Stone row

Stone Group, Stone Category, Sub Category, Stone Article and UOM fill from the source record.

BD-35 HIGH

Stone fields locked when setting OFF

Change Article Name = OFF

All stone classification fields are read-only; lock banner shown.

BD-36 HIGH

Stone Article drives hierarchy when ON

Setting ON → change Stone Article

Stone Group, Category and Sub Category update to match the selected article.

BD-37 MED

UOM always read-only

UOM cannot be changed regardless of the setting.

6 Weight Details & Calculations

All net / pure / diamond / balance weight fields are system-calculated and read-only. Weight inputs accept positive decimals up to 9 decimal places and cannot exceed the source record's corresponding weight. Net Weight can never be negative.

6.1 — Metal / Brand Weight Fields

Gross Weight with Tare	Textbox; auto-filled from the record; editable. Shown only when the record has tare data. Mandatory when the record has tare weight. Positive decimal (up to 9 places); cannot exceed the record gross weight.
Tare Weight (label)	Read-only display; default 0.000. Shows the total tare applied after the Tare Weight popup is confirmed.
Tare Weight (button)	Opens the Tare Weight Split popup. On apply, the tare is deducted from Gross Weight and Net Weight recalculates.
Gross Weight	Textbox; auto-filled from the record. Mandatory (Metal). Editable when no

	tare is applied; becomes read-only and auto-calculated (Gross Weight with Tare – Applied Tare) when tare is applied. Positive decimal; cannot exceed the record gross weight; cannot be zero / negative.
Component Weight (label)	Read-only display; default 0.000. Shows the total component gross weight applied. Metal item type only.
Component Weight (button)	Opens the Component Details popup. Metal only; disabled when the record has no component data or the item is Set Tag locked.
Diamond Weight	Read-only display card; auto-calculated from the record's diamond stone data (Cts × 0.2, or Gms directly) and summed across all diamond stone entries. Metal and Brand.
Stone Weight (label)	Displays the total stone weight applied. Brand → editable input (when no tare); Metal → always read-only (set via the Stone Details popup). When tare is applied, it becomes read-only and is auto-calculated as Gross Weight with Tare – Applied Tare. Positive decimal; cannot exceed the record stone weight.
Stone Weight (button)	Opens the Stone Details (Edit & Split) popup. On save, the Stone Weight label updates and Net Weight recalculates. Metal and Brand.
Net Weight	Textbox; read-only; auto-calculated as Gross Weight – Component Weight – Stone Weight. Mandatory (Metal). Cannot be negative.
Balance Strip	Read-only display. Shows Record Gross Weight, Record Net Weight, Balance Gross Weight and Balance Net Weight; updates after each "Add to lot".

$$\begin{aligned}
 \text{Gross Weight (tare applied)} &= \begin{array}{l} \text{Gross} \\ \text{Weight} \\ \text{with} \\ \text{Tare} - \\ \text{Applied} \\ \text{Tare} \end{array} \quad \text{read-only when tare applied} \\
 \\
 \text{Net Weight} &= \begin{array}{l} \text{Gross Weight} \\ - \text{Component} \end{array} \quad \text{must be } \geq 0
 \end{aligned}$$

Weight -
Stone Weight

Diamond Weight (Cts)

= Carats
× 0.2 when stone UOM = Cts

Diamond Weight (Gms)

= Grams
directly when stone UOM = Gr

CALC-01 HIGH

Net Weight auto-calculates

Gross 45.250, Component 8.500, Stone 2.100

Net Weight = 34.650 (read-only).

CALC-02 HIGH

Net Weight cannot be negative

Gross 5.000, Component 6.000

Red error banner under the weight section; "Add to lot" blocked.

CALC-03 HIGH

Gross becomes read-only with tare

Apply tare via the Tare popup

Gross Weight shows "Auto-calculated from Tare", greyed background, not editable.

CALC-04 HIGH

Gross cannot exceed record gross

No tare → enter Gross above record value

Red border + hint; entry rejected.

CALC-05 HIGH

Diamond Weight auto-calc (Cts)

Diamond rows: 5.25 Cts + 2.10 Cts

Diamond Weight = $(5.25 \times 0.2) + (2.10 \times 0.2) = 1.470$ gms (read-only).

CALC-06 MED

Balance strip updates per add

Add a lot row

Record Gross / Net and Balance Gross / Net update to reflect remaining quantity.

6.2 — Stone Weight Fields

Stone Pieces	Textbox; auto-filled from the record; editable. Mandatory. Stone item type only. Positive integer, minimum 1; cannot exceed the record pieces (red hint "Cannot exceed: [max] pcs" on violation).
Gross Weight with Tare	Textbox; auto-filled from the record; editable. Shown only when the record has tare data. Mandatory when the record has tare weight. Positive decimal (up to 9 places); cannot exceed the record gross weight.
Tare Weight (label)	Read-only display; default 0.000. Shows the applied tare deducted from Gross Weight with Tare.
Tare Weight (button)	Opens the Tare Weight Split popup. On apply, tare is deducted from Gross Weight and Stone Net Weight recalculates.
Stone Gross Weight	Textbox; auto-filled from the record; editable. Mandatory. Stone only. Label changes with UOM ("Weight in Grams (Gms)" or "Weight in Carats (Cts)"). Positive decimal (up to 9 places); cannot exceed the record maximum weight.
Balance Weight	Read-only; auto-calculated as $\max(0, \text{Record Weight} - \text{Used in prior lot rows})$. Stone only.
Stone Net Weight	Textbox; read-only; mandatory. Stone only. If tare applied $\rightarrow$ Gross Wt with Tare – Tare Weight; if no tare $\rightarrow$ the entered weight value. Recalculates when tare is applied.
Balance Strip	Read-only display. Shows Record Pieces, Record Weight, Balance Pieces and Balance Weight; updates after each "Add to lot".

Stone Net Weight (tare)	$\begin{array}{l} \text{Gross Wt} \\ \text{with} \\ \text{Tare} - \\ \text{Tare} \\ \text{Weight} \end{array}$	<i>when tare applied</i>
Stone Net Weight (no tare)	Entered Weight	<i>when no tare</i>

Balance Weight

$\text{max}(0, \text{Record Weight} - \text{Used in prior rows})$ *read-only*

CALC-07 HIGH

Stone Net Weight with tare

Gross w/Tare 45.700, Tare 3.200

Stone Net Weight = 42.500 (read-only).

CALC-08 HIGH

Balance Weight calculation

Record 25.500, used 10.000

Balance Weight = 15.500. When fully used, Balance = 0.000.

CALC-09 HIGH

Stone pieces cannot exceed record

Record max = 8; enter 10

Red hint below Pieces: "Cannot exceed: 8 pcs". Minimum value is 1.

CALC-10 HIGH

Stone weight cannot exceed record

Enter weight above record maximum

Red border + hint; entry rejected.

CALC-11 MED

Weight label reflects UOM

Label reads "Weight in Grams (Gms)" or "Weight in Carats (Cts)" per the record's UOM.

7 Popups — Tare / Component / Stone / Image

7.1 — Tare Weight Split Popup

Opened from the Tare Weight button in the Weight Details section (Metal, Brand and Stone). An info banner reads: "Adjust split weight per row, or remove to exclude." The user adjusts the split weight

per tare row or removes rows; on Apply, the applied tare is deducted from Gross Weight and Net Weight recalculates.

#	Column	Type	Remarks
1	Item	Label	Tare item name (e.g., Box, Tag, Pouch)
2	Tare Weight Type	Badge	e.g., "Per Pcs" — blue if pieces > 0, grey otherwise
3	No of Pieces	Label	Tare pieces from source record
4	Per Piece Weight	Label	Weight per tare piece from source record
5	Tare Weight	Label	No of Pieces × Per Piece Weight
6	Split Weight	Editable Input	User-adjusted weight to apply; positive decimal up to 9 places; cannot exceed Tare Weight
7	Action	Button	Remove (X) — excludes the tare row

Footer

Shows the totals of the Tare Weight and Split Weight columns, with a strip at the bottom showing the total tare weight that will be applied.

Buttons

Apply tare weight applies the tare, takes it off the Gross Weight, and updates the Net Weight.
Cancel closes the popup without applying anything.

POP-01 HIGH

Apply deducts tare

Adjust split → Apply tare weight

Tare Weight label and Net Weight update; Gross becomes read-only auto-calculated.

POP-02 HIGH

Split cannot exceed tare

Tare = 2.000, Split = 3.000

Red border on the split input; cannot apply.

POP-03 MED

Remove row excludes tare

Click X on a row

Row removed; footer totals recompute.

POP-04 MED

Cancel discards changes

Open popup, edit, click Cancel

Popup closes; no tare applied; original values retained.

POP-05 MED

Footer totals correct

Footer shows accurate column totals for Tare Weight and Split Weight, plus a "Total tare weight to apply" strip.

7.2 — Component Details Popup (Metal only)

Opened from the Component Weight button (Metal item type). Disabled when the source record has no component data or the item is Set Tag locked. The user selects component rows and adjusts issue weights.

#	Column	Type	Remarks
1	Checkbox	Checkbox	Include component row (default checked)
2-5	Group Category / Category / Article / Purity	Label	Component classification
6	Gross Weight	Editable Input	Issue gross weight; positive decimal up to 9 places
7	Diamond Weight	Label (auto)	From component stone data, Diamond category
8	Stone Weight	Label + Edit	Edit opens Component Stone Details Popup
9	Net Weight	Label (read-only)	Gross Weight – Stone Weight
10	Pure Weight	Label (auto)	Net Weight × Purity%

Footer

Shows how many rows are selected (for example, "0 of 2 selected") and the total component weight being issued.

Buttons

Save Component Details saves the component weights to the lot item. **Cancel** closes the popup without saving.

Component Net Weight = $\text{Gross Weight} - \text{Stone Weight}$ *read-only*

Component Pure Weight = $\text{Net Weight} \times \text{Purity\%}$ *read-only*

POP-06 HIGH

Component Net & Pure auto-calc

Gross 8.500, Stone 0.300, Purity 91.6%

Net = 8.200; Pure = $8.200 \times 91.6\% = 7.511$.

POP-07 HIGH

Save carries component weight back

Adjust → Save Component Details

Component Weight on the main form updates; Net Weight recalculates.

POP-08 MED

Unchecking excludes component

Uncheck a component row

Footer "selected" count and Total Issue Component Weight update.

POP-09 MED

Button disabled when no components

Select a record with no component data

Component Weight button is disabled.

POP-17 MED

Cancel discards component changes

Open popup, adjust weights, click Cancel

Popup closes without saving; component weights on the main form are unchanged.

7.3 — Component Stone Details Popup

Opened from the Stone WT edit button inside the Component Details Popup. The user adjusts issue pieces and weight for each stone row of the selected component. Issue values cannot exceed the source record's receipt values. The header shows the selected

component's name and category (e.g., "Component: Clasp | Category: Hook").

#	Column	Type	Remarks
1	Checkbox	Checkbox	Include stone row (default checked)
2	Stone Group	Label	Stone group classification
3	Stone Category	Label	Stone category
4	Stone Sub Category	Label	Stone sub-category
5	Stone Article	Label	Stone article name
6	UOM	Label	Cts or Gms
7	Receipt Pieces	Label	Total pieces from source record
8	Issue Pieces	Editable Input	Positive integer; cannot exceed Receipt Pieces
9	Receipt Weight	Label	Total weight from source record
10	Issue Weight	Editable Input	Positive decimal up to 9 places; cannot exceed Receipt Weight

Footer Shows how many rows are selected (for example, "0 of 2 selected") and the total stone weight.

Buttons **Save Stone Details** saves the changes — the component's stone weight and net weight are updated. **Cancel** closes the popup without saving.

POP-10 HIGH

Issue Pieces cannot exceed Receipt

Receipt 18, Issue 20

Red border on input; rejected. Issue 10 of 18 is accepted.

POP-11 HIGH

Save updates component stone weight

Adjust issue values → Save

Component Diamond / Stone weight recalculates and carries back to the Component popup.

POP-12 MED

Header shows component context

Popup header displays the component name and category.

POP-18 HIGH

Issue Weight cannot exceed Receipt

Receipt 5.250, Issue 6.000

Red border on input; rejected. Issue 2.500 of 5.250 is accepted.

POP-19 MED

Cancel discards stone changes

Adjust issue values → Cancel

Popup closes without saving; component stone weight is unchanged.

7.4 — Stone Details (Edit & Split) Popup

Opened from the Stone Weight (+) button (Metal and Brand item types). An info banner reads: "Select rows to include. Enter Issue Pieces and Issue Weight less than record values to split a partial quantity." The user selects and adjusts stone rows from the source record. On Save, the Stone Weight label updates and Net Weight recalculates (for Brand, the editable stone weight input also updates).

#	Column	Type	Remarks
1	Checkbox	Checkbox	Include stone row (default checked)
2	Stone Group	Label	Stone group classification
3	Stone Category	Label	Stone category
4	Stone Sub Category	Label	Stone sub-category
5	Stone Article	Label	Stone article name
6	UOM	Label	Cts or Gms
7	Receipt Pieces	Label	Total pieces from source record
8	Issue Pieces	Editable Input	Positive integer; cannot exceed Receipt Pieces
9	Receipt Weight	Label	Total weight from source record
10	Issue Weight	Editable Input	Positive decimal up to 9 places; cannot exceed Receipt Weight

Footer

Shows how many rows are selected (for example, "0 of 2 selected") and the total stone weight being issued.

Buttons

Save Stone Details saves the stone weights to the lot item. **Cancel** closes the popup without saving.

POP-13 HIGH**Stone Save recalculates Net Weight**

Adjust stone rows → Save

Stone Weight label updates; $\text{Net Weight} = \text{Gross} - \text{Component} - \text{Stone}$ recomputes.

POP-14 MED**Brand editable stone weight**

Brand item → edit stone weight

Editable stone input also updates; cannot exceed record stone weight (red border on violation).

POP-20 HIGH**Issue Pieces cannot exceed Receipt**

Receipt 18, Issue 20

Red border on input; rejected. Issue 10 of 18 is accepted.

POP-21 HIGH**Issue Weight cannot exceed Receipt**

Receipt 5.250, Issue 6.000

Red border on input; rejected. Issue 2.500 of 5.250 is accepted.

POP-22 MED**Cancel discards stone changes**

Adjust stone rows → Cancel

Popup closes without saving; the Stone Weight on the main form is unchanged.

7.5 — Image Popup

POP-15 MED**Add image via webcam / file**

Click Add Image → capture or browse

Image attaches to the lot item and is saved with it on submit.

POP-16 LOW

Cancel discards image

Open modal → Cancel

No image is attached.

8 Assignment & Add to Lot

8.1 — Assignment Fields

Employee — Data Source	Path: HRM > Setup > Employee > Employee (employees of designation type "Barcode")
Employee — Filtration	Mandatory before "Add to lot". Toast error if empty on add.
Business Unit — Data Source	Path: Admin > Organization > Business Unit
Business Unit — Filtration	Optional.
Remarks — Data Source	Entered manually on screen — no setup required. Free-text. Optional.

BI-17 HIGH

Employee is mandatory

Leave Employee empty → Add to lot

Toast error shown; row not added.

BI-18 MED

Business Unit optional

Add a lot row without Business Unit

Row added successfully.

BI-19 LOW

Remarks accepts free text

Enter alphanumeric + special characters

Accepted; saved with the lot item.

8.2 — Add to Lot Validation

"Add to lot" runs all field validations before adding: Employee (mandatory), Article (mandatory for Metal / Brand), Gross Weight (required), Net Weight (≥ 0), and Amount (Brand, $\leq$ record max). On success the row is added and Step 3 resets for the next item; on failure, toast errors and red borders appear.

BI-20 HIGH

Valid entry adds row & resets

Fill all required fields → Add to lot

Row appears in the Lot Details Table; Step 3 clears for the next item.

BI-21 HIGH

Missing Article blocks add (Metal/Brand)

Clear Article → Add to lot

Toast error + red border on Article; row not added.

BI-22 HIGH

Missing Gross Weight blocks add

Leave Gross Weight blank → Add to lot

Toast error; row not added.

BI-23 HIGH

Negative Net Weight blocks add

Force Net Weight below 0

Red error banner; "Add to lot" blocked.

9 Lot Details Table

Lists all items added to the current lot session; updates dynamically as items are added or removed. At the bottom, a "Totals" row adds up the Net Weight of all the rows and shows the total under the Net Weight column.

Column	Description
#	Serial number
Type	Item Type (Metal / Brand / Stone)

Group Category	Group category
Purity	Purity name
Brand	Brand name (Brand items only)
No Of Pcs	Number of pieces
Total Gross Weight with Tare Weight	Total gross weight including tare
Tare Weight	Tare weight
Gross Weight	Gross weight
Component Weight	Component weight
Stone Weight	Stone weight
Net Weight	Net weight
Employee	Assigned employee name
MRP	MRP (Brand items only)
Delete (X)	Removes the row from the current session (not a permanent delete)

BI-24 HIGH

Added rows appear correctly

Add multiple lot items

Each row shows correct type, weights, employee, and (for Brand) MRP.

BI-25 HIGH

Delete removes from session only

Click X on a row

Row removed from the table; footer Net Weight total recomputes; no database change.

BI-26 MED

Footer total matches sum of rows

Footer Net Weight equals the sum of all row Net Weights.

10 Calculations Reference

All calculated fields below are read-only and system-managed.

Any calculated field that accepts manual input is an automatic release blocker. Decimal precision is up to 9 places.

10.1 — Weight Calculations

Gross Weight (tare)	=	Gross Weight with Tare - Applied Tare	<i>tare applied</i>
Net Weight	=	Gross Weight - Component Weight - Stone Weight	≥ 0
Stone Net Weight	=	Gross Wt with Tare - Tare Weight	<i>stone, tare applied</i>
Balance Weight	=	max(0, Record Weight - Used in prior rows)	<i>read-only</i>

CALC-12 HIGH

Net Weight (no stone, no component)

Gross 22.500, Component 0.000, Stone 0.800

Net Weight = 21.700.

CALC-13 HIGH

Stone Net Weight (no tare)

Entered Weight 42.500, no tare

Stone Net Weight = 42.500.

10.2 — Component Calculations

Component Net Weight	=	Gross Weight - Stone Weight	<i>read-only</i>
Component Pure Weight	=	Net Weight × Purity%	<i>read-only</i>
Diamond Weight	=	Carats × 0.2 (Cts) or Grams (Gms)	<i>summed across diamond</i>

CALC-14 HIGH

Component Pure Weight

Net 8.200, Purity 91.6%

Pure Weight = 7.511.

CALC-15 HIGH

Diamond Weight conversion

1.5 Cts diamond

Diamond Weight = 0.300 gms.

10.3 — Brand Amount Calculations

Amount = Pieces × MRP ≤ record max

MRP = $\frac{\text{Amount}}{\text{Pieces}}$ when Amount edited

CALC-16 HIGH

Amount from MRP

Pieces 5, MRP ₹2,500

Amount = ₹12,500.

10.4 — Lot Header Totals (on Submit)

Total Pieces = Sum of all lot-row pieces header total

Total Net Weight = Sum of all lot-row Net Weights header total

Total Gross Weight = Sum of all lot-row Gross Weights header total

CALC-17 HIGH

Header totals roll up rows

Add 3 lot rows → submit

Saved lot's Pieces, Gross and Net Weight equal the sum of all added rows.

11 Submit & Post-Submit Behaviour

Submit Validation

SUB-01 HIGH

At least one item required

Click Submit with an empty lot table

Toast error: "At least one item required to save lot". Nothing is saved.

SUB-02 HIGH

Successful submit generates lot number

Add valid rows → Submit

Success modal shows a lot number in the format LOT-YYYY-XXXXX.

SUB-03 MED

Success modal print option

On success modal

"Yes, print" opens print preview; "No, go back" closes the modal.

Stock Impact — what gets reduced on Submit

When the lot is submitted, the weight and pieces in the lot are taken out of the stock you picked from. What gets reduced depends on the source you chose. Whatever is left over stays available for future use.

Inward source

The lot weight is reduced from the inward stock you selected — the stock matching your chosen Item Type, From Transaction Type and Vendor. Any remaining quantity stays available; if you used the whole record, nothing is left for it.

Locker source

The lot weight is reduced from the selected employee's locker — the stock held under the chosen Employee and Locker Name. Only that locker's stock goes down; other lockers are not affected.

Process source (Process Mode)

The lot weight is reduced from the process stock you selected — the stock matching the chosen Source From, From Process, From Sub Process and From Transaction Type. Any remaining quantity stays available.

SUB-04 HIGH

Inward submit reduces the selected stock

Submit an inward lot for part of a record

The lot weight is taken out of the selected inward stock (Item Type + From Transaction Type + Vendor). The leftover quantity stays available; if fully used, nothing remains for that stock.

SUB-05 HIGH

Locker submit reduces the employee's locker

Submit a locker lot

The lot weight is taken out of the selected employee's locker (Employee + Locker Name); other lockers are unchanged.

SUB-09 HIGH

Process submit reduces the process stock

Process Mode → submit a process lot

The lot weight is taken out of the selected process stock (Source From + From Process + From Sub Process + From Transaction Type); the leftover quantity stays available.

SUB-06 HIGH

Saved lot appears in Table View

Submit → return to list

New lot is listed with its lot number, date, item type, source, pieces and weights.

SUB-07 MED

Clear All resets the form

Click Clear All

Form reloads to the initial empty state; no database changes occur.

SUB-08 MED

Approval status on save

Submit a lot

New lot's Approval Status is "Created".

12 **Table View (List)**



The Table View lists all saved Lot Generation records for the current location and financial year.

Column	Description
Lot No.	Auto-generated lot number
Date	Transaction date
Item Type	Metal / Brand / Stone
Stock Source	Inward / Locker / Process
Pieces	Total pieces in the lot
Gross Weight	Total gross weight
Net Weight	Total net weight
Employee	Assigned employee name
Business Unit	Assigned business unit name
Approval Status	Created, Approved, Rejected, Cancelled, etc.
Active	True / False
Actions	Edit / View / Delete / Cancel

LV-01 HIGH

List loads with correct columns

All columns above are present and populated for saved lots.

LV-02 MED

Search filters the list

Type in the Search box

Only matching records are shown.

LV-03 HIGH

Cancel changes Approval Status

Cancel a lot in Created / Pending status

Confirmation prompt shown; on confirm, status becomes Cancelled.

LV-04 HIGH

Cancel blocked when linked

Cancel a lot linked to active transactions

Error: "Lot Generation record cannot be cancelled as it is linked with active transactions."

LV-05 MED

Export filtered records

Apply a filter → Export

Only records matching the current filter are exported.

LV-06 MED

Export All

Click Export All

All records export regardless of the current filter.

LV-07 LOW

Records-per-page & pagination

Change page size; navigate pages

Row count and pagination update accordingly.

LV-08 MED

Print a selected lot

Use Print action (with permission)

Print-ready view / print dialog opens.

13 Operating Modes & Flags

13.1 — Normal Mode vs Process Mode

Normal Mode (Process Wise Maintenance OFF)

Stock Source Type offers Inward and Locker. Standard barcoded stock flow. Source From, From Process, From Sub Process and Vendor (filter) are not shown.

Process Mode (Process Wise Maintenance ON)

Stock Source Type locked to "Process". Non-barcoded flow. Source From, Vendor (filter), From Process, From Sub Process and a Process version of From Transaction Type are shown. Switching the toggle resets all current selections.

SPL-05 HIGH

Process toggle changes field set

Toggle Process Wise Maintenance

Field set switches between Normal and Process layouts; selections reset.

SPL-06 HIGH

Process locks Stock Source Type

Process Mode ON

Stock Source Type shows "Process" read-only.

13.2 — Change Article Name Flag

SPL-07 HIGH

OFF locks article fields

Change Article Name = OFF

Design Number, Category, Sub Category, Article and all Stone hierarchy fields are read-only; yellow lock banner shown.

SPL-08 HIGH

ON unlocks article fields

Change Article Name = ON

Those fields become editable dropdowns; original article from the source record is preserved separately.

13.3 — Set Tag Items

SPL-09 HIGH

Set Tag locks weight controls

Select a Set Tag row

Article and all weight / tare / component / stone controls are disabled; red banner shown.

13.4 — Regular User vs Supervisor (Locker)

SPL-10 HIGH

Regular User locked to own locker

Regular User → Locker flow

Employee field is fixed to the logged-in user and disabled; only their locker stock loads.

SPL-11 HIGH

Supervisor can choose any employee

Supervisor → Locker flow

Employee dropdown lists all locker-mapped employees; selecting one loads that locker's stock and resolves Locker Name (still non-editable).

A Custom Control button (gear icon, purple border) appears in the Lot Configuration section (lot level), the Metal item detail panel, and the Stone item detail panel. It opens client-configured custom fields for that level; values entered are saved with the lot on Submit.

SPL-12 MED**Custom Control button opens inputs**

Click the gear icon at lot / item level

The configured custom controls (textbox, dropdown, checkbox, date, etc.) render for that level.

SPL-13 MED**Custom values persist on submit**

Enter custom values → Submit

Values are saved against the correct level (lot, metal item, or stone item).

SPL-14 LOW**No custom controls configured**

Client with no custom controls

Opening the panel shows no custom fields; form behaves normally.

EC-01 HIGH**Zero pieces**

| Pieces = 0

Rejected — Pieces must be a positive integer (minimum 1 for Stone).

EC-02 HIGH**Negative weight**

| Gross Weight = -5

Rejected — only positive decimals accepted.

EC-03 HIGH

Weight at record maximum

Enter exactly the record gross weight

Accepted; no error.

EC-04 HIGH

Weight just over maximum

Record max + 0.001

Red border + hint; "Add to lot" blocked.

EC-05 MED

Decimal in Pieces field

Pieces = 3.5

Rejected — whole numbers only.

EC-06 MED

Alphabetic in numeric field

Gross = "abc"

Rejected / not entered.

EC-07 HIGH

9-decimal precision

Weight = 12.123456789

Accepted to 9 decimal places without truncation error.

EC-08 HIGH

Fully consume a source record

Add the entire record quantity

On submit, the source record shows no remaining balance.

EC-09 MED

Tare split exceeds record total

Set split above the row tare

Red border; cannot apply.

EC-10 MED

Issue pieces exceed receipt (component stone)

Receipt 18, Issue 19

Red border; rejected.

EC-11 MED

Network interruption during submit

Drop connection mid-submit

No partial lot is created; user can retry; no orphan ledger entries.

EC-12 MED

Many lot rows (performance)

Add a large number of lot rows

Lot table, footer totals and submit remain responsive and accurate.

EC-13 MED

Special characters in Remarks

Remarks with symbols

Accepted and saved without breaking the form.

EC-14 MED

Change Item Type mid-entry

Build a partial lot, then change Item Type

All later selections and the lot table reset; no stale data carried over.

16 UI / UX & Field Visibility



Quick Visibility Checklist

- ☐ Step indicator (Lot Configuration → Product & Weight Details → Review & Submit) visible with the active step highlighted.
- ☐ Lot Configuration section header with gear / settings icon visible.
- ☐ Item Type dropdown shows a red border when left empty (mandatory).
- ☐ Stock Source Type disabled until Item Type is selected.
- ☐ From Transaction Type appears only for Inward.
- ☐ Vendor filter and (for Brand) Brand filter render in the correct position.

- ☐ Process Mode fields (Source From, From Process, From Sub Process) appear only when Process Wise Maintenance is ON.
- ☐ Yellow lock banner shows when Change Article Name is OFF.
- ☐ Green "Yes" Set Tag badge renders in the inward grid.
- ☐ Red banner shows for Set Tag locked items.
- ☐ Search box, Records Per Page selector and pagination controls visible on grids.
- ☐ Grid column set changes correctly per Item Type / entity.
- ☐ Tare Weight, Component Weight and Stone Weight buttons visible per applicable item type.
- ☐ Read-only weight fields (Net, Diamond, Balance) appear greyed / non-editable.
- ☐ Balance strip displays record vs balance values.
- ☐ Add to Lot button visible and enabled when fields are valid.
- ☐ Lot Details Table shows the per-row Delete (X) action.
- ☐ Lot Details Table footer shows the total Net Weight.
- ☐ Custom Control gear icon (purple border) visible at lot and item levels.
- ☐ Clear and Submit buttons visible in the floating bottom bar.
- ☐ Success modal with lot number and print options appears on submit.

Field Type Summary

Mandatory Fields

MANDATORY

- Item Type
- Stock Source Type
- From Transaction Type (Inward)
- Stock Entity Type (Locker)
- Stock Identity Type (Locker)
- Employee (locker flow & assignment)
- Article (Metal / Brand)
- Pieces
- Purity (Metal)
- Gross Weight (Metal)
- Net Weight (Metal)
- Stone Group / Category / Sub Category / Article (Stone)
- Stone Pieces & Stone Net Weight (Stone)
- Amount (Brand)

- At least one lot row (Submit)

Auto-Calculated (Read-Only)

CALC

- Net Weight
- Gross Weight (when tare applied)
- Diamond Weight
- Stone Net Weight
- Balance Weight
- Tare Weight (label)
- Component Weight (label)
- Component Net & Pure Weight
- Brand Amount / MRP (bi-directional)
- Locker Name (auto-assigned)
- Group Category & Purity (always read-only)
- UOM (Stone)
- Balance strip values
- Lot header totals (on submit)

Optional Fields

OPTIONAL

- Vendor filter
- Brand filter
- From Process / From Sub Process
- Source From
- Business Unit
- Remarks
- Add Image
- MRP (Brand — conditional)
- Gross Weight with Tare (conditional — only when record has tare)
- Custom Controls (client-configured)

✅ **Test Sign-off Criteria:** All HIGH priority test cases must PASS before release. MED priority should pass for standard release. LOW priority items are regression/enhancement candidates. Any CALC or READ-ONLY field showing editable input is an automatic release blocker.