• The hardware *and* software resources located in the MVB Linux lab(s). (e.g., MVB-1.15 or MVB-2.11) are managed by the Faculty IT Support Team, a subset of IT Services. If you encounter a problem (e.g., a workstation that fails to boot, an error when you try to use some software, or you just cannot log into your account), they can help: you can contact them, to report then resolve said problem, using details collated at

## https://www.bristol.ac.uk/it-services/contacts

• The worksheet is written *assuming* you work in the lab. using UoB-managed equipment. If, however, you prefer to use your own equipment, *unsupported*<sup>a</sup> alternatives *do* exist: you could a) manually install any software dependencies yourself, *or* b) use the unit-specific Vagrant<sup>b</sup> box by following instructions at

### https://www.github.com/danpage/COMS20001/blob/COMS20001\_2019/vagrant/README.md

- We intend the worksheet to be attempted, at least partially, in the lab. slot. Your attendance is important, because the lab. slot represents a primary source of formative feedback and help. Note that, perhaps more so than in units from earlier years, *you* need to actively ask questions of and/or seek help from the lectures and/or lab. demonstrators present.
- The questions are roughly classified as either C (for core questions, that *should* be attempted within the lab. slot), A (for additional questions, that *could* be attempted within the lab. slot), or R (for revision questions, that support preparation for any viva and/or exam). Keep in mind that we only *expect* you to attempt the first class of questions: the additional content has been provided *purely* for your benefit and/or interest, so there is no problem with nor penalty for totally ignoring it (since it is not directly assessed).

<sup>&</sup>lt;sup>a</sup>The implication here is that such alternatives are provided in a best-effort attempt to help you: they are experimental, and so *no* guarantees about nor support for their use will be offered.

b https://www.vagrantup.com

# COMS20001 lab. worksheet #3

Before you start work, download (and, if need be, unarchive<sup>a</sup>) the file

http://tinyurl.com/y2fxztqv/csdsp/os/sheet/lab-3\_q.tar.gz

somewhere secure<sup>b</sup> in your file system; from here on, we assume \${ARCHIVE} denotes a path to the resulting, unarchived content. The archive content is intended to act as a starting point for your work, and will be referred to in what follows.

"Use the gz and tar commands within a BASH shell (or prompt, e.g., a terminal window) or similar, or the archive manager GUI (available either via the menu Applications→Accessories→Archive Manager or by directly executing file-roller) if you prefer.

Q1[C]. This question develops a simple yet functioning operating system kernel, which is based on the concept of cooperative multi-tasking. The goal is to provide a concrete introduction to representation of processes, and, crucially, realisation of a basic context switching mechanism. Doing so requires support for system calls including yield, that allows a process to cooperatively yield control of the processor.

Note that although the lab. worksheet does conclude with a set of hands-on tasks and challenges, at this point they are intentionally biased towards reading and understanding the material (vs. more active alternatives, e.g., programming). It is *crucial* not to view this as optional effort: carefully working through the admittedly detailed content should allow you to more easily and rapidly engage with longer-term challenges (e.g., those relating to a given coursework assignment).

### Q1-§1 Explore the archive content

*Normally*, the kernel would be totally separate from any given user program: the idea is the kernel can dynamically retrieve a given program image from a storage medium (e.g., a disk), then use it to populate the address space (e.g., the text segment) of a user process to capture the state of execution. However, doing so is complex<sup>1</sup> in general and certainly *too* complex to consider at this stage. We therefore make some significant simplifications: throughout, we will

- a assume the entire system (i.e., the kernel *plus* any user programs) is statically compiled to form a single kernel image,
- b assume each such user program is executed exactly once (by the kernel, so automatically) and never terminates,
- c restrict the form of the user programs executed so they cannot make use of static or global<sup>2</sup> variables.


This implies a fairly limited remit for the kernel we will consider: it really only needs to a) include an appropriate process table that captures the state of execution (for each executed user program), and b) implement a context switch mechanism and scheduling algorithm so said processes can be suspended and resumed as need be. As Figure 1 illustrates, the content and structure of the archived material provided matches worksheet #2. The only difference is some additional files within the (previously empty) user directory: in line with the above, these are

- P1.[ch] and P2.[ch], which are definitions of user programs statically compiled into the kernel image,
- libc.[ch], which represents a (very limited) library against which the user programs are linked: it acts as a layer of abstraction that hides low-level interaction with the kernel (i.e., the detail of system calls) via two high-level, C wrapper functions.

<sup>&</sup>lt;sup>b</sup>For example, the Private sub-directory within your home directory (which, by default, cannot be read by third-parties).

<sup>&</sup>lt;sup>1</sup> Beyond the fact a storage medium must actually exist in the first place, note that the kernel would have to include components such as a) a file system, supported by an device driver, and b) a loader rich enough to understand appropriate executable and/or object file formats.

<sup>&</sup>lt;sup>2</sup> A technical justification for this in fact stems from the first simplification above. Consider a given user program; a static or global variable defined in said program will be located in the single data or bss segment in memory (depending whether it is initialised or uninitialised). Now imagine the user program is executed twice, yielding two independent processes. Each of the processes is executing the same user program, so access to the static or global variable will conflict: there is only one such variable, rather than one per process. Note that the analogous problem is easier to resolve with local variables, since they reside on the stack.



**Figure 1:** A diagrammatic description of the material in lab-3\_q.tar.gz.

```
SECTIONS {
      /* assign load address (per QEMU) */
10
                    0x70010000;
      /* place text segment(s)
       .text : { kernel/lolevel.o(.text) *(.text .rodata) }
13
      /* place data segment(s)
                                            *(.data
       .data : {
14
                                                            ) }
15
       /* place bss segment(s)
       .bss
                                            *(.bss
                                                            ) }
16
             : {
17
      /* align
                      address (per AAPCS)
18
              = ALIGN( 8 );
      /* allocate stack for svc mode
19
20
      . = . + 0x00001000;
tos_svc = .;
21
      /* allocate stack for P1
22
      . = . + 0x00001000;
tos_P1 = .;
23
24
25
26
27
28
      /* allocate stack for P2
      . = . + 0x00001000;
tos_P2 = .;
```

Figure 2: The linker script image. 1d.





Figure 3: A diagrammatic description of the memory layout realised by image.1d.



(a) Stack layout at function en- (b) Stack layout after sub (i.e., (c) Stack layout after stmia (i.e., (d) Stack layout after stmdb try point (i.e., Line #32). Line #33). Line #34). (i.e., Line #36).

**Figure 4:** An example showing how lolevel\_handler\_svc preserves the USR mode state on the SVC mode stack (Lines #33 to #36) ready for use by hilevel\_handler\_svc and then subsequent restoration (Lines #43 to #46). Note that the eventual value of sp is passed to the high-level interrupt handler hilevel\_handler\_svc as ctx: this allows it to manipulate the execution context preserved on the stack.

## Q1-§2 Understand the archive content

**image.1d**: **the linker script** Figure 2 illustrates the linker script image.1d. It controls how 1d produces the kernel image from object files, which, in turn, stem from compilation of the source code files; the resulting layout in memory is illustrated by Figure 3.

int.[sh]: low-level support functionality The header file int.h and source code int.s are essentially
identical to worksheet #2 (bar the specialisation to interrupt types handled), so we omit any discussion of them.

**lolevel.[sh]: low-level kernel functionality** All low-level, kernel-specific functionality is captured by the header file lolevel.h and source code lolevel.s: the latter is subtly, but *significantly* more complex than similar files in previous worksheets. This complexity stems from the fact that when an interrupt occurs, we now expect a *user* mode process to be executing. As a result, the execution context must be a) preserved at the interrupt handler entry point, and b) restored at the interrupt handler exit point. These differences are limited to the top part, and so the two functions outlined below:

- lolevel\_handler\_svc can be viewed as three parts:
  - a 5-instruction prologue,
  - invocation of hilevel\_handler\_svc, the high-level, C interrupt handler defined in hilevel.c, and
  - a 5-instruction epilogue.

To understand how this works, imagine the processor is executing a user mode process (in USR mode) and executes an svc instruction. This requests a supervisor call interrupt, and causes <code>lolevel\_handler\_svc</code> to be invoked (with the processor now in SVC mode). The kernel must avoid corrupting the execution context associated with the user process, because otherwise would be impossible to resume (i.e., recommence execution of) the user process later. To see how a lack of care *could* cause problems, note that only certain registers are banked: the SVC mode <code>r0</code> register holds a value "owned" by USR mode, for example. So, it preserves said context on the SVC mode stack:

- Line #32 corrects the return address,
- Line #33 allocates space on the SVC mode stack for the execution context.

- Line #34<sup>3</sup> preserves USR mode r0 through to r12, plus sp (i.e., r13) and 1r (i.e., r14).
- Lines #35 and #36<sup>4</sup> preserve USR mode CPSR (which was copied into SVC mode SPSR by the interrupt), plus USR mode pc (which was copied into SVC mode 1r by the interrupt).

Figure 4 illustrates the stack content<sup>5</sup> at each step. With the USR mode execution context now preserved on the SVC mode stack, hilevel\_handler\_svc is invoked:

- Line #38 sets argument #0 equal to the SVC mode sp.
- Lines #39 and #40 set argument #1 equal to the 24-bit immediate value encoded in the svc instruction that requested the interrupt now being handled.
- Line #41 invokes hilevel\_handler\_svc with the arguments as specified above.

Since argument #0 is effectively a pointer to the preserved execution context, hilevel\_handler\_svc can use and/or update it as appropriate. However, in doing so it must consider one fact: whatever the preserved execution context contains once the function returns will always be restored by the epilogue in lolevel\_handler\_svc:

- Lines #43 and #44 restore USR mode CPSR into SVC mode SPSR, plus USR mode pc into SVC mode 1r.
- Line #45 restores USR mode r0 through to r12, plus sp (i.e., r13) and 1r (i.e., r14).
- Line #46 deallocates space on the SVC mode stack for the execution context.
- Line #47 returns control at the now restored program counter value held in SVC mode 1r; note that simultaneously, SVC mode SPSR is copied into USR mode CPSR which is what invokes the processor mode switch.
- lolevel\_handler\_rst is a lot easier to explain:
  - As with worksheet #2, Lines #16 to #19 initialise the interrupt vector table and SVC mode stack.
  - Lines #26 to #30 match the epilogue in lolevel\_handler\_svc, so restore an execution context from the SVC mode stack once hilevel\_handler\_rst returns.
  - Unlike lolevel\_handler\_svc, however, there is nothing sane to preserve because this interrupt
    relates to initialisation after reset: there can never be a currently executing user process at that point!
    As a result, Line #21 allocates the right amount of space on the SVC mode stack *for* an execution
    context, but does not fill it with anything.
  - Lines #23 and #24 invoke hilevel\_handler\_rst, with sp as an argument so the function can update
    the execution context: it *must* do so, otherwise the restoration steps in the epilogue will essentially
    just corrupt the register content.

It is vital to remember this implementation represents a trade-off in favour of simplicity, but at the expense of efficiency. For example, preserving the *entire* execution context on *every* interrupt allows for a clean and uniform separation between low- and high-level interrupt handlers, *but* could be inefficient if/when the same execution context is restored as preserved: in this case, we may have avoided the overhead of the former (and could do so, more easily at least, by writing more of the interrupt handler at a low-level where control over use of registers is easier and more explicit).

<sup>&</sup>lt;sup>3</sup>Note some niche, slightly cryptic syntax used here: the ^ denotes access to USR mode registers, even though it is being executed here in SVC mode; see, e.g., http://infocenter.arm.com/help/index.jsp?topic=/com.arm.doc.dui0489g/Cihcadda.html.

<sup>&</sup>lt;sup>4</sup>Note some niche, slightly cryptic syntax used here. The ! denotes a form of auto-indexed addressing mode, where the base address in sp (i.e., the old stack pointer) is updated to the address *after* those used to store r0 and lr (i.e., the new stack pointer); see, e.g., http://infocenter.arm.com/help/index.jsp?topic=/com.arm.doc.dui0489g/Cihcadda.html.

<sup>&</sup>lt;sup>5</sup> Although not specifically important here, it still makes sense to explain two subtleties wrt. preservation of the USR mode execution context. First, notice that we first decrement the stack pointer then store the USR mode registers in *ascending* order; you might ask why not omit the first step, storing them in descending order instead. The reason for this choice is that when ctx->gpr is used as an array, elements with a larger index are expected to have a higher address: ctx->gpr[1] should, for example, be at an address 4B higher than ctx->gpr[0]. The approach used satisfies precisely this requirement. Second, notice that we treat r11 as a general-purpose register; this assumes it is not being used as a frame pointer, which, per worksheet #1, we guaranteed by invoking GCC with the -fomit-frame-pointer flag. Within the coursework assignment this becomes important when implementing fork: when creating a new process the kernel has to initialise the stack pointer, but if the frame pointer is disabled then it be ignored (meaning the task of implementing fork is simpler than if the frame pointer were enabled).

**hilevel.[ch]:** high-level kernel functionality All high-level, kernel-specific functionality is captured by the header file hilevel.h and source code hilevel.c. When compared to previous worksheets, the former has some additional content which needs explanation:

- Line #42 define MAX\_PROCS, a fixed, maximum number of active user processes,
- Line #44 define a type pid\_t that captures an integer Process IDentifier (PID).
- Lines #46 to #55 define a type status\_t that captures the status of a user process; this would include whether or not it is currently executing, for example.
- Lines #57 to #59 define a type ctx\_t that captures an execution context (i.e., the processor state). In addition to noting that each pertinent component is present, keep in mind that ctx\_t uses a specific order for the components: reading the content from sp upward, it matches Figure 4 wrt. elements of said content. So if we have a pointer ctx of type ctx\_t\* equal to sp, we can access the preserved execution context using (high-level) field in ctx (rather than via an unstructured, low-level offset from sp).
- Lines #61 to #66 define a type pcb\_t that captures a Process Control Block (PCB), instances of which form entries in the process table: given the limited remit here, each such entry includes only a PID and execution context.

These definitions are used by the latter, which implements the kernel itself in what can be viewed as two parts. The top part implements some support functionality:

- Line #20 defines a fixed-size array of pcb\_t instances that acts as a process table: there is an entry for each user process, with the current entry, i.e., the user process that is currently being executed<sup>6</sup>, indicated by the pointer executing.
- Lines #22 to #44 implement the function dispatch, which captures the dispatch operation: it suspends execution of the previous (or outgoing) process (that was executing) then resumes execution of the next (or incoming) process (that will be executed), thereby performing a context switch. In more detail, it a) preserves the execution context of the previous process (if there is one, i.e., if prev does not equal NULL), invoking memcpy to copy ctx into the associated PCB, b) restores the execution context of the next process (if there is one, i.e., if next does not equal NULL), invoking memcpy to copy the associated PCB into ctx, c) updates current, so it points at the executing user process.
- Lines #46 to #61 implement the function schedule, which captures the scheduling operation: it decides which process should resume execution. The implementation is particularly simple, a fact that stems from our assuming a fixed number of processes. execute. is (very) special-purpose: it just a) inspects current in order to determine which process is currently executing, b) uses dispatch to perform a context switch, and so resume execution of the *other* process, updating the status of each process to match.

The bottom part implements two high-level interrupt handler functions, which use the support functionality outlined above:

- hilevel\_handler\_rst is invoked by lolevel\_handler\_rst every time a reset interrupt is requested and needs to be handled.
  - Lines #73 to #75 initialises the process table, ensuring that each entry is marked as invalid, i.e., not representing an active process.
  - Lines #85 to #91 and Lines #93 to #9 automatically execute the user programs P1 and P2 by setting
    fields in a PCBs for each resulting process; in each case the PCB is first zero'ed by memset, then fields
    such as the program counter are set (to the address of the entry point, e.g., main\_P1).
  - Line #106 then selects a PCB entry (in this case the 0-th entry), and activate it. Note that the specific value<sup>7</sup> used to initialise CPSR means each process will execute in USR mode, with IRQ interrupts enabled. As such, there is no explicit call to int\_enable\_irq (as was required in worksheet #2 for example).

<sup>&</sup>lt;sup>6</sup> Although we continue to use it, the term "currently executing" needs some care. For example, if the kernel is executing as the result of an interrupt, by definition there cannot *also* be a user process "currently executing". What we mean by this is the user process whose execution context was in use at the point said interrupt occurred, and so was preserved in cxt by the interrupt handler. Put another way, *it* is the user process that was interrupted.

 $<sup>^{7}</sup>$ Using the literal  $50_{(16)}$  implies that CPSR[M] =  $10000_{(2)}$ , CPSR[F] =  $1_{(2)}$ , and CPSR[I] =  $0_{(2)}$ , i.e., USR mode, with FIQ interrupts disabled and IRQ interrupts enabled.

- hilevel\_handler\_svc is invoked by lolevel\_handler\_svc every time a software interrupt is requested and needs to be handled. Recall that it is passed two arguments, namely
  - a pointer to the preserved execution context (on the SVC mode stack, i.e., the value of sp), and
  - the immediate operand of the svc instruction that requested the interrupt being handled: this is used as the system call identifier.

The function uses the system call identifier to decide how the interrupt should be handled, and so what the kernel-facing side of the system call API should do:

- Lines #121 to #125 deal with identifier 00<sub>(16)</sub>, i.e., the yield system call: when one of the user processes invokes yield as defined in libc.c, the resulting supervisor call interrupt is eventually handled by this case. The semantics of this system call are that the process scheduler should be invoked, i.e., that the currently executing user process has yielded control of the processor (thus permitting the other to execute).
- Lines #127 to #139 deal with identifier 01<sub>(16)</sub>, i.e., the write system call: when one of the user processes invokes write as defined in libc.c, the resulting supervisor call interrupt is eventually handled by this case. The semantics of this system call are that some n-element sequence of bytes pointed to by x are written to file descriptor fd; the kernel ignores fd, and simply writes those bytes to the PL011\_t instance UARTO.

Note that not *all* potential system calls are handled by this kernel, but adding additional cases is simply a matter of following the same approach as the above.

**libc.[ch]:** the user mode library The header file libc.h and source code libc.c. capture the user-facing side of the system call API. Put another way, we described the *kernel*-facing side (i.e., *implementation*) above; libc.h and libc.c support use of that implementation, providing a more appropriate level of abstraction by wrapping raw, low-level svc instructions in high(er)-level functions. These wrappers abstract (at least) two details:

• To specifically execute an svc instruction, we need to use assembly language: the C language has no native support for such low-level concepts. To do so, as hinted in worksheet #1, we harness inline assembly language to combine C and assembly language (in particular, variables in the former can be used in the latter). Resources such as

#### http://wiki.osdev.org/Inline\_Assembly

provide an introduction, but, briefly, you can consider each function as being

- a top part which is an assembly language template (e.g., with place-holders such as %0 akin to those used in printf) "filled in" by the compiler using the stated inputs and outputs,
- a (potentially empty) list of outputs referring to C variables,
- a (potentially empty) list of inputs, referring to C variables (or constants),
- a (potentially empty) list of registers that are "clobbered" (or changed) within the template; the
  rationale for this list, at a high level, is to communicate any hidden impact of the template to the
  compiler (e.g., a change to some register is would otherwise assume remains the same after as before
  the template).
- The user-facing side of the system call API must adhere to the calling convention. Various choices exist: here we opt to use the svc instruction itself to communicate a system call identifier, with arguments and return values communicated via the first four general-purpose registers (much like a function call).

**P[12].[ch]:** the user mode programs The header file P1.h and source code P1.c capture user program #1, and similarly for P2.h and P2.c. The purpose (and thus form) of both user programs is intentionally simple, which is evident by using P1.c as an example:

- Lines #11 to #13 implement an infinite while loop, which implies that the function never returns. Each iteration makes two system calls, namely
  - a call to write that instructs the kernel to write a string to the file descriptor STDOUT\_FILENO; per the above, this is interpreted as transmitting it via the PL011\_t instance UARTO as a form of standard output stream, and

- a call to yield that instructs the kernel to invoke the scheduler: per the above this means a context switch occurs.
- Line #15 performs an exit system call. Although the kernel has no associated implementation yet, it does so for completeness: a normal program<sup>8</sup> would call exit to terminate the associated process, although the while loop described above means control-flow never reaches *this* call.

## Q1-§3 Experiment with the archive content

Following the same approach as worksheet #1, first launch QEMU. Next, launch gdb and issue the

#### continue

command in the debugging terminal so the kernel image is executed. You should observe the two strings "P1" and "P2" being written alternately to the emulation terminal, interspersed with some debugging output from the dispatch function to indicate which user process is being preserved and restored.

At an intuitive level, the behaviour of this kernel is easy to summarise. It should be clear that when the processor is reset, each of the two user programs are (automatically) executed and form associated processes. Over time, the processor is shared between said processes; this is achieved by the kernel switching between them when the process currently executing (cooperatively) relinquishes control via the yield system call. Each process does so, using the write system call to identify itself beforehand (so as to *demonstrate* it is executing), meaning the result is a sequence of identifier strings written to the emulator terminal as observed.

## Q1-§4 Next steps

There are various things you could (optionally) do next: here are some ideas.

- a An effective way to gain insight into an example of this type, in which the timing of events is crucial, is by drawing a time-line to illustrate said events. For example, by including a) when events (e.g., interrupts) occur, b) what the processor and memory (e.g., stack) state is, and c) what instructions (i.e., what function) is being executed at different periods of time, one can align the observed behaviour with the source code. Try to construct such a diagram for this example, limiting the duration to the first three context switches at most.
- b Add an *additional*, third user program: initially this could be more or less identical to the other two, but the goal would be to explore questions like
  - i what happens if it behaves in a semi-cooperative (i.e., does invoke yield, just less often than the other two user programs) or non-cooperative (i.e., does not invoke yield) manner, or
  - ii whether/how the new user program can exploit the lack of protection implemented by this kernel, and what behaviour might result when it does so.
- c Add an *additional* system call by updating both to the user- and kernel-facing side of the system call API. A good candidate is read, since this acts as the natural counterpart to write by allowing processes to read bytes from the emulated UART.
- d As outlined above, there are various possible choices wrt. design of the system call API: investigate how system call invocation is implemented in Linux, then alter the implementation used by this kernel to match. Having done so, what can you say about potential advantages or disadvantages of the different design choices?

## Q2[A]. Consider this quote

One process wrote A, the other wrote B, so I saw AAAA, BBBB, and so on [1].

This *should* sound somewhat familiar. Who said it? Linus Torvalds. What was the context? Early development of Linux. So, put another way, from the previous question you have a starting point *more or less* equivalent to a *very* early, prototypical Linux!

The history of Linux is interesting, and there are numerous sources that offer an overview; the Wired interview [1] from which the quote above was taken is one, early example. Absorbing this history is arguably time well spent, whether you do so in depth or not:

<sup>&</sup>lt;sup>8</sup>From the programmers perspective, the entry point for a normal C program is the main function. However, main is called from and returns to a wrapper called \_start (or similar): although it *looks* like main lacks a call to exit, this is actually performed implicitly by \_start.

- lessons learned from how *it* developed *can* be applied in your own work (in this, and other units), and, perhaps more importantly,
- it should offer motivation: although *obviously* challenging for a variety of reasons, you can take stock after the first 3 weeks of the unit and be confident the outcome is already of *real* value and relevance.

## Q3[A]. There is a fantastic short film at

### http://www.youtube.com/watch?v=Q07PhW5sCEk

focusing on the Compatible Time-Sharing System (CTTS), developed at MIT in the early 1960s. CTTS was *highly* influential in terms of later technology: a range of subsequent systems such as Multics and UNIX refined concepts and approaches *it* pioneered. However, the film is arguably more remarkable because a) it offers such a brilliant explanation of what, at the time, was a revolutionary concept, and b) gives an insight into the challenges faced by computing in that era: it neatly illustrates the cost associated with maintaining one computer, for example, and so the value in maximising utilisation of it!

## References

[1] G. Moody. The Greatest OS That (N)ever Was. 1997. url: http://www.wired.com/1997/08/linux-5 (see p. 8).