

Strawberry Jam



Water bath canning - Beginner

INGREDIENTS

- 2 quarts crushed strawberries
- 6 cups sugar

INSTRUCTIONS

Sterilize canning jars. Combine berries and sugar; bring slowly to boiling, stirring occasionally until sugar dissolves. Cook rapidly until thick, about 40 minutes. As mixture thickens, stir frequently to prevent sticking. Pour hot jam into hot jars, leaving 1/4-inch headspace. Wipe jar rims and adjust lids. Process using table below.

Style of Pack

Jar Size

0 - 1,000 ft

1,001 - 6,000 ft

Above 6,000 ft

Hot Half-pints or Pints

5 min

10

15

After processing, take canner off heat. Remove lid. Wait 5 minutes before removing jars.

In season (Willamette Valley): June to July

Headspace 1/4 inch | Process 5 minutes at 0-1,000 ft, 10 minutes at 1,001-6,000 ft, 15 minutes above 6,000 ft | Yield about 8 half-pint jars

Source: SP 50-777 Jams jellies preserves with no added pectin, Revised January 2025, p. 3

This recipe has been tested for safety by SP 50-777 Jams jellies preserves with no added pectin. Always follow tested recipes exactly. Do not alter ingredients, proportions, or processing times.

Tomato Salsa (using slicing tomatoes)



Water bath canning - Intermediate

INGREDIENTS

- 4 cups peeled, cored, chopped slicing tomatoes
- 2 cups seeded, chopped long green chiles
- 1/2 cup seeded, chopped jalapeño peppers
- 3/4 cup chopped onions
- 4 cloves garlic, finely chopped
- 2 cups vinegar (5% acid)
- 1 teaspoon ground cumin (optional)
- 1 tablespoon oregano leaves (optional)
- 1 tablespoon fresh cilantro (optional)
- 1 1/2 teaspoons salt

INSTRUCTIONS

Combine all ingredients in a large saucepan and bring to a boil, stirring frequently. Reduce heat and simmer 20 minutes, stirring occasionally. Ladle hot salsa into hot pint jars, leaving 1/2-inch headspace. Remove air bubbles and adjust headspace if needed. Wipe rims. Adjust lids and process in a boiling water canner 15 minutes at 0-1,000 feet altitude; 20 minutes at 1,001-6,000 feet; or 25 minutes above 6,000 feet.

In season (Willamette Valley): July through September (peak fresh tomato season)

Headspace 1/2-inch | Process 15 minutes at 0-1,000 feet altitude; 20 minutes at 1,001-6,000 feet; or 25 minutes above 6,000 feet | Yield 4 pints

Source: PNW 395 Salsa recipes for canning, p. 7

This recipe has been tested for safety by PNW 395 Salsa recipes for canning. Always follow tested recipes exactly. Do not alter ingredients, proportions, or processing times.

Reduced Sodium Sliced Dill Pickles



Water bath canning - Beginner

INGREDIENTS

4 lbs pickling cucumbers (3 to 5 inches)
6 cups vinegar (5%)
6 cups sugar
2 tbsp canning or pickling salt
1 1/2 tsp celery seed
1 1/2 tsp mustard seed
2 large onions, thinly sliced
8 heads fresh dill

INSTRUCTIONS

- Wash cucumbers and cut 1/16-inch slice off blossom end and discard.
- Cut cucumbers in 1/4-inch slices.
- Combine vinegar, sugar, salt, celery, and mustard seeds in large saucepan. Bring mixture to boiling.
- Place 2 slices of onion and 1/2 dill head on bottom of each pint jar.
- Fill jars with cucumber slices, leaving 1/2-inch headspace.
- Add 1 slice of onion and 1/2 dill head on top.
- Pour hot pickling solution over cucumbers, leaving 1/4-inch headspace.
- Adjust lids and process according to the recommendations in table below.

Recommended process time for Reduced-Sodium Sliced Dill Pickles in a boiling-water canner.

Process Time at Elevations of Style of Pack Jar Size

0 - 1,000 ft 1,001 - 6,000 ft Above 6,000 ft

Raw Pints 15 min 20 min 25 min

In season (Willamette Valley): June through August (typical Oregon cucumber seas
Headspace 1/4 inch headspace (pour hot pickling solution over cucumbers, leaving 1/4-inch headspace) | Process 15 minutes pint jars at 0-1,000 ft; 20 minutes at 1,001-6,000 ft; 25 minutes above 6,000 ft | Yield About 8 pints

Source: SP 50-533 Pickles for special diet, Revised December 2024, p. 2

This recipe has been tested for safety by SP 50-533 Pickles for special diet. Always follow tested recipes exactly. Do not alter ingredients, proportions, or processing times.

Canned peaches



Water bath canning - Beginner

INGREDIENTS

Peaches
Syrup, water, or juice
Ascorbic acid solution (optional for preventing darkening)

INSTRUCTIONS

1. Dip fruit in boiling water for 30 to 60 seconds until skins loosen. Dip quickly in cold water and slip off skins.
2. Cut in half, remove pits and slice if desired.
3. To prevent darkening, keep peeled fruit in ascorbic acid solution (1 teaspoon ascorbic acid powder per gallon of water OR crush and dissolve six 500-milligram vitamin C tablets per gallon of water). Drain.
4. Hot pack - In a large saucepan place drained fruit in syrup, water, or juice and bring to boil.
5. Fill jars with hot fruit and cooking liquid, leaving 1/2-inch headspace. Place halves in layers, cut side down.
6. Raw pack - Fill jars with raw fruit, cut side down, and add hot water, juice or syrup, leaving 1/2-inch headspace.
7. Adjust lids and rings.
8. Process in a boiling water canner.
9. After processing, take canner off heat. Remove lid and wait 5 minutes before removing jars.

In season (Willamette Valley): July to September

Headspace 1/2-inch | Process Recommended process time for Peaches, halved or sliced in a boiling-water canner:

Style of Pack | Jar Size | 0 - 1,000 ft | 1,001 - 3,000 ft | 3,001 - 6,000 ft | Above 6,000 ft

Source: SP 50-444 Preserving peaches, Revised July 2024, p. page 2

This recipe has been tested for safety by SP 50-444 Preserving peaches. Always follow tested recipes exactly. Do not alter ingredients, proportions, or processing times.

Whole or halved tomatoes, packed raw without added liquid



INGREDIENTS

Whole or halved ripe tomatoes
Acid (lemon juice or citric acid)
Salt (optional)

INSTRUCTIONS

1. Prepare tomatoes by dipping in boiling water for 30 to 60 seconds or until skins split. Dip in cold water and slip off skins. Remove cores.
2. Leave tomatoes whole or halve them.
3. Loosely fill jars with raw tomatoes, pressing until spaces fill with juice.
4. Leave 1/2 inch headspace.
5. Add acid: 2 tablespoons bottled lemon juice or 1/2 teaspoon citric acid per quart jar (half these amounts for pint jars).
6. If desired, add salt: 1/2 teaspoon per quart or 1/4 teaspoon per pint.
7. Adjust lids and process in a boiling water canner according to processing time and altitude (see below).

In season (Willamette Valley): August to September

Headspace 1/2 inch | Process Boiling water canner processing time for whole or halved tomatoes packed raw without added liquid:
Pint or Quart jars - 40 minutes at 0-1,000 ft altitude

Source: PNW 300 Canning tomatoes and tomato products, p. 10-11

This recipe has been tested for safety by PNW 300 Canning tomatoes and tomato products. Always follow tested recipes exactly. Do not alter ingredients, proportions, or processing times.

Green beans



Pressure canning - Beginner

INGREDIENTS

Wash beans and trim ends. Leave whole or cut into 1-inch pieces. Add salt, if desired (1/2 teaspoon per pint; 1 teaspoon per quart).

INSTRUCTIONS

1. Wash beans and trim ends.
2. Leave whole or cut into 1-inch pieces.
3. Use either the hot or raw pack method:
Hot Pack - Cover the beans with boiling water and boil for 5 minutes. Pack hot beans loosely in jars. Add salt if desired. Cover with boiling water, leaving 1 inch headspace. Remove air bubbles. Wipe rims, adjust lids, and process in a pressure canner at 240 deg F.
Raw Pack - Pack beans tightly into jars. Add salt if desired. Cover beans with boiling water, leaving 1 inch headspace. Remove air bubbles. Wipe rims, adjust lids, and process in a pressure canner at 240 deg F.
4. Process times: Pints for 20 minutes; quarts for 25 minutes.
5. After processing, take canner off heat, remove lid, and wait 5 minutes before removing jars.

In season (Willamette Valley): July through September

Headspace 1 inch | Process Pints for 20 minutes; quarts for 25 minutes at 240 deg F (10 pounds pressure weighted gauge or 11 pounds dial gauge). Wait 5 minutes before removing jars after processing. | Yield Approximately 11/2 to 21/2 pounds of beans per
Source: SP 50-445 Preserving green italian or wax beans, Revised February 2015, p. 1-2

This recipe has been tested for safety by SP 50-445 Preserving green italian or wax beans. Always follow tested recipes exactly. Do not alter ingredients, proportions, or processing times.

Canned Pears



Water bath canning - Beginner

INGREDIENTS

Pears
Sugar
Water

(For syrup proportions per 9-pint load: Very light syrup: 6 1/2 cups water, 3/4 cup sugar; Light syrup: 5 3/4 cups water, 1 1/2 cups sugar; Medium syrup: 5 1/4 cups water, 2 1/4 cups sugar; Heavy syrup: 5 cups water, 3 1/4 cups sugar)

INSTRUCTIONS

1. Mix sugar and water together in a large kettle. Bring to a boil.
2. Drain pears.
3. Hot pack - Drain pears, place into hot syrup and simmer 5 minutes or until pears are heated through.
4. Pack hot pears in jars and cover with boiling syrup, leaving 1/2 inch headspace.
5. Remove air bubbles by running a plastic spatula or bubbler between the jar and the fruit.
6. Wipe rims and adjust lids.
7. Process pints for 20 minutes in a boiling water canner; quarts 25 minutes.
8. After processing, take canner off heat. Remove lid and wait 5 minutes before removing jars.

Raw pack -

1. Drain fruit and pack raw into hot jars.
2. Cover with boiling syrup, leaving 1/2 inch headspace.
3. Remove air bubbles.
4. Wipe rims and adjust lids.
5. Process pints 25 minutes in a boiling water canner; quarts 30 minutes.
6. After processing, take canner off heat. Remove lid and wait 5 minutes before removing jars.

In season (Willamette Valley): August through October

Headspace 1/2 inch | Process Hot pack: Pints 20 minutes, Quarts 25 minutes. Raw pack: Pints 25 minutes, Quarts 30 minutes.

Altitude adjustments: Hot pack pints - 1,001 to 3,000 ft: 25 min; 3,001 to 6,000 ft: 30

Source: SP 50-678 Preserving pears, Revised May 2024, p. Page 2

This recipe has been tested for safety by SP 50-678 Preserving pears. Always follow tested recipes exactly. Do not alter ingredients, proportions, or processing times.

Bread-and-Butter Pickles



Water bath canning - Intermediate

INGREDIENTS

6 pounds pickling cucumbers (4- to 5-inch)
8 cups thinly sliced onions (about 3 pounds)
1/2 cup canning or pickling salt
Ice
4 cups vinegar (5% acidity)
4 1/2 cups sugar
2 Tablespoons mustard seed
1 1/2 Tablespoons celery seed
1 Tablespoon ground turmeric

INSTRUCTIONS

1. Wash cucumbers. Cut 1/16 inch off blossom end and discard. Cut into 3/16-inch slices.
2. Combine cucumbers and onions in a large bowl. Add salt. Cover with 2 inches crushed or cubed ice. Refrigerate 3 to 4 hours, adding more ice as needed.
3. Drain.
4. Combine remaining ingredients in a large pot. Boil 10 minutes.
5. Add cucumbers and onions to the vinegar solution and slowly reheat to boiling.
6. Fill hot pint or quart jars with slices and cooking syrup, leaving 1/2 inch headspace.
7. Remove air bubbles and adjust headspace if needed.
8. Adjust lids and process in a boiling water canner as follows or use the lower-temperature pasteurization treatment described above.
9. Hot pack processing times for Bread-and-Butter Pickles:
Altitude 0-1,000 ft: Pint 10 min.
1,001 - 6,000 ft: 15 min.
above 6,001 ft: 20 min.

In season (Willamette Valley): Summer (peak cucumber season June through August)

Headspace 1/2 inch | Process Altitude 0-1,000 ft: Pint 10 min; 1,001 - 6,000 ft: 15 min; above 6,001 ft: 20 min | Yield About 8 pints or 4 quarts

Source: PNW 355 Pickling vegetables, p. 12

This recipe has been tested for safety by PNW 355 Pickling vegetables. Always follow tested recipes exactly. Do not alter ingredients, proportions, or processing times.

Berry Jams (Blackberry, Blueberry, Boysenberry, Dewberry, Gooseberry, Loganberry, Raspberry,

Water bath canning - Beginner



INGREDIENTS

9 cups crushed berries
6 cups sugar

INSTRUCTIONS

1. Sterilize canning jars.
2. Combine berries and sugar.
3. Bring slowly to a boil, stirring occasionally until sugar dissolves.
4. Cook rapidly to, or almost to, gelling point, depending upon whether a firm or soft jam is desired.
5. As mixture thickens, stir frequently to prevent sticking.
6. Pour hot jam into hot jars, leaving 1/4 inch headspace.
7. Wipe jar rims.
8. Adjust lids.
9. Process in a boiling water canner.

In season (Willamette Valley): July to August

Headspace 1/4 inch | Process Process all jelled products in a boiling water canner. Process half pints and pints for 5 minutes (or time specified in recipe). | Yield 7 or 8 half-pint jars

Source: SP 50-777 Jams jellies preserves with no added pectin, Revised January 2025, p. 1

This recipe has been tested for safety by SP 50-777 Jams jellies preserves with no added pectin. Always follow tested recipes exactly. Do not alter ingredients, proportions, or processing times.

No Sugar Added Pickled Beets

Water bath canning - Intermediate



INGREDIENTS

7 lbs. of 2 - to 2 - 1/2 - inch diameter beets
4 to 6 onions (2 - to 2 - 1/2 - inch diameter), if desired
6 cups apple cider or white distilled vinegar (5%)
1 - 1/2 teaspoons canning or pickling salt
2 cups Splenda® (optional)
3 cups water
2 cinnamon sticks
12 whole cloves

INSTRUCTIONS

1. Wash and rinse pint canning jars; keep hot until ready to use. Prepare lids according to manufacturer's directions.
2. Trim off beet tops, leaving 1 inch of stem and roots to prevent bleeding of color. Wash thoroughly. Sort for size. Cover similar sizes together with boiling water and cook until tender (about 25 to 30 minutes). Caution: Drain and discard liquid.
3. Cool beets. Trim off roots and stems and slip off skins. Slice into 1/4 - inch slices. Peel, wash and thinly slice onions.
4. Combine vinegar, salt, Splenda®, and fresh water in large Dutch oven. Tie cinnamon sticks and cloves in cheesecloth bag and add to vinegar mixture. Bring to a boil. Add beets and onions. Simmer 5 minutes. Remove spice bag.
5. With a slotted spoon, fill hot beets and onion slices into clean, hot pint jars, leaving 1/2 - inch headspace. Cover with boiling hot vinegar solution, leaving 1/2 - inch headspace. Remove air bubbles and adjust headspace if needed. Wipe rims of jars with a dampened clean paper towel; apply two - piece metal canning lids.
6. Process in a boiling water canner according to the recommendations in the table below. Let cool, undisturbed, 12 to 24 hours and check for seals.

Recommended process time for No Sugar Added Pickled Beets in a boiling-water canner. (Hot pack)

Process Time at Altitudes of

Jar Size 0 - 1,000 ft 1,001 - 3,000 ft 3,001 - 6,000 ft Above 6,000 ft

Pints 30 minutes 35 minutes 40 minutes 45 minutes

In season (Willamette Valley): Late summer to early fall

Headspace 1/2 - inch | Process Pints: 30 minutes at 0 - 1,000 ft, 35 minutes at 1,001 - 3,000 ft, 40 minutes at 3,001 - 6,000 ft, 45 minutes at above 6,000 ft | Yield About 8 pints

Source: SP 50-533 Pickles for special diet, Revised December 2024, p. 4

This recipe has been tested for safety by SP 50-533 Pickles for special diet. Always follow tested recipes exactly. Do not alter ingredients, proportions, or processing times.

Canning Applesauce



Water bath canning - Beginner

INGREDIENTS

Apples
Sugar to taste
Water (small amount, if needed)

INSTRUCTIONS

1. Wash, peel and core apples. Peeling is especially important when making applesauce from windfalls. Applesauce made from unpeeled apples can result in a higher incidence of spoilage during storage.
2. Cut large fruit into slices.
3. Simmer until soft, adding a small amount of water to prevent sticking.
4. Put cooked apples through a food mill or strainer. Omit this step for chunky-style sauce.
5. Add sugar to taste.
6. Reheat applesauce to boiling and pack hot into jars, leaving 1/2 inch headspace.
7. Adjust lids and process in a boiling water canner according to the chart.
8. After processing, take canner off heat. Remove lid and wait 5 minutes before removing jars.

In season (Willamette Valley): Apples peak in late summer through fall (general)
Headspace 1/2 inch | Process Process time at elevations of Style of Pack Jar Size 0 - 1,000 ft 1,001 - 3,000 ft 3,001 - 6,000 ft Above 6,000 ft Hot Pints 15 min 20 20 25 Hot Quarts 20 25 30 35 | **Yield** Not specifically stated for applesauce, but related yield for
Source: SP 50-446 Preserving apples, p. 2

This recipe has been tested for safety by SP 50-446 Preserving apples. Always follow tested recipes exactly. Do not alter ingredients, proportions, or processing times.

Canned Tuna



Pressure canning - Intermediate

INGREDIENTS

Raw tuna
Optional: 1/2 teaspoon salt per pint or 1/4 teaspoon per half-pint
Optional: small pieces of belly fat
No added liquid or oil is necessary

INSTRUCTIONS

1. You may can tuna either raw or precooked. Precooking removes most of the oil that tends to have a strong flavor; however, many people find it easier to can the tuna raw in its own juices.
2. When you can raw tuna, it is easier to fillet the fish when it is partially frozen. You can skin raw tuna before or after filleting. It is not necessary to remove the viscera before filleting.
3. For either raw or precooked tuna, peel off the skin with a sharp knife. Scrape the surface lightly to remove blood vessels and any other discolored flesh.
4. Separate the fish into quarters by cutting meat away from the bones. Pull off and cut out all bones and fin bases. Scrape and cut out all the very dark flesh as this has a stronger flavor which can affect the delicate tuna flavor.
5. Cut fish loins crosswise with a sharp knife into lengths suitable for jars.
6. Pack pieces into hot half-pint or pint jars, pressing down gently to make a solid pack. A small piece of belly fat can be added to each jar to enhance the flavor and texture of the meat.
7. Salt or other spices are optional. Use 1/2 teaspoon salt per pint or 1/4 teaspoon per half-pint as a good flavor.
8. Leave 1 inch headspace between top of fish and jar. No added liquid or oil necessary.
9. Wipe the jar rims clean with a paper towel moistened with vinegar to remove any oil from the tuna before putting on the lid and rings.
10. Tighten rings snugly but do not overtighten to avoid buckling of lids during processing.
11. Process in a pressure canner following manufacturer's instructions. Exhaust steam for 10 minutes before pressurizing. Start timing when recommended pressure is reached. Maintain pressure and process for 100 minutes.
12. After processing, remove canner from heat and let pressure return to zero.
13. Remove weight or slowly open petcock. Wait 10 minutes before opening lid and removing jars.
14. Allow jars to sit undisturbed for 12 hours before testing seals.
15. Remove rings for storage. Store jars in a cool, dark, dry place. Use within one year for best quality.

In season (Willamette Valley): Late spring through early fall
Headspace 1 inch | Process 100 minutes
Process at 11 psi (dial gauge) or 10 psi (weighted gauge) at 0-2,000 ft altitude; increase pressure according to altitude:
Source: PNW 194 Canning seafood, p. 5-6

This recipe has been tested for safety by PNW 194 Canning seafood. Always follow tested recipes exactly. Do not alter ingredients, proportions, or processing times.