CS107, Lecture 3
Bits and Bytes; Bitwise Operators

reading:
Bryant & O'Hallaron, Ch. 2.1

Plan For Today

- **Recap**: Integer Representations
- Truncating and Expanding
- Bitwise Boolean Operators and Masks
- **Demo 1:** Courses
- **Break:** Announcements
- **Demo 2:** Powers of 2
- Bit Shift Operators

Plan For Today

- **Recap**: Integer Representations
- Truncating and Expanding
- Bitwise Boolean Operators and Masks
- **Demo 1:** Courses
- **Break:** Announcements
- **Demo 2:** Powers of 2
- Bit Shift Operators

Base 2

1	0	1	1
2^3	2^2	2^1	2^0

Hexadecimal

Hex digit	0	1	2	3	4	5	6	7
Decimal value	0	1	2	3	4	5	6	7
Binary value	0000	0001	0010	0011	0100	0101	0110	0111

Hex digit	8	9	A	B	C	D	E	F
Decimal value	8	9	10	11	12	13	14	15
Binary value	1000	1001	1010	1011	1100	1101	1110	1111

Number Representations

C declaration		Bytes	
Signed	Unsigned	32-bit	64-bit
[signed] char	unsigned char	1	1
short	unsigned short	2	2
int	unsigned	4	4
long	unsigned long	4	8
int32_t	uint32_t	4	4
int64_t	uint64_t	8	8
char *		4	8
float		4	4
double		8	8

Myth

Unsigned Integers



Signed Integers: Two's Complement

- In **two's complement**, we represent a positive number as **itself**, and its negative equivalent as the **two's complement of itself.**
- The **two's complement** of a number is the binary digits inverted, plus 1.
- This works to convert from positive to negative, **and** back from negative to positive!



Signed Integers: Two's Complement

- **Con:** more difficult to represent, and difficult to convert to/from decimal and between positive and negative.
- **Pro:** only 1 representation for 0!
- **Pro:** all bits are used to represent as many numbers as possible
- **Pro:** it turns out that the most significant bit *still indicates the sign* of a number.
- **Pro:** arithmetic is easy: we just add!



Overflow and Underflow

- If you exceed the **maximum** value of your bit representation, you *wrap around* or *overflow* back to the **smallest** bit representation.

```
0b1111 + 0b1 = 0b0000
```

- If you go below the **minimum** value of your bit representation, you *wrap around* or *underflow* back to the **largest** bit representation.

```
0b0000 - 0b1 = 0b1111
```

Min and Max Integer Values

Type	Width (bytes)	Width (bits)	Min in hex (name)	Max in hex (name)
char	1	8	80 (CHAR_MIN)	7F (CHAR_MAX)
unsigned char	1	8	0	FF (UCHAR_MAX)
short	2	16	8000 (SHRT_MIN)	7FFF (SHRT_MAX)
unsigned short	2	16	0	FFFF (USHRT_MAX)
int	4	32	80000000 (INT_MIN)	7FFFFFFF (INT_MAX)
unsigned int	4	32	0	FFFFFFFF (UINT_MAX)
long	8	64	8000000000000000 (LONG_MIN)	7FFFFFFFFFFFFFFF (LONG_MAX)
unsigned long	8	64	0	FFFFFFFFFFFFFFFF (ULONG_MAX)

Aside: ASCII

- ASCII is an encoding from common characters (letters, symbols, etc.) to bit representations (chars).
  - E.g. 'A’ is 0x41
- Neat property: all uppercase letters, and all lowercase letters, are sequentially represented!
  - E.g. 'B’ is 0x42

Unsigned Integers



Signed Numbers



Casting

- What happens at the byte level when we cast between variable types? **The bytes remain the same!** **This means they may be interpreted differently depending on the type.**

```
int v = -12345;
unsigned int uv = v;
printf("v = %d, uv = %u\n", v, uv);
```

The bit representation for -12345 is **`0b1100000000111001`.**

If we treat this binary representation as a positive number, it's *huge*!

Casting


0
1
2
3
4
5
6
7
-8
-7
-6
-5
-4
-3
-2
-1
0000
0001
0010
0011
0100
0101
0110
0111
1000
1001
1010
1011
1100
1101
1110
1111
4-bit
two's complement
signed integer
representation


0
1
2
3
4
5
6
7
8
9
10
11
12
13
14
15
0000
0001
0010
0011
0100
0101
0110
0111
1000
1001
1010
1011
1100
1101
1110
1111
4-bit
unsigned integer
representation

Comparisons Between Different Types

- **Be careful** when comparing signed and unsigned integers. **C will implicitly cast** the signed argument to unsigned, and then performs the operation assuming both numbers are non-negative.

Expression	Type	Evaluation	Correct?
`0 == 0U`			
`-1 < 0`			
`-1 < 0U`			
`2147483647 > -2147483647 - 1`			
`2147483647U > -2147483647 - 1`			
`2147483647 > (int)2147483648U`			
`-1 > -2`			
`(unsigned)-1 > -2`			



Comparisons Between Different Types

- **Be careful** when comparing signed and unsigned integers. **C will implicitly cast** the signed argument to unsigned, and then performs the operation assuming both numbers are non-negative.

Expression	Type	Evaluation	Correct?
`0 == 0U`	Unsigned	1	yes
`-1 < 0`	Signed	1	yes
`-1 < 0U`	Unsigned	0	No!
`2147483647 > -2147483647 - 1`	Signed	1	yes
`2147483647U > -2147483647 - 1`	Unsigned	0	No!
`2147483647 > (int)2147483648U`	Signed	1	No!
`-1 > -2`	Signed	1	yes
`(unsigned)-1 > -2`	Unsigned	1	yes



Comparisons Between Different Types

Which many of the following statements are true? (*assume that variables are set to values that place them in the spots shown*)

s3 > u3
u2 > u4
s2 > s4
s1 > s2
u1 > u2
s1 > u3



Comparisons Between Different Types

Which many of the following statements are true? (*assume that variables are set to values that place them in the spots shown*)

s3 > u3
u2 > u4
s2 > s4
s1 > s2
u1 > u2
s1 > u3



Comparisons Between Different Types

Which many of the following statements are true? (*assume that variables are set to values that place them in the spots shown*)

```
s3 > u3 - true
u2 > u4 - true
s2 > s4 - false
s1 > s2 - true
u1 > u2 - true
s1 > u3 - true
```



Plan For Today

- **Recap**: Integer Representations
- Truncating and Expanding
- Bitwise Boolean Operators and Masks
- **Demo 1:** Courses
- **Break:** Announcements
- **Demo 2:** Powers of 2
- Bit Shift Operators

Expanding Bit Representations

- Sometimes, we want to convert between two integers of different sizes (e.g. short to int, or int to long).
- We might not be able to convert from a bigger data type to a smaller data type, but we do want to always be able to convert from a **smaller** data type to a **bigger** data type.
- For **unsigned** values, we can add *leading zeros* to the representation ("zero extension")
- For **signed** values, we can *repeat the sign of the value* for new digits ("sign extension"
- Note: when doing <, >, <=, >= comparison between different size types, it will *promote to the larger type*.

Expanding Bit Representation

```
unsigned short s = 4;
// short is a 16-bit format, so                    s = 0000 0000 0000 0100b

unsigned int i = s;
// conversion to 32-bit int, so i = 0000 0000 0000 0000 0000 0000 0000 0100b
```

Expanding Bit Representation

```
short s = 4;
// short is a 16-bit format, so                          s = 0000 0000 0000 0100b

int i = s;
// conversion to 32-bit int, so i = 0000 0000 0000 0000 0000 0000 0000 0100b
```

— or —

```
short s = -4;
// short is a 16-bit format, so                          s = 1111 1111 1111 1100b

int i = s;
// conversion to 32-bit int, so i = 1111 1111 1111 1111 1111 1111 1111 1100b
```

Truncating Bit Representation

If we want to **reduce** the bit size of a number, C *truncates* the representation and discards the *more significant bits*.

```
int x = 53191;
short sx = x;
int y = sx;
```

What happens here? Let's look at the bits in x (a 32-bit int), 53191:

0000 0000 0000 0000 1100 1111 1100 0111

When we cast x to a short, it only has 16-bits, and C *truncates* the number:

1100 1111 1100 0111

This is -12345! And when we cast sx back an int, we sign-extend the number.

1111 1111 1111 1111 1100 1111 1100 0111 // still -12345

Truncating Bit Representation

If we want to **reduce** the bit size of a number, C *truncates* the representation and discards the *more significant bits*.

```
int x = -3;
short sx = x;
int y = sx;
```

What happens here? Let's look at the bits in x (a 32-bit int), -3:

1111 1111 1111 1111 1111 1111 1111 1101

When we cast x to a short, it only has 16-bits, and C *truncates* the number:

1111 1111 1111 1101

This is -3! **If the number does fit, it will convert fine.** y looks like this:

1111 1111 1111 1111 1111 1111 1111 1101 // still -3

Truncating Bit Representation

If we want to **reduce** the bit size of a number, C *truncates* the representation and discards the *more significant bits*.

```
unsigned int x = 128000;
unsigned short sx = x;
unsigned int y = sx;
```

What happens here? Let's look at the bits in x (a 32-bit unsigned int), 128000:

0000 0000 0000 0001 1111 0100 0000 0000

When we cast x to a short, it only has 16-bits, and C *truncates* the number:

1111 0100 0000 0000

This is 62464! **Unsigned numbers can lose info too.** Here is what y looks like:

0000 0000 0000 0000 1111 0100 0000 0000 // still 62464

The `sizeof` Operator

- **`sizeof`** takes a variable type as a parameter and returns the number of bytes that type uses.

```
printf("sizeof(char): %d\n", (int) sizeof(char));
printf("sizeof(short): %d\n", (int) sizeof(short));
printf("sizeof(int): %d\n", (int) sizeof(int));
printf("sizeof(unsigned int): %d\n", (int) sizeof(unsigned int));
printf("sizeof(long): %d\n", (int) sizeof(long));
printf("sizeof(long long): %d\n", (int) sizeof(long long));
printf("sizeof(size_t): %d\n", (int) sizeof(size_t));
printf("sizeof(void *): %d\n", (int) sizeof(void *));
```

```
$ ./sizeof
sizeof(char): 1
sizeof(short): 2
sizeof(int): 4
sizeof(unsigned int): 4
sizeof(long): 8
sizeof(long long): 8
sizeof(size_t): 8
sizeof(void *): 8
```

Type	Width in bytes	Width in bits
char	1	8
short	2	16
int	4	32
long	8	64
void *	8	64

Plan For Today

- **Recap**: Integer Representations
- Truncating and Expanding
- Bitwise Boolean Operators and Masks
- **Demo 1:** Courses
- **Break:** Announcements
- **Demo 2:** Powers of 2
- Bit Shift Operators

Bitwise Operators

- You're already familiar with many operators in C:
  - **Arithmetic operators:** +, -, *, /, %
  - **Comparison operators:** ==, !=, <, >, <=, >=
  - **Logical Operators**: &&, ||, !
- Today, we're introducing a new category of operators: **bitwise operators:**
  - &, |, ~, ^, <<, >>

And (&)

AND is a binary operator. The AND of 2 bits is 1 if both bits are 1, and 0 otherwise. **Note:** this is different from Boolean AND (&&)!

```
output = a & b;
```

a	b	output
0	0	0
0	1	0
1	0	0
1	1	1

Or (|)

OR is a binary operator. The OR of 2 bits is 1 if either (or both) bits is 1. **Note:** this is different from Boolean OR (||)!

```
output = a | b;
```

a	b	output
0	0	0
0	1	1
1	0	1
1	1	1

Not (~)

NOT is a unary operator. The NOT of a bit is 1 if the bit is 0, or 1 otherwise.
Note: this is different from Boolean NOT (!)!

```
output = ~a;
```

a	output
0	1
1	0

Exclusive Or (^)

Exclusive Or (XOR) is a binary operator. The XOR of 2 bits is 1 if *exactly* one of the bits is 1, or 0 otherwise.

```
output = a ^ b;
```

a	b	output
0	0	0
0	1	1
1	0	1
1	1	0

An Aside: Boolean Algebra

- These operators are not unique to computers; they are part of a general area called **Boolean Algebra**, and are called **Boolean Operators**. These are applicable in math, hardware, computers, and more!



a	y
0	1
1	0

a	b	y
0	0	0
0	1	0
1	0	0
1	1	1

a	b	y
0	0	0
0	1	1
1	0	1
1	1	1

a	b	y
0	0	0
0	1	1
1	0	1
1	1	0

Operators on Multiple Bits

- When these Boolean operators are applied to numbers (multiple bits), the operator is applied to the corresponding bits in each number. For example:

AND

```
  0110
& 1100
  ----
  0100
```

OR

```
  0110
| 1100
  ----
  1110
```

XOR

```
  0110
^ 1100
  ----
  1010
```

NOT

```
~ 1100
  ----
  0011
```

Bit Vectors and Sets

- We can use bit vectors (ordered collections of bits) to represent finite sets, and perform functions such as union, intersection, and complement.
- **Example:** we can represent current courses taken using a **`char`**.



Bit Vectors and Sets



- How do we find the union of two sets of courses taken? Use OR:

```
  00100011
| 01100001
  --------
  01100011
```

Bit Vectors and Sets



- How do we find the intersection of two sets of courses taken? Use AND:

```
  00100011
& 01100001
  --------
  00100001
```

Bit Masking

- We will frequently want to manipulate or isolate out specific bits in a larger collection of bits. A **bitmask** is a constructed bit pattern that we can use, along with bit operators, to do this.
- **Example:** how do we update our bit vector to indicate we've taken CS107?




```
  00100011
| 00001000
----------
  00101011
```

Bit Masking

```
enum Classes {
    CS106A = 0x1,     /* 0000 0001 */
    CS106B = 0x2,     /* 0000 0010 */
    CS106X = 0x4,     /* 0000 0100 */
    CS107  = 0x8,     /* 0000 1000 */
    CS110  = 0x10,    /* 0001 0000 */
    CS103  = 0x20,    /* 0010 0000 */
    CS109  = 0x40,    /* 0100 0000 */
    CS161  = 0x80,    /* 1000 0000 */
};

char myClasses = ...;
myClasses = myClasses | CS107;   // Add CS107
```

Bit Masking

```
enum Classes {
    CS106A = 0x1,     /* 0000 0001 */
    CS106B = 0x2,     /* 0000 0010 */
    CS106X = 0x4,     /* 0000 0100 */
    CS107  = 0x8,     /* 0000 1000 */
    CS110  = 0x10,    /* 0001 0000 */
    CS103  = 0x20,    /* 0010 0000 */
    CS109  = 0x40,    /* 0100 0000 */
    CS161  = 0x80,    /* 1000 0000 */
};

char myClasses = ...;
myClasses |= CS107;     // Add CS107
```

Bit Masking

- **Example:** how do we update our bit vector to indicate we've *not* taken CS103?




```
  00100011
& 11011111
  --------
  00000011
```

```
char myClasses = ...;
myClasses = myClasses & ~CS103;  // Remove CS103
```

Bit Masking

- **Example:** how do we update our bit vector to indicate we've *not* taken CS103?




```
  00100011
& 11011111
  --------
  00000011
```

```
char myClasses = ...;
myClasses &= ~CS103;    // Remove CS103
```

Bit Masking

- **Example:** how do we check if we've taken CS106B?




```
  00100011
& 00000010
  --------
  00000010
```

```
char myClasses = ...;
if (myClasses & CS106B) {...
    // taken CS106B!
```

Bit Masking

- **Example:** how do we check if we've *not* taken CS107?




```
char myClasses = ...;
if ((myClasses & CS107) ^ CS107) {...
     // not taken CS107!
```

Bit Masking

- **Example:** how do we check if we've *not* taken CS107?




```
char myClasses = ...;
if (!(myClasses & CS107)) {...
     // not taken CS107!
```

Demo: Bitmasks and GDB

Bit Masking

- Bit masking is also useful for integer representations as well. For instance, we might want to check the value of the most-significant bit, or just one of the middle bytes.

- **Example:** If I have a 32-bit integer **`j`**, what operation should I perform if I want to get *just the lowest byte* in **`j`**?

```
int j = ...;
int k = j & 0xff;          // mask to get just lowest byte
```

Practice: Bit Masking

- **Practice 1:** write an expression that, given a 32-bit integer j, sets its least-significant byte to all 1s, but preserves all other bytes.

- **Practice 2:** write an expression that, given a 32-bit integer j, flips ("complements") all but the least-significant byte, and preserves all other bytes.

Practice: Bit Masking

- **Practice 1:** write an expression that, given a 32-bit integer j, sets its least-significant byte to all 1s, but preserves all other bytes.

```
j | 0xff
```

- **Practice 2:** write an expression that, given a 32-bit integer j, flips ("complements") all but the least-significant byte, and preserves all other bytes.

```
j ^ ~0xff
```

Plan For Today

- **Recap**: Integer Representations
- Truncating and Expanding
- Bitwise Boolean Operators and Masks
- **Demo 1:** Courses
- **Break:** Announcements
- **Demo 2:** Powers of 2
- Bit Shift Operators

Announcements

- Office Hours Updates – Nick's OH location, Fri time, and future 1-time adjustments. *See office hours calendar!*
- Please send us any OAE letters or athletics conflicts as soon as possible. Thanks!
- Assignment 0 deadline tonight at 11:59PM PST
- Assignment 1 (Bit operations!) goes out tonight at Assignment 0 deadline
  - Saturated arithmetic
  - Game of Life
  - Unicode and UTF-8
- Lab 1 this week!

Demo: Powers of 2

Plan For Today

- **Recap**: Integer Representations
- Truncating and Expanding
- Bitwise Boolean Operators and Masks
- **Demo 1:** Courses
- **Break:** Announcements
- **Demo 2:** Powers of 2
- Bit Shift Operators

Left Shift (<<)

The LEFT SHIFT operator shifts a bit pattern a certain number of positions to the left. New lower order bits are filled in with 0s, and bits shifted off of the end are lost.

```
x << k;     // shifts x to the left by k bits
```

8-bit examples:

```
00110111 << 2 results in 11011100
01100011 << 4 results in 00110000
10010101 << 4 results in 01010000
```

Right Shift (>>)

The RIGHT SHIFT operator shifts a bit pattern a certain number of positions to the right. Bits shifted off of the end are lost.

```
x >> k;    // shifts x to the right by k bits
```

Question: how should we fill in new higher-order bits?

Idea: let's follow left-shift and fill with 0s.

```
short x = 2;  // 0000 0000 0000 0010
x >> 1;       // 0000 0000 0000 0001
printf("%d\n", x); // 1
```

Right Shift (>>)

The RIGHT SHIFT operator shifts a bit pattern a certain number of positions to the right. Bits shifted off of the end are lost.

```
x >> k;    // shifts x to the right by k bits
```

Question: how should we fill in new higher-order bits?

Idea: let's follow left-shift and fill with 0s.

```
short x = -2; // 1111 1111 1111 1110
x >> 1;       // 0111 1111 1111 1111
printf("%d\n", x); // 32767!
```

Right Shift (>>)

The RIGHT SHIFT operator shifts a bit pattern a certain number of positions to the right. Bits shifted off of the end are lost.

```
x >> k;     // shifts x to the right by k bits
```

Question: how should we fill in new higher-order bits?

Problem: always filling with zeros means we may change the sign bit.

Solution: let's fill with the sign bit!

Right Shift (>>)

The RIGHT SHIFT operator shifts a bit pattern a certain number of positions to the right. Bits shifted off of the end are lost.

```
x >> k;     // shifts x to the right by k bits
```

Question: how should we fill in new higher-order bits?

Solution: let's fill with the sign bit!

```
short x = 2;   // 0000 0000 0000 0010
x >> 1;        // 0000 0000 0000 0001
printf("%d\n", x); // 1
```

Right Shift (>>)

The RIGHT SHIFT operator shifts a bit pattern a certain number of positions to the right. Bits shifted off of the end are lost.

```
x >> k;     // shifts x to the right by k bits
```

Question: how should we fill in new higher-order bits?

Solution: let's fill with the sign bit!

```
short x = -2; // 1111 1111 1111 1110
x >> 1;       // 1111 1111 1111 1111
printf("%d\n", x); // -1!
```

Right Shift (>>)

There are *two kinds* of right shifts, depending on the value and type you are shifting:

- **Logical Right Shift:** fill new high-order bits with 0s.
- **Arithmetic Right Shift:** fill new high-order bits with the most-significant bit.

Unsigned numbers are right-shifted using **Logical Right Shift**.

Signed numbers are right-shifted using **Arithmetic Right Shift.**

This way, the sign of the number (if applicable) is preserved!

Shift Operation Pitfalls

1. *Technically*, the C standard does not precisely define whether a right shift for signed integers is logical or arithmetic. However, a**lmost all compilers/machines** use arithmetic, and you can most likely assume this.
2. Operator precedence can be tricky! For example:

   `1<<2 + 3<<4` means `1 << (2+3) << 4` because addition and subtraction have higher precedence than shifts! Always use parentheses to be sure:

   ```
   (1<<2) + (3<<4)
   ```

Recap

- **Recap**: Integer Representations
- Truncating and Expanding
- Bitwise Boolean Operators and Masks
- **Demo 1:** Courses
- **Break:** Announcements
- **Demo 2:** Powers of 2
- Bit Shift Operators

Next time: C strings