JODA POS

User manual

English

Contents

GETTING STARTED

Sign in
Enter the two-factor authentication code
Create your store
Understand roles
Find your way in Admin
Choose the language
Notifications
Using help
Forgot your password

TILL

The till screen
The till on a phone
Till keyboard shortcuts
Add products and manage the cart
Sell a product by weight
Choose the customer and the salesperson
Discounts and promo codes at the till
Customer group prices and discount
Change a price at the till
Get a manager to approve an action
Charge: the payment screen
Cash in dollars or gourdes and giving change
Pay by card, MonCash, or bank transfer
Pay with loyalty points
Sell and redeem a gift card
Sale on account (credit) and customer store credit
Give the receipt (print, email, link)
Hold a cart and resume it
The customer display
Take an order with a deposit and hand it over

SHIFTS

Open a shift
Paid in, paid out, safe drops and opening the drawer
Close the shift, count the drawer and print the Z-report
Track register shifts (managers)
Denominations, business day and shift corrections

RETURNS AND VOIDS

Process a return and refund the customer
Make an exchange
Give a goodwill refund
Track returns in the admin area
Void a sale

OFFLINE

Selling offline
Uploading offline sales when the connection returns

SALES AND EXPENSES

The dashboard
Sales history, reprinting and sending the receipt
Create an estimate and convert it into a sale
Record an expense
Approve, reject and pay an expense
Reconcile card settlements
The review queue
Follow orders and their deposits

REPORTS

Open and read a report
Export a report (CSV, Excel, PDF)
Reconciliation and daily summary

CATALOG

The product list and labels
Create or edit a product
Variants, attributes and barcodes
Units and products sold by weight
Organize categories
Import products (Excel or CSV)
Price lists
Tax categories
Create a discount or promo code

INVENTORY

View stock and spot low stock
Receive stock without a purchase order
Correct stock, view movements and check stock
Transfer stock between locations
Do a stock count
Stock aging and valuation

PURCHASING
Manage suppliers
Create a purchase order and get it approved
Receive a supplier delivery
Record a supplier invoice
Pay a supplier and track payables
Return goods to a supplier
Prepare a reorder

CUSTOMERS
Find and create a customer
The customer profile (notes, addresses, custom fields)
Adjust a customer's loyalty points
Customer credit accounts and payments
Customer groups
Merge duplicate customers
Gift cards and store credit (admin)
Anonymise a customer (right to erasure)

STAFF
Manage employees
Time clock and attendance
Add or invite a user
Edit or suspend a user, or reset their password
Roles and permissions

SETTINGS
General store settings
The USD / HTG exchange rate
Business information and logo
Receipts and printing
Branches, registers and sale numbering
Warehouses and stock locations
Tax rates
The loyalty program
Payment methods
Offline and security
Schedule a change and view the history
Scale labels (weighed items)

HARDWARE AND SYSTEM
Hardware: printer, cash drawer and scanner
Devices (registered tills)
The audit log
System events

MY ACCOUNT

Account security, password and sessions
Turn on two-factor authentication (2FA)
Invitations and switching stores


FAQ

FAQ: at the till
FAQ: offline
Account locked, forgotten password, access denied
FAQ: sales and currencies
FAQ: printer and cash drawer
FAQ: reports and exports
Why is a date rejected?

Getting started

Sign in

Each employee has their own account: an email address and a password. Never share your account: every sale, every discount and every drawer opening is recorded under your name.



Sign-in page in English

1. Open the app's address in the browser (Chrome is best).
2. At the top right, click **EN** to show the app in English.
3. Enter your address in the **Email** field.
4. Enter your password in the **Password** field.
5. Click **Sign in**.

Forgot your password? Click **Forgot password?** next to **Password** (see Forgot your password).

If two-factor authentication is turned on for your account, the app then asks for a 6-digit code (see Enter the two-factor authentication code).

Where do you land after signing in?

Role	Landing page
Cashier, manager, administrator, owner	The till screen. The **Admin** button opens store management.
Accountant	The admin **Dashboard** (accountants do not sell).
Stock clerk	The admin **Inventory** (stock clerks do not sell).

You stay signed in on this device thanks to a secure cookie: you do not need to sign in again each time you open the app. Click **Sign out** before handing the device to a coworker.

Error messages

- **Invalid credentials**: the address or the password is wrong. Check what you typed (Caps Lock key) and try again.
- **Too many failed attempts. This account is locked for a few minutes.**: after 5 wrong tries in a row, the account is locked for 15 minutes. See Account locked or forgotten password.
- **Too many attempts. Wait a few minutes and try again.**: too many sign-ins from this device in a short time. Wait a little.
- **This user is already signed in on another device**: an account can only be signed in on one device at a time. The message names the other device and its last activity. Sign out on that device first, or ask a manager to disconnect you (see Disconnect a user). A device left unused for 15 minutes no longer blocks the sign-in: it is signed out when you sign in here.

⚠ **Warning:** each new wrong try during the lock extends it. Wait without trying again.

Tip: if the link **New here? Create a store** appears under the form, this server lets you create a new store (see Create your store).

Enter the two-factor authentication code

Two-factor authentication protects an account with a 6-digit code. This code changes every 30 seconds in an app on your phone (Google Authenticator, Microsoft Authenticator, 1Password...).

If it is turned on for your account, the **Two-Factor Authentication** screen appears after the password:

1. Open the authenticator app on your phone.
2. Read the 6-digit code shown for your account.
3. Enter it in the **Verification Code** field.
4. Click **Verify**.
5. If something goes wrong, click **Back to Login** to start over.


> **Tip:** if the message **Invalid verification code** appears, check that the phone's time is correct: a phone that is running late produces wrong codes. A code works only once: wait for the next one if you just used it.

> **Warning:** wrong codes count as login attempts. After 5 errors in a row, the account is locked for 15 minutes.

The store can require two-factor authentication for people who manage users, roles, settings, or the audit log. In that case, the app sends you to **Account security** to turn it on before doing anything else (see Turn on two-factor authentication).

Create your store

On some servers, the sign-in page offers **New here? Create a store.** This page creates a new store and makes you its **Owner**.



Create a store page

1. On the sign-in page, click **Create a store**.
2. Enter the **Store name**.
3. Enter your **First name**, **Last name**, **Email** and a **Password** (at least 8 characters).
4. Check the main **Currency** (3-letter code, for example USD or HTG).
5. Click **Create store**.

The app sets up a branch, a register and the Cash and Card payment methods for you. You then land in the app, signed in as the owner.

> **Tip:** if you already have an account (in another store), enter the same email and password: the new store is added to your account. If that account uses two-factor authentication, the code is requested. You can then switch from one store to another in **Account security** (see Invitations and switching stores).

> **Warning:** if the message "Sign-up is not available on this server. Ask your administrator for an account." appears, store creation is closed. Ask your administrator for an account.

Recommended next steps:

1. Fill in the General settings and the Business information.
2. Check the exchange rate.
3. Create your products or import them.
4. Add your staff.

Understand roles

Each user is given a role. The role decides which menus are visible and which actions are allowed. Roles can be viewed in **Admin** > **Roles & permissions** (owner and administrator).

Role	For whom	What it can do	What it cannot do
Owner	The store's boss	Everything, including managing other owners. This role cannot be changed.	—
Admin	The owner's right hand	Manage everything: sales, stock, settings, staff accounts, roles, devices.	Edit or remove an owner.
Manager	The day-to-day store manager	Sell, void, refund, manage all shifts, approve variances, discounts and prices, manage products, stock, purchasing, customers, reports, settings.	Manage staff accounts, roles, devices and system monitoring.
Cashier	Till staff	Sell, give discounts up to the store limit, put sales on hold, open and close their own shift, record expenses, find and create customers, make estimates, view stock, reprint a receipt.	Change a price, go over the discount limit, sell on credit, make cash movements, refund, void. These actions need a manager's approval.
Inventory clerk	The stock person	Receive, adjust, count and transfer stock, manage suppliers, purchase orders and products.	Sell: no access to the till.
Accountant	The accountant	Dashboard, reports and exports, sales (read only), expenses, card settlements, audit log.	Sell or edit sales.


Tip: when a cashier tries a restricted action, the **Manager approval needed** window opens. A manager enters their credentials on the spot; the approval is valid only once, for that action.

Tip: if a page is missing from your menu, nothing is broken: your role does not give access to it. Ask the administrator.

Find your way in Admin

Admin is where you manage the store: sales, products, stock, staff and settings. Cashiers do not have access to it.

1. On the till screen, click **Admin**.
2. The first page your role allows is shown (usually the **Dashboard**).
3. To go back to the till, click **Back to POS** at the bottom of the menu.



The Admin menu

The menu

The left menu is organized into sections: **Sales**, **Catalog**, **Stock**, **People** and **System**. Everyone sees only the pages their role allows. At the top of the menu: your email, your role, the **Help** button and the notifications bell.

At the bottom of the menu, you always find:

- the **Language** list;
- **Help**;
- **Account security**;
- **Back to POS**;


- **Sign out.**

On a phone

On a narrow screen, the menu is collapsed:

1. Tap the ≡ button (**Open menu**) at the top left.
2. The menu slides in from the left. Tap a page: it closes by itself.
3. To close it without choosing, tap ✕ (**Close menu**), the grayed-out area or the Esc key.

The top bar keeps the page title, the **Help** button and the bell.



Admin on a phone, menu open

On a phone, tables are shown as **cards**: one card per row, with the same information and the same buttons as the table. Tap a card to open it.

> **Tip:** the widest pages (reports, inventory) remain usable on a phone, but a computer or tablet is more comfortable for long data entry.

Choose the language

The app is available in English, French, Haitian Creole and Spanish. Each person chooses their language on their own device; the choice is kept for later sign-ins.

- **Sign-in page and till (computer):** click **EN**, **FR**, **HT** or **ES** at the top right. The active button is blue.
- **Till on a phone:** tap ⋯ (**More actions**), then choose the language in the list.
- **Admin:** at the bottom of the menu, choose the language in the **Language** list.
- **Help center:** the language buttons are at the top of the page.


The change is immediate, including help. The store's default language is set in **Settings** > **General**: it applies to anyone who has not made a personal choice.

> **Tip:** product, category and payment method names stay in the language they were entered in. So you will sometimes see "Cash" or "Card".

Notifications

The bell flags important events: low stock, purchase orders and expenses to approve, till, payments, devices, system. The blue number shows how many alerts are unread.

1. Click the bell (at the top of the till or of the admin menu).
2. Read the list of recent alerts. The type appears in color, for example **LOW STOCK**.
3. Click an alert to open what it is about, and mark it as read: a **Low stock** alert for one product opens the **Inventory** on that product and its location; a low-stock summary for a location opens that location with **Low stock only**; stock counts to approve open the **Counts** tab; the other alerts open their page (expenses, purchasing, shifts, payments, devices, system).
4. Click **Dismiss** next to an alert to mark it as read without opening it, or click **Mark all as read**.
5. Click **All notifications and preferences** to open the full page.



The Notifications page and preferences

On the **Notifications** page:

1. Choose **Unread** or **All** in the list at the top.
2. Click **Mark as read** on an alert, or **Mark all as read**.
3. Under **Notification preferences**, check **Show the unread count on the bell** and, if email is set up, **Also send me an e-mail for new alerts**. **Quiet hours (no e-mail)** prevent emails at night.
4. Click **Save**.

> **Tip:** marking an alert as read only affects you. An alert disappears for everyone when its problem is fixed (for example when the stock is replenished).

> **Tip:** you only see alerts for your branches. A repeating alert is grouped: "85 times" shows how many times it happened.

Using help


The manual is built into the app. It opens on the topics of the page you are on.

Open help

- Press the **F1** key, anywhere in the app.

- At the till: click the **?** icon at the top of the screen. On a phone: ⋯ then **Help**.
- In the admin area: click **?** at the top of the menu, or **Help** at the bottom of the menu. On a phone: **?** in the top bar.
- On the login page: click **Need help?**.

Help opens in a panel on the right (full screen on a phone). It shows **Help for this page**: only the topics of the page you are on (for example, on **Products**, the product topics). If a window is open, for example **Payment**, help opens that window's topic directly.



The help panel open on the Products page

All topics and the PDF

Two buttons sit under the search box:

- **All topics** shows the whole manual, by category. **Topics for this page** goes back to the page's list.
- **Download the PDF** downloads the whole manual, in the app language, to read or print outside the app.

Search

1. Type one or more words in **Search the help...**, for example "change" or "transfer".
2. Matching topics appear with an excerpt; the words found are highlighted.
3. Click a topic to read it.

Search ignores accents and capitals ("etiquette" finds "étiquette") and tolerates a small typo.


Read a topic

- Click an image to enlarge it; click again (or press Esc) to close it.
- **Related topics**, at the bottom, suggests similar topics.
- **Back** returns to the previous topic or to the help home.
- **Full page** opens the help center in the page, at the address /help.

Help follows the app's language. If a topic is not translated yet, it appears in English (or French) with a message.

Forgot your password


If you no longer know your password, choose a new one yourself with a link sent to your email address.



The Forgot your password page

1. On the sign-in page, click **Forgot password?** (next to **Password**).
2. Enter the email of your account in **Email**.
3. Click **Send the link**. The page confirms that a link is on its way.
4. Open the email **Reset your password** and click **Choose a new password**. Check the spam folder if it is not in your inbox.

5. Enter your new password twice (at least 8 characters): **New password** and **Confirm the new password**.
6. Click **Save the new password**, then **Sign in** with the new password.



Choosing the new password

Good to know

- The link works **once** and expires after **30 minutes**. A new request replaces the previous link.
- The email is written in the language shown on the page when you asked for it.
- For security, the page shows the same message whether the address has an account or not.
- Saving the new password **signs out every device** signed in to your account, and unlocks an account locked after too many wrong tries.
- If two-factor authentication is on, the app still asks for your 6-digit code at sign-in.
- At most 3 links per hour per account.

Error messages

- **This link is invalid or has expired. Ask for a new one.**: the link was already used, is more than 30 minutes old, or was replaced by a newer one. Click **Ask for a new link**.
- **The two passwords are different**: type the same password in both fields.


Tip: no email after a few minutes? Check the address you typed. A manager can also set a new password for you in **Users** (see Reset the password).

Till

The till screen

After signing in, sales staff land on the till screen. It has three areas:

- **The top bar**: the store, the till, the shift and the quick-access buttons.
- **Products** (on the left): the search, the categories and the product tiles.
- **The cart** (on the right): the customer, the salesperson, the items, the totals and the **Charge** button.



The till screen

A sale always follows the same order:

1. Add the products to the cart.
2. Choose the customer, if needed.
3. Apply discounts, if needed.
4. Click **Charge** (F12).
5. Record the payment or payments, then click **Complete sale**.
6. Hand over the receipt and the change.

The top bar


Item	What it is for
Store name	Reminds you which store you are working in.
Till list	Chooses the till and the branch for this station. The choice is kept on the device.
Open shift / SH-000004 · Open	Opens the till shift, or shows the current shift (see Open a shift).
Open drawer	Opens the drawer without a sale, with a reason. Visible when the shift is open.
Clock in / Clock out	Records your hours. Visible if your account is linked to an employee profile.
Online / Offline	Connection status. A click opens the offline sales.
Held carts	The carts set aside (F9).
Keyboard icon	The keyboard shortcuts.
?	This help (F1).
Returns	Return or exchange. Visible to people allowed to give refunds.
Admin	Opens the admin area (owner, administrator, manager).
Bell	The notifications.
EN FR HT ES	The language of this device.
Shield	Account security.
Exit arrow	**Sign out.**

> **Tip:** always sign out before handing the till to a coworker. Otherwise, their sales will be recorded under your name.

> **Tip:** if the store requires it, the till refuses to sell until the shift is open.

The till on a phone

On a phone (or any narrow screen), the till adapts: products and the cart become two tabs, and the secondary buttons move into a menu.



The till on a phone, Products tab

The two tabs


- **Products**: search, categories and product tiles. Tap a tile to add it to the cart. A short "Added: ..." message confirms it.
- **Cart (3)**: the number in parentheses is the number of items. Here you find the customer, the lines, the discounts and the totals.

The Charge bar

At the bottom of the **Products** tab, a bar always stays visible: it shows the number of items and the total. Tap **Charge** to go straight to payment without switching tabs. Tap the summary to see the cart.

The ⋯ menu (More actions)

Tap ⋯ at the top right for the top-bar actions that do not fit:



The More actions menu

- **Open drawer** and **Clock in / Clock out**;
- **Held carts** and **Returns**;
- **Admin** (depending on your role);
- **Help**;
- **Account security** and **Language**;
- **Sign out**.


The shift and the register list stay on the second line of the top bar.

> **Tip:** on a phone, the cursor does not go back to the search box by itself after each item is added (so the keyboard does not keep popping up). Tap the search box to type or scan.

> **Tip:** windows (payment, customer, discounts…) open full screen; their main buttons stay at the bottom, within thumb reach.

Till keyboard shortcuts

You can run the till entirely with the keyboard and the barcode scanner. Press **?** or click the keyboard icon to show the list.



The Keyboard shortcuts window

Key	Action
F1	Open help
F2	Search products / scan
F4	Choose customer
F6	Hold the cart
F8	Discounts
F9	Held carts
F12 or **Ctrl + Enter**	Charge
↑ ↓	Select a cart line
+ −	Change the quantity of the selected line
Delete	Remove the selected line
Esc	Close the open window
?	Show these shortcuts

> **Tip:** after each action, the cursor goes back to the search field: you can scan the next item right away.

> **Tip:** the **+**, **−**, **?**, **Delete** and arrow keys do not work while you are typing in a field. The F keys work anywhere on the till screen.


Add products and manage the cart

You have three ways to add a product:

- **Scan the barcode**: the product is added to the cart automatically.
- **Search**: type part of the name, the SKU or the barcode in **Search products or scan a barcode… (F2)**, then click the product tile.
- **Browse**: click a category (**All**, **Drinks**…) then the product tile.

Each tile shows the name, the variant (size, color), the SKU, the price and the stock, for example **65 in stock**.

Clicking the same tile again (or scanning the product again) increases the quantity on its line: the product appears only once in the cart. The line keeps its discount or changed price. Only items sold by weight get one line per weighing.



The cart with several items

Manage the cart

The cart, on the right, shows each line with its unit price, quantity and total.

- Click **+** or **−** to change the quantity, or type it in the box.
- Click the trash can to remove the line.
- Click **Add a note** to write a remark printed on the receipt.
- Click **Clear cart** to remove everything (you are asked to confirm).

Below the lines: the **Subtotal**, discounts, **Tax**, the **Total** and its equivalent in the other currency (for example **≈ in HTG**).

> ⚠ **Warning:** the till never sells more than the available stock. An **Out of stock** tile is grayed out. If you ask for too many, a message shows the available quantity, for example "Only 3 × … in stock".

> 💡 **Tip:** if a scanned code is unknown, the message "No product found for …" appears. Check the item or search for it by name.

> 💡 **Tip:** on the keyboard, ↑ ↓ select a line, **+** and **−** change its quantity and **Delete** removes it.

Offline, searching by name, SKU or barcode also works: it uses the copy of the catalog kept on the device (see Sell offline).

Sell a product by weight

Some products are sold by weight, length or volume (for example rice by the kilo).

- **With a scale label**: scan the label. The weight or price is read from the barcode and the line is added automatically.
- **Without a label**: click the product. The **Enter the quantity** window opens. Type the weight shown on the scale, for example 1.250, then click **Apply**.

In the cart, the line shows as "1.250 kg × US$1.20/kg". To correct the weight, click the line's quantity.


> 💡 **Tip:** each scale label creates its own line, even for the same product.

> 💡 **Tip:** weighed products and their unit are set up in Admin (see Units and products sold by weight). The label format is set in Scale labels.

Choose the customer and the salesperson

With no customer, the sale goes to the **Walk-in customer**. Choose a customer to give them loyalty points, apply their group prices, use their store credit or sell on credit.

1. Click **Walk-in customer** at the top of the cart (**F4** key).
2. Type at least 2 characters: name, phone, email or customer code.
3. Click the right customer in the list. Their points are shown, for example **4037 pts**.



The Customer window

To create a new customer:

1. In the same window, click **New customer**.
2. Fill in **First name**, **Last name**, **Phone** and, if possible, **Email**.
3. Click **Add customer**. They are chosen for the sale right away.

If the customer belongs to a group (for example Wholesale), their group prices and group discount apply right away (see Group prices and discount). Removing the customer brings back the normal prices.

> **Tip:** for a customer who has an account, the window also offers **Take a payment**: you record a payment on their account. Cash goes into your till shift. A large payment by another method (bank transfer, check) needs a manager's approval.

> **Warning:** searching for and creating customers needs a connection. Offline, the sale continues as a walk-in customer.

Choose the salesperson

The salesperson is the person who helped the customer; they get credit for the sale in reports (commissions). They can be different from the cashier.

1. Under the customer, open the **No salesperson** list.
2. Choose the name. It is printed on the receipt.

Discounts and promo codes at the till


Discount on a line

1. On the product line, type the percentage in the **%** box.
2. The discount shows in green under the line total.
3. If the discount is over the store limit, fill in the **Reason for the discount (required)** field.

> ⚠ **Warning:** above the limit, the cashier sees **Needs a manager's approval at checkout.** A manager will have to approve when taking payment (see Get a manager's approval).

Discount on the whole cart or promo code

1. Click **Discount** (**F8** key).
2. For a promo code, type it in **Discount code** and click **Apply**. The accepted code shows with its description.
3. For a free discount, go to **Manual discount on the sale**. Choose **%** or **Amount**, type the value and click **Apply**.
4. Above the store limit, fill in the requested reason.
5. Close the window. The button shows the active discount, for example **WELCOME10**.



The Discounts window

> **Tip:** click **Remove** to take off a code. Promo codes need an internet connection.

> **Warning:** a code whose end date has passed is refused, even if its status is still **Active**.

Automatic discounts (active promotions, the customer's group discount) apply without you doing anything; they appear in the totals and on the receipt.

Customer group prices and discount

A customer can belong to a **Group** (for example Wholesalers or VIP). The group can have a **Default price list** and a **Discount %** (see Customer groups).

At the till, everything is automatic:

1. Choose the customer (F4).
2. The cart is recalculated with the prices from the group's list. A message confirms it, for example "Group Wholesalers: group prices and a 5% group discount apply."
3. The discount appears in the totals on the **Group discount (Wholesalers, 5%)** line, then on the receipt.

No approval is asked for: the store decided these prices for this group. There is no price list to choose by hand.

> **Tip:** removing the customer (going back to walk-in) restores normal prices right away.


> ⚠ **Warning:** a cart loaded from an estimate keeps the estimate's negotiated prices (see Estimates).

> 💡 **Tip:** products not on the group's list keep their normal price; the group's discount % still applies to them.

Change a price at the till

The price comes from the catalog. Only change it in specific cases, for example a damaged item.

1. In the cart, click the line's unit price (the text with the small pencil).
2. Type the **New unit price**.
3. Click **Apply**. The old price appears crossed out on the line.
4. To go back to the normal price, click **Use catalog price**.



The Change price window

> ⚠ **Warning:** a cashier is not allowed to change a price alone. A manager will have to approve at checkout (see Get a manager's approval). Offline, this approval is not possible.

Get a manager to approve an action

When someone tries an action they are not allowed to do alone, the **Manager approval needed** window opens. It shows the missing permission. A manager who is present can approve without anyone signing out.

1. The manager types their **Manager email** and **Password**.

2. If they turned on two-factor authentication, they also type the **Two-factor code**.
3. They click **Approve**. The action continues as usual.
4. If several actions need approval (a price and a discount, for example), the window comes back for each one. The manager must work in all of your branches: a manager limited to another branch cannot approve for you.

To give up, click **Cancel**.

Actions that often need approval

Action	Who needs it
Change a price, discount above the limit	Cashier, at checkout
On account (credit) sale, going over the credit limit	Cashier
Cash in, cash out, safe drop, cash variance	Cashier (see Shifts)
Late return, refund to another method, void	Anyone without the permission
Approve your own expense or your own purchase order	Everyone, even the owner
Large top-up on a gift card or store credit	Second person required


Rules

- The manager must have the requested permission themselves.
- The manager must be a different person from the one doing the action.
- An approval works only once, for this action only, and lasts 2 minutes.
- Every approval is recorded in the audit log, with the manager's name (**Approved by**).

⚠ **Warning:** the manager never gives out their password: they type it into the window themselves.

Charge: the payment screen

1. Click **Charge** (**F12** key). On a phone, tap **Charge** in the bottom bar.
2. The **Payment** window shows the **Total**, **Received** and **Remaining**, in dollars and in gourdes.
3. Below these boxes, the day's rate is shown, for example **1 USD = 132.5 HTG**.



The Payment window

It always works the same way:

1. Choose the currency in **Customer pays in: USD** or **HTG**.
2. Click the payment method.
3. Check or type the amount, then click **Add**.
4. Repeat while there is an amount left to pay: one sale can combine several methods and several currencies.
5. Click **Complete sale**.

Button	Payment method	Good to know
Cash	Cash	The only method that can go over the amount due: the difference becomes the change. See Cash and change.
Card	Bank card	Exact amount. See Card, MonCash, bank transfer.
MonCash	Mobile payment	Exact amount. The **Reference** is required.
Bank transfer	Bank transfer	Exact amount. The **Reference** is required.
Loyalty points	Loyalty points	Appears if the customer has points.
Gift card	Gift card	Asks for the card code.
On account	Credit sale	Needs a customer with an account.
Store credit	Store credit	Appears if the customer has store credit.

Method names are set by the store (see Payment methods), so they may be different.


> **Tip:** to remove a payment added by mistake, click its trash can in the list.

> **Warning:** if the **Manager approval needed** window opens after **Charge**, the cart contains a restricted action (changed price, large discount…). See Get a manager to approve.

Offline, the window shows in orange: "Offline — the sale will be saved on this device and uploaded later." Cash, card and MonCash still work; points, gift cards, on-account sales and store credit need a connection.

Cash in dollars or gourdes and giving change

1. In **Customer pays in**, choose **USD** or **HTG**.
2. Click **Cash**.
3. Click one of the suggested amounts (exact amount or round bills), or type the amount received and click **Add**.
4. The green **GIVE BACK TO THE CUSTOMER** box appears. It shows the change in USD and in HTG.
5. Tap the currency you are giving change in: it is shown in large type.
6. Click **Complete sale · give … change**.



Cash payment with the change to give

Paying in gourdes shows the conversion, for example "= $45.28". After the sale, the **Sale complete** window shows the change to give in large type (**Received**, **Sale total**, **Give back**), or "Exact amount: no change to give".

Two rates apply. The amount asked in gourdes and the value of the gourdes received use the **sell rate**. Change given in gourdes for dollars uses the **buy rate**. If the customer paid in gourdes, change in gourdes is worked out directly (2,000 HTG given for 1,350 HTG due: give back 650 HTG). Both rates show under the totals, for example "1 USD = 135 HTG (sell) · 130 HTG (buy)".

⚠ **Warning:** make sure the customer is really paying in the chosen currency. The rate used is today's rate, set in admin (see Exchange rate). The change given can never be more than the cash received.

Tip: the cash taken (minus the change given) is added to your shift and will be expected at the end-of-shift count.

Pay by card, MonCash, or bank transfer

1. Click **Card**, **MonCash**, or **Bank transfer**.

2. Check the amount (these methods take the exact amount).
3. If the **Reference** field appears, type the approval code from the terminal or the MonCash transaction number.
4. Click **Add**, then **Complete sale**.

> ⚠ **Warning:** always check on the customer's phone or on the terminal that the payment was accepted before clicking **Add**. Without a reference, the app refuses the payment ("MonCash needs a reference (e.g. approval code)").

With a connected card terminal

If the store has connected a payment terminal, you don't type a code: the card is charged when you complete the sale. The **Card payment** window follows the transaction:

- wait for the customer to present their card;
- if the response is slow, click **Check now**;
- if it fails, click **Try again** or choose **Cancel sale**.

If the customer cancels on the terminal, the sale is not recorded but the cart stays: take another payment.

> 💡 **Tip:** card payments are then matched against the bank statements in Card settlements.

Pay with loyalty points

The chosen customer must have points. The **Loyalty points** button shows their points and their value, for example "4037 pts = $40.37".

1. Choose the customer before charging.
2. In **Payment**, click **Loyalty points**.
3. Type the amount to pay with points, then click **Add**.
4. Add another payment if needed.

> ⚠ **Warning:** the store sets a minimum number of points per use (100 for example) and a maximum share of the sale that can be paid with points (50% for example). Points need a connection. With no customer, the message "Add a customer to use points" appears.


> 💡 **Tip:** the customer earns points on the items bought. The part paid with points, a gift card, store credit or on account does not earn points. The receipt shows the **Points earned** and the **Points balance**.

The rules are set in Loyalty program; balance corrections are made on the customer's profile.

Sell and redeem a gift card

Sell a gift card

1. Click **Gift card** under the cart.
2. In **Sell a gift card**, type the **Amount** (at least 1.00).
3. If you have a pre-printed card, scan its code into **Card code (optional)**. Otherwise, leave it empty: a code will be created.
4. Click **Add to the sale**, then check out as usual.
5. After the sale, the **Gift cards issued — give the codes to the customer** box shows the code. Give it to the customer.



The Gift cards window

⚠ **Warning:** a card code has **12 to 32 characters**, letters and digits only, with **at least one letter and at least one digit**. Otherwise the message "A gift card code has 12 to 32 characters, with letters and digits" appears.

> ⚠ **Warning:** the full code is shown only once. A gift card has no tax and no discount; it can only be sold online and cannot be put on hold.

Pay with a gift card

1. In the **Payment** window, click **Gift card**.
2. Scan or type the card code.
3. Click **Check balance**. The available balance appears.
4. Check the suggested amount, then click **Add**.
5. If the card does not cover everything, add another payment for the rest.

> 💡 **Tip:** "This gift card can't be used" means the card is unknown, not active yet or expired. How long cards stay valid is set in General settings.

The **Check a balance** part of the **Gift cards** window gives a card's balance without a sale: type the code and click **Check balance**.

Sale on account (credit) and customer store credit

Sell on account

An **On account** sale is charged to the customer's account, and the customer pays later. It is only for customers who have an account and a credit limit.

1. Choose the customer before taking payment.
2. In **Payment**, click **On account**.
3. The message "Charged to ...'s account. A manager may need to approve it at checkout." appears. Check the amount, then click **Add**.
4. Click **Complete sale**.

> ⚠ **Warning:** the cashier needs a manager's approval for a sale on account. Above the credit limit, an additional authorization is required. A customer **On credit hold** can no longer buy on account.

> 💡 **Tip:** with no customer selected, the **On account** button shows **Add a customer first.**

Pay with the customer's store credit

Store credit is credit kept by the store, for example after a return refunded as store credit.

1. Choose the customer.
2. In **Payment**, click **Store credit**: the button shows the available amount.
3. Click **Add**, then complete with another payment if needed.

> **Tip:** the **Store credit** button only appears if the selected customer has store credit. Both methods need an internet connection.

Balances and payments are tracked in Customer accounts.

Give the receipt (print, email, link)

After **Complete sale**, the **Sale complete** window opens. At the top, the **Give back** box reminds you of the change to give.

You can then:

- **Print receipt**: prints on the connected receipt printer (see Hardware), otherwise through the browser's print window.
- **Email receipt**: the customer's address is suggested. Check "The customer asked to receive this receipt by e-mail (no marketing)", then click **Send**.
- **Receipt link (SMS, WhatsApp)**: click **Create link**, then **Copy link** or **Share**. The link is valid for 30 days.
- **New sale**: closes the window and clears the screen for the next customer.

> **Tip:** a reprint is always marked COPY. Past sales are reprinted from **Admin** > **Sales** (see Sales history).

> **Warning:** sending by email is only possible if email is set up for the store, and it is limited to a few sends per minute. It does not count as consent to receive advertising.

If the store has checked **Print automatically when a sale is completed** (see Receipts and printing), the receipt prints without a click.

Hold a cart and resume it

A customer forgot something? Set their cart aside and serve the next customer.

1. Click **Hold** (key **F6**).
2. The message "Cart held as H-000003. Resume it from Held carts (F9)." appears and the cart is emptied.

3. To resume it, click **Held carts** in the top bar (key **F9**; on a phone: ⋯ then **Held carts**).
4. Choose the **This register** or **Whole store** tab.
5. Click **Resume** next to the right cart.



The list of held carts

The resumed cart shows "Resumed held cart — completing it closes the hold." Finish the sale as usual.


> ⚠ **Warning:** items in a held cart stay reserved. The cart expires after a set time (24 hours, for example). Holding a cart requires a connection.

> **Tip:** if prices have changed since the cart was held, the "Prices changed since this cart was held" window shows the old and new totals and asks you to confirm. The trash can in the list cancels a held cart: its items go back on sale.

The customer display

The customer display is a second screen facing the customer. It shows the items, the total, then the change given. It runs on the same computer as the till, without going through the Internet.

1. Plug a second screen into the till computer.
2. In **Admin** > **Hardware**, click **Open customer display**. You can also open a new window of the same browser at the app's address followed by /customer-display.
3. Drag this window onto the customer's screen and make it full screen (F11 key).
4. Go back to the till window and sell as usual.



The customer display waiting for a sale

With no sale in progress, the screen shows the store name and **Welcome!**. During the sale, it shows each item with its quantity and price, then discounts, tax and the **TOTAL**. At the end, it shows **Thank you!**, the total paid and the change.

> ⚠ **Warning:** open the customer display in the same browser and the same session as the till. Another machine or another browser shows nothing.

> 💡 **Tip:** the customer display keeps working offline, because it does not go through the Internet. The F1 key does not open help there: the screen is meant for the customer.

Take an order with a deposit and hand it over

For a service you prepare (printing, a banner, a repair…), the customer can pay part now and the rest when they come back. Orders are for items **not tracked in stock** (services).

Take the order

1. Add the services to the cart as for a sale. Put the details in the line note (size, colours, text).
2. Click **Take as an order** (under the cart).
3. Choose the **Customer**: they are the one who comes back for the order.
4. Choose the **Ready by** date and type the **Notes for the preparation** if needed.

5. Under **Deposit (optional)**, type the amount the customer gives and choose how they pay (cash, card, mobile money…). Any amount works, even none.
6. Click **Take the order**.

The order receipt opens. It shows the total, the **Deposits paid** and the **BALANCE DUE AT PICKUP**. Print it and give it to the customer.

> **Note:** the deposit goes into **your cash session today:** cash is added to the drawer (as a paid-in), other methods appear under **Order deposits** in the session. The order is not a sale yet: the sale is counted at pickup.

Follow the orders

Click **Orders** in the top bar (on a phone: ⋯ then **Orders**). Search by order number, customer name or phone. Open an order to:

- **Add a deposit**: the customer pays another part (never more than the balance).
- **Mark ready**: the order is prepared. Call the customer. **Back in preparation** undoes it.
- **Edit details**: change the **Ready by** date or the notes.
- **Print**: the order receipt again, with every deposit.

Hand the order over

1. In **Orders**, open the order and click **Pick up: take the balance**.
2. The order goes into the cart at its prices. The cart shows **Deposits paid** and the **Balance due**.
3. Click **Charge** and take the balance as usual.

The receipt shows the total, a **Deposit paid** line for the deposits and what the customer pays now. The order becomes **Picked up**.

> ⚠ **Warning:** a pickup needs a connection. The balance is taken in cash or with a payment confirmed at the till.

Cancel an order

Open the order and click **Cancel the order**. Type the reason, then choose:

- **Give the deposits back**: each deposit goes back the way it was paid (cash in cash, in the currency it was handed over in; a card deposit by card). Cash comes out of your open session. If a way of paying is no longer available, choose another one.
- **Keep the deposits**: the store keeps them.

Note: cancelling needs the permission "Cancel orders and refund or keep their deposits", or a manager's approval. Voiding the pickup sale puts the order back to **Ready** with its deposits.

Shifts


Open a shift

In the app, a work shift is called a **shift**. A shift belongs to a register: it starts with counting the opening float and ends with counting the drawer. Each cashier opens and closes their own shift.

With **One cashier per drawer** (the default, see Branches and registers), each cashier sells in **their own shift**: a second cashier on the same register never sells in a colleague's shift; the till asks them to **Open your own shift on this register before selling**. With **Shared drawer**, several cashiers sell in the same shift and each sale keeps its cashier.

Open the shift before the first sale:

1. Check that the right register is selected in the list at the top of the screen.
2. Click **Open shift**.
3. Leave the **Count by denomination** tab active.
4. For each bill or coin, type the number found in the drawer. The **Counted total** is calculated automatically.
5. If you prefer, click **Enter total** and type the **Opening float** amount directly.
6. If the store accepts another currency (for example the gourde), type in **HTG cash in the drawer** the amount of that currency already in the drawer. Leave it empty if there is none. At closing, this amount counts in the expected HTG.
7. Add a remark in **Notes (optional)** if needed.
8. Check the **Opening float** line at the bottom, then click **Open shift**.



The Open shift window, with the float in dollars and the gourdes in the drawer

The top-bar button then shows the shift number, for example **SH-000004 · Open**. Click it at any time to see the drawer details.

> ⚠ **Warning:** by default the till refuses to charge a sale while no shift is open on its register: the **Charge** button is greyed out with the message **No cash session is open on this register**. The owner can change this in **Settings › General** (**Require an open cash session to sell**). Sales made offline still go through and are reviewed when they sync.

> 💡 **Tip:** the list of denominations (bills and coins) is set in **Admin > Shifts & cash, Cash denominations** block (see Denominations, business day and corrections).


> 💡 **Tip:** if the previous cashier handed the register over to you when closing, your shift is already open, with their counted cash as the opening float.

Paid in, paid out, safe drops and opening the drawer

Every cash movement that is not a sale must be recorded; otherwise the drawer will be off at closing.

View the current shift

Click the shift button (for example **SH-000004 · Open**). The **Shift and cash drawer** window shows how the drawer is calculated:




The current shift

Line	Meaning
Opening float	Amount counted at opening.
Cash sales (net of change)	Cash taken, minus the change given.
Paid in	Cash added during the day.
Paid out	Cash taken out for a small expense.
Safe drops	Cash moved from the drawer to the safe.
Expense payouts	Expenses paid with money from the drawer.
Expected in drawer	What should be in the drawer right now.
Expected HTG	The gourdes that should be in the drawer (float, sales, paid in, paid out and safe drops in HTG). They are counted separately at close.

Record a movement

1. In the shift window, click **Paid in**, **Paid out** or **Safe drop**.
2. Choose the **Currency**: **USD** or **HTG**, depending on the notes going in or out of the drawer. Enter the **Amount** in that currency and the **Reason** (at least 2 characters).
3. If you have a bag or receipt number, enter it in **Reference (optional)**.
4. Click **Record**.



The Paid in window, in gourdes

> **Tip:** a movement in HTG only changes the expected gourdes; the expected dollars stay the same.

> **Warning:** a cashier is not allowed to make these movements alone: the **Manager approval needed** window opens after **Record**. The manager enters their credentials and clicks **Approve** (see Get a manager's approval).

Open the drawer without a sale

For example, to make change for a customer. Each opening is recorded with your name and a reason.

1. Click **Open drawer** in the top bar (on a phone: ⋯ then **Open drawer**).
2. Enter the **Reason**, for example "Change for a customer".
3. Click **Record and open**, read the message, then click **Done**.

- **Recorded. The drawer is open.**: the connected drawer opened.
- **Recorded. No hardware connected: open the drawer with its key.**: no drawer is connected to this station.

> **Tip:** the **Open drawer** button only appears when the shift is open. If the drawer did not respond, the opening is still recorded.

Close the shift, count the drawer and print the Z-report

At the end of your shift, count the drawer and close the shift.

1. Click the shift button in the top bar.
2. Click **Close shift**.
3. Leave the **Blind count** box checked: you count without seeing the expected amount, which makes the count more honest.
4. Click **Start count**.

> **Warning:** as soon as the count starts, the till stops selling: the shift changes to **Counting**. To sell again, click **Back to selling**. To return to the count later: **Continue closing**.

Count

1. Type the number of each dollar bill and coin.
2. In **HTG cash in the drawer**, type the total gourdes in the drawer (leave empty if there are none).
3. Click **Review count**.

For each currency, the app shows **Counted**, **Expected** and **Variance**:

- no variance or within the tolerance: green message, for example "Within the $5.00 tolerance.";
- variance above the tolerance: red message; a **Variance reason** is required and the cashier must get a manager's approval.

Finish

1. If a reason is requested, fill in **Variance reason**.
2. If the next cashier takes over this drawer, choose their name in **Hand over to (optional)**: their shift will open with the counted cash. Otherwise, leave **Nobody: just close**.
3. Add **Notes (optional)** if needed. If in doubt, click **Recount**.
4. Click **Close shift** (or **Close and hand over**).

When the variance is above the tolerance, the **Manager approval needed** window opens: the manager checks the drawer, enters their credentials and clicks **Approve**. Their name appears on the Z-report (**Approved by**).

The Z-report

The **Shift closed** window shows the **Z-REPORT**: times, cashier and manager, sales by payment method, voided sales, drawer calculation in USD and HTG, cash movements, count, variance, tolerance and reason.


1. Click **Print Z-report**.
2. Click **Done**.

> **Tip:** a reprinted Z-report is marked COPY. Reports for past shifts can be found in Track shifts. The variance tolerance is set in the store settings.

Track register shifts (managers)

The manager, administrator, and owner track all shifts from **Admin** > **Shifts & cash**.

A cashier sees only **their own shifts** (the ones they opened or closed), and a shared-drawer shift while it is open.



The register shift list

1. Filter by status (**Open**, **Counting**, **Closed**), by register, or by dates (**From** and **To**: the start date must be before the end date).
2. Check **Variance above tolerance** to see only problem shifts. They have a red triangle.
3. Click a shift to open its details.

A shift's details show the **Opening float**, **Expected**, **Counted**, **Variance** and its reason, the drawer calculation, sales by payment method, and **Cash movements**. From these details, the manager can:

- reprint the **Z-report** (closed shift) or an **X-report** (shift still open);
- view the **Drawer ledger** (each opening, with its reason);
- click **Close shift** or **Force-close** to close the shift of an absent cashier;
- see **Late uploads after close** (offline sales that arrived after closing);
- add a correction (see Cash cuts, business day, and corrections).

> ⚠ **Warning:** only people allowed to manage all shifts (manager, administrator, owner) can force-close a shift or add a correction.

> **Tip:** on a phone, the list appears as cards; tap a card to open the details.

Denominations, business day and shift corrections

Below the list of shifts, the **Shifts & cash** page has two settings and, in each shift's details, the corrections.

Denominations

The **Cash denominations** section lists the bills and coins offered for counting (opening and closing).

1. Add, edit or remove the values for each currency.
2. Click **Save**. **Use defaults** restores the original list.

Business day

The **Business day** section sets the time the day starts (**Day starts at**). With 04:00, a sale made at 02:30 counts toward the previous day in reports. This setting requires the right to manage settings.

Correct a closed shift

A closed shift is never reopened: you correct it with a reason.

1. Open the shift from the list.
2. In **Corrections after close**, click **Add correction**.
3. Choose **Expected cash correction** or **Counted cash correction**, enter the amount and the reason.
4. Click **Save correction**.

The correction is added to the shift's history and to the audit log; the original figures remain visible.

Returns and voids


Process a return and refund the customer

A **return** takes back sold items, even days later. It creates a **credit note**; the original sale stays in the history, marked as refunded. For a sale entered by mistake during the same shift, use a void instead.

> ⚠ **Warning:** returns are reserved for people allowed to refund (manager, administrator, owner by default). The cashier does not see the **Returns** button: they call the manager. Offline, the button is grayed out.

Find the sale and choose the items

1. Click **Returns** in the top bar (on a phone: ⋯ then **Returns**).
2. In **New return**, scan the receipt barcode or type its number, for example MAIN-000001.
3. Click **Find sale**. The sale shows with its customer and payments.
4. Leave the **Return** tab active.
5. For each item brought back, type the quantity in **RETURN NOW** (0 for the others: this is a partial return).
6. In **CONDITION**, choose: **Back to stock**, **Damaged — keep in quarantine** or **Damaged — dispose**.
7. Fill in the **Reason for the return**.



The New return window

The **REFUND** column calculates the amount per line, including the original discounts and taxes.

Choose the refund

Choice in "Refund to"	Effect	Approval
Original payment (card first, then cash)	Refunds to the sale's payment methods.	None.
Customer's store credit	Creates store credit usable on a future purchase.	None. Needs a customer on the sale.
Cash, Card, MonCash…	Refunds to another method.	May need a manager.

1. Choose **Refund to**, then the **Register** the cash comes out of.
2. Check the summary, for example "2 item(s) · refund about US$2.48".
3. Click **Refund …**.

> ⚠ **Warning:** cash refunds are taken from the open shift of the chosen register and will show at the count. Past the return window (30 days, for example), a manager's approval is required. The items go back to a location in your branch.

Hand over the credit note

The **Return complete** window shows the **CREDIT NOTE** document, with its own number (for example MAIN-R-000001) and the original invoice. Click **Print credit note**, have the customer sign if needed, give back the money, then click **Done**.

> 💡 **Tip:** if the customer paid in gourdes, the cash refund is given in gourdes, at the rate of the original sale (not today's rate). The window shows the HTG amount to hand back in green, and it comes out of the gourdes in the drawer.

Make an exchange

The customer brings back an item and takes another one instead. The exchange records the return and the new sale in a single operation.

1. Click **Returns**, find the sale, then click the **Exchange** tab.
2. Enter the items brought back in **RETURN NOW**, with their **CONDITION**.
3. In **Replacement items**, search for the new item by name, SKU or barcode. Click it to add it; adjust the quantity with **+** and **−**.
4. Fill in the **Reason for the return**, for example "Size too small".

5. Read the summary, for example "Returned $16.49 · new items $14.99 · refund about $1.50". If the new item costs less, choose in **Refund to** how to give back the difference. If it costs more, choose the payment method in **The customer pays the difference with**.
6. Choose the **Register**, then click **Exchange**.

The **Exchange recorded** window shows the return's credit note and the new sale number, for example "Exchange complete: new sale MAIN-000006".

> **Tip:** the exact difference is calculated when the exchange is saved. If the new sale fails, the return stays recorded: finish the exchange from **Admin** > **Returns**, in the **Incomplete exchanges** section.

Give a goodwill refund


A goodwill refund gives money back without taking back any goods, for example as a gesture for an unhappy customer.

1. Click **Returns**, find the sale, then click **Goodwill refund**.
2. Type the **Amount to refund (no goods come back)**.
3. Fill in the **Reason for the return**.
4. Choose **Refund to** and the **Register**.
5. Click **Refund ...**.

> **Warning:** goodwill refunds are limited to people who have this permission (manager, administrator, owner). Otherwise, the **Manager approval needed** window opens. After a goodwill refund, the sale can no longer be voided.

Track returns in the admin area

1. Open **Admin** > **Returns**.
2. The list shows each credit note: number, date, original sale, reason, amount, and status.
3. Filter by status: **Refunded**, **Refund pending**, or **Refund failed**.
4. Click **New return** to make a return from the admin area: the window is the same as at the till (see Make a return).
5. Click a credit note to review it or **Print** it.



The return list


> **Tip:** a card refund can stay **Refund pending** while the bank responds. If it fails, click **Retry card refund**, or refund another way.

> **Tip:** from a sale's details (**Sales** page), the **Return items** button opens the return for that sale directly.

Void a sale

Voiding corrects a sale entered by mistake: the stock is put back, earned points are removed and payments are reversed. It is done in the admin area.

1. Open **Admin** > **Sales**.
2. Search for the sale by its number, then click it.
3. Click **Void sale**.
4. Read the warning: this action cannot be undone.
5. Type the **Reason**, for example "Entered by mistake".
6. Click the red **Void sale** button. To back out, click **Keep sale**.



The void confirmation

The sale changes to **Voided**. On-account, gift card or store credit payments are returned to the customer; a gift card sold in this sale is canceled.

Situation	Can it be voided?	What to do
Completed sale, till shift still open	Yes	Void the sale.
The sale's shift is closed	No	Do a return.
The sale already had a return or refund	No (the button no longer appears)	Do a return for the rest.
Sale with no shift, made more than 24 hours ago	No	Do a return.
Sale paid on a linked card terminal	No	Do a return to refund the card.

If the void is refused, the reason shows in red under the **Reason** field.

> **Tip:** without the permission to void, the **Manager approval needed** window opens: a manager authorizes the void with their credentials.

Offline


Selling offline

The till keeps a copy of products, prices, taxes, and stock on the device. If the Internet goes down, you keep selling: each sale is saved on the device and then sent to the server as soon as the connection returns.

To sell offline, the till must have received an **offline lease** while it was online. It is renewed automatically when the till is connected and stays valid for a set time (24 hours by default, see Offline and security).

Sell without Internet

When the connection drops, the indicator at the top changes from **Online** (green) to **Offline** (orange). A banner may remind you of the deadline.



The till offline

1. Scan or search for products as usual (search by name, SKU, or barcode works offline).
2. Click **Charge**.
3. Take cash, card, or MonCash, then click **Complete sale**.
4. The **Sale complete** window shows "Saved offline". The receipt has a temporary number that starts with **OFFLINE-**. Give it to the customer as usual.

What does not work offline

Feature	Why
Held carts	They are kept on the server.
Estimates sold at the till	The server marks the estimate as sold.
Gift cards (sale and payment)	The server checks the code and the balance.
Points, sale on account, store credit	The server checks the customer's balance.
Search for or create a customer	The sale continues as a walk-in customer.
Promo codes	The server validates the code.
Manager approval	It goes through the server.
Discounts above the store limit	They need a manager's approval, unless your role can override discounts.
Returns and voids	The **Returns** button is grayed out.

⚠ **Warning:** offline, the till does not sell more than the stock it knows about ("Only … in stock on this till (offline)"). A payment in another currency uses the rate stored on the till.

When offline selling is paused

If the till stays offline too long, the screen locks: **Offline selling is paused**. Possible causes: the lease has expired, the device's clock went backward, or the till was deactivated. Sales already made stay safe. Reconnect, then click **Try again**.


⚠ **Warning:** a new till must be opened at least once with Internet, otherwise it cannot sell offline.

Uploading offline sales when the connection returns

As soon as the connection returns, the till uploads the sales on its own, then retries regularly if any are left. While sales are waiting, the indicator shows how many, for example **Online · 1 pending**.

1. Click the **Online** / **Offline** indicator.

2. The **Offline sales** window lists the sales still on the device, with their number, time and amount.
3. Click **Upload now** to force the upload.



The Offline sales window

Status shown	Meaning	What to do
Waiting to upload	The sale will be uploaded automatically.	Nothing. Keep the device on and connected.
Upload postponed, next try at …	The server could not be reached.	Check the connection.
Needs review	The server refused the sale, with the reason.	Have a manager fix the cause, then click **Retry**.

Once uploaded, sales move to the **Uploaded** list with the temporary number and the final number, for example **OFFLINE-321E10D8 → MAIN-000008**. In **Admin** > **Sales**, you can search for a sale by its offline number.

⚠ **Warning:** never clear the browser data while sales are waiting: they would be lost. Signing out, however, keeps the waiting sales.


Tip: if a till can no longer connect at all, a manager clicks **Export unsynced sales** in this window (approval required). An administrator imports the file in Devices.

Offline sales that exceed the real stock or the limits go to the Review queue. A sale sent without the till's offline permission is not recorded: it shows **Needs review**, and an administrator records it by importing it in Devices.

Sales and expenses

The dashboard

The **Dashboard** summarizes the store's activity.



The dashboard

- **Date range** (opens on **Today**): **Today**, **Yesterday**, **Last 7 days**, **Last 30 days**, **This month** or **Custom range.** For a custom range, choose a start date and an end date (the end cannot be before the start).
- **Branch**: **All branches** or a single one.
- **Exchange rates**: the USD/HTG rate used at the till. **Update rate** changes it; **History** shows past rates (see Exchange rate).
- **Key figures**: net and gross sales, discounts given, returns, net taxes, number of sales, average basket, items sold, total collected (tax included), gross margin, voided sales, expenses, cash variance, gift cards sold, inventory value, owed to suppliers and low stock.
- **Further down**: the **Sales by day** and **Payment methods** charts, then **Sales by cashier** and **Top products.**

Yellow boxes call for your attention (cash variance, low stock). Click **View inventory →** to act.


> ⚠ **Warning:** margin, inventory value and costs only show for roles allowed to see costs. An account limited to certain branches only sees their figures.

> **Tip:** if you have an invitation from another store, it also shows at the top of the dashboard (see Invitations).

Sales history, reprinting and sending the receipt

The **Sales** page lists all sales with the number, date, customer, cashier, total and status.

A cashier sees only **their own sales** (the ones they rang up): **View every sale (all cashiers)** is kept for the manager, the admin and the owner. Without it, the **All cashiers** filter is not shown, and another cashier's sale cannot be found, not even through its link or a reprint.



The sales history

1. In the menu, click **Sales**.
2. Type a sale number in the search. Sales made offline also have an OFFLINE-… number you can search for.
3. Filter by status: **Completed**, **Voided**, **Payment pending**, **Held**… To see one person's sales, choose them in **All cashiers** (for example, to check a cashier's day).
4. Choose a period. The page opens on **Today**; choose **All time**, **Yesterday**, **Last 7 days**, **Last 30 days**, **This month** or **Custom range** (from ≤ to). To find an older sale by its number, choose **All time** first.

5. Use **Previous** and **Next** to change pages.

> **Tip:** a sale can also be **Refunded** or **Partially refunded** after a return. The salesperson's name appears under the cashier when it is different.

Sale details and reprinting

1. Click the sale's row (on a phone: its card).
2. The full receipt appears: items, taxes, total, payments and change given.
3. To print it again, click **Reprint (copy)**. The printed receipt is marked COPY.



A sale's details

From these details, you can also **Return items** (return) or **Void sale** (void).

Send the receipt to the customer


1. In the sale details, click **Email receipt**.
2. Enter the customer's email address.
3. Check **The customer asked to receive this receipt by e-mail (no marketing)**.
4. Click **Send**.

For SMS or WhatsApp, click **Receipt link (SMS, WhatsApp)**: the app creates a link to the receipt, valid for 30 days.

> ⚠ **Warning:** this is only for sending the receipt; it does not give the customer's consent to receive marketing. If the address is not that of the sale's customer, their contact details are left off the document sent.

Create an estimate and convert it into a sale

An estimate shows prices to a customer before they buy. It does not reserve stock. The **Estimates** page lists every estimate with its status: **Draft**, **Sent**, **Accepted**, **Declined** or **Sold**.



The estimate list

> 💡 **Note:** an estimate for a branch only holds products sold at that branch: the product search offers only them, and a product of another branch is refused when saving. Only the people with access to that branch see the estimate. Every estimate has a branch: for an employee of a single branch, it is theirs, chosen automatically.

Create an estimate

1. Click **New estimate**.
2. In **Customer**, type the name, phone number or email and choose the customer. For someone who is not in your customers, just type their name.

3. Check **Valid until** (30 days by default). This date cannot be in the past. If the store has several branches, choose the **Branch** making the estimate (the last one used is offered). Its name heads the estimate when **Name under the logo** is set to **Branch name** in receipt settings.
4. In **Add products**, search for each product and click **Add**.
5. For each line, set the **Qty**, the **Unit price** if you are giving a special price, the discount (**Disc. %**) and a **Note**.
6. If needed, add a discount on the whole estimate, **Notes** and **Terms & conditions** (deposit…).
7. Click **Save estimate**. The exact totals (including taxes) are calculated when you save.

Send the estimate and record the answer

1. Click **Print** (or save as PDF), or **Print pro forma** if the customer asks for a pro forma invoice.
2. Give it to the customer, then click **Mark as sent**.
3. When the customer answers, click **Accepted** or **Declined**.

> **Tip: Duplicate** creates a new estimate from this one. **Edit** lets you, for example, extend the validity date.


Convert into a sale

1. Open the accepted estimate and click **Sell at the till**.
2. The till opens with the customer and the items, at the estimate prices. A banner reminds you: "Estimate … — sold at the quoted prices; completing the sale converts it."
3. Take payment as usual. The estimate changes to **Sold**.

> **Warning:** an expired estimate cannot be sold: edit it first to extend **Valid until**. Estimate prices apply only once, for its customer and its quantities; extra units are charged at the normal price. If the cart already has items, the app asks you to replace them.


Record an expense

The **Expenses** page tracks the store's costs: supplies, transport, repairs, rent…



The expense list

1. In the menu, click **Expenses**, then **New expense**.
2. Enter the **Date**, the **Amount**, and the **Description**.
3. Choose the **Category** and enter the **Supplier / payee**.
4. Choose **Paid by: Cash, Card, Bank transfer**, or **Other**.
5. For cash taken from a drawer, choose the register in **From till**. Leave **Not from a till** for petty cash.
6. Enter the **Receipt reference** and **Notes** if needed.
7. Click **Submit** to send it for approval, or **Save draft** to finish it later.



The New expense form

> ⚠ **Warning:** an expense date cannot be in the future ("The expense date cannot be in the future").

An expense above the store's approval threshold moves to **submitted** status and waits for approval. Below the threshold, it is approved automatically.

> 💡 **Tip:** the **Categories** tab creates your expense categories (electricity, repairs…) with **Add category**, for reports.

> 💡 **Tip:** an expense paid in gourdes is entered in gourdes: choose **HTG** next to the **Amount**. The app converts it to dollars at the sell rate for the reports and keeps the amount in gourdes. Paid in cash at a register, it comes out of the gourdes in the drawer.

Approve, reject and pay an expense

Expense statuses: **draft**, **submitted**, **approved**, **rejected**, **paid**.

Approve or reject

1. The person in charge of approvals (manager or accountant) opens **Expenses** and finds the **submitted** rows.
2. They click **Approve**, or **Reject** and enter the **Reason**.

> ⚠ **Warning:** an expense must be approved by someone other than the person who recorded or submitted it, even if that person is the owner. If it is your expense, click **Approve** anyway: the **Manager approval needed** window opens and another authorized person enters their **Manager email**, their **Password** (and their two-factor code if needed), then clicks **Approve**. That person is recorded as the approver.

A rejected expense can be edited and submitted again by the person who recorded it.


Pay

1. On the row of the **approved** expense, click **Pay**.
2. In **Paid from till**, choose the till the money comes out of, or **Not from a till (petty cash)**.
3. Enter a **Payment reference (optional)**.
4. Click **Mark paid**. The expense changes to the **paid** status.

> ⚠ **Warning:** cash paid from a till is recorded as a pay-out in that till's open shift; with no open shift, the payment is refused. The pay-out will show in the end-of-shift count.

Reconcile card settlements

The **Card settlements** page compares the statements from your bank or payment provider with the card payments taken at the till.



The Card settlements page

Import a statement

1. In the menu, click **Card settlements**.
2. Under **Import a settlement report**, choose the **Provider**.
3. Add a **Batch reference (optional)**, for example "payout 2026-09-21".
4. Choose the **CSV file** you got from the provider (reference, amount, fee and date columns).
5. Click **Import**. Lines are matched to payments by reference and amount.


Handle what is left "To reconcile"

- **Settlement lines without a payment:** statement lines that no payment covers. Choose the matching payment and click **Match and resolve**, or explain why there is none.
- **Card payments not yet settled:** payments taken that no statement covers yet. Click **Resolve**, write a **Note** (for example "Terminal batch closed late"), then confirm.

> **Tip:** at the bottom of the page, **Imported batches** lists the statements already imported, with the number of matched lines, the gross amount and the fees. **Card terminal per payment method** shows which terminal is linked to each method.

The review queue

The **Review queue** lists sales accepted offline that need to be checked. The sale is already recorded: fix the cause, then close the case with a note.



The review queue

Case type	What happened	What to do
Sold offline beyond stock	The till sold more than the stock	Count the shelf, adjust the stock, then close
Offline discount or price not approved	Discount or price changed offline without the right	Check with the cashier, then close
Uploaded after its shift closed	The sale is not in the count	Check the shift's cash, then close
Sold offline with no shift open	No shift was open	Link the cash to the right shift
Sold offline outside the till's lease	Sale made after the offline permission ended	Check the till and the sale
Till marked lost	A lost device had unsent sales	Estimate the lost sales, then close

1. In the menu, click **Review queue**.
2. Keep the **Open** filter to see the cases to handle; choose a type if needed.

3. Click the sale number to open the sale. For a stock problem, click **Open inventory**.
4. Click **Close case**, and write in **Note** what was checked (required).
5. Click **Mark resolved**, or **Dismiss (nothing to do)**.

> **Tip:** each type is handled by whoever has the right: stock by whoever adjusts inventory, till cases by whoever manages shifts. Work through the queue every day.

Follow orders and their deposits

The **Orders** page lists the services prepared for customers who paid a deposit. Each order shows its **Total**, **Deposits paid**, **Balance due**, **Ready by** date and status: **In preparation**, **Ready**, **Picked up** or **Cancelled**.

1. Choose a status (by default **Waiting for the customer**: in preparation or ready).
2. Search by order number, customer name or phone.
3. Click an order to see its lines, every deposit (date, method, who took it) and its history.

From an order you can **Print** the order receipt, **Add a deposit**, **Edit details** (ready date and notes), **Mark ready** or **Cancel the order**. The customer picks it up at the till: **Orders**, then **Pick up: take the balance**.

Where the money appears

- **Cash session**: a cash deposit is a paid-in of the session that took it. Every deposit is listed under **Order deposits** in the session and on the Z report.
- **Reports**: the **Order deposits** report lists each deposit and refund. **Payments by method** counts deposits when they are paid.
- **Sales**: the sale is counted at pickup, for the full total. Its **Deposit paid** line is not counted again as money received.

Cancel an order


Click **Cancel the order**, type the reason and choose **Give the deposits back** or **Keep the deposits**. Each deposit goes back the way it was paid, in the currency it was handed over in. A cash refund comes out of an open session on a register of the order's branch. Cancelling needs the permission "Cancel orders and refund or keep their deposits", or a manager's approval.

> **Note:** branch staff see only their branches' orders. Orders are for items not tracked in stock (services).

Reports

Open and read a report

The **Reports** page (**Sales** menu) is only for people allowed to see reports.



The Sales by day report

Topic	Reports
Sales	By day, by product, by category, by cashier, by hour, by salesperson
Payments and taxes	Payments by method, by currency, tax summary, discounts given
Returns and voids	Returns and refunds, voided sales
Inventory	Inventory valuation, low stock, stock card, counts and adjustments, transfers
Cash	Shifts and cash variances
Purchasing	Purchases, supplier aging
Expenses	Expenses
Customers	Loyalty points
Administration	Audit log activity

1. Click the report you want in the list on the left (on a phone: in the **Report** list at the top).
2. Choose the date range (a report opens on **Today**): **Today**, **Yesterday**, **Last 7 days**, **Last 30 days**, **This month**, or change the dates directly. The start date cannot be after the end date, and a period covers at most 400 days.

> **Note:** days are the store's days, in the time zone of the branch (or of the first branch for all branches), wherever you look at the report from. The dashboard and the sales, payment, return, cash and customer reports need the permission to see all sales.

3. If needed, choose a branch in **All branches**.
4. The table shows with a **Total** row. **Generated …** shows when it was calculated.

Some reports show the current state (**Inventory valuation**, **Low stock**): the date picker disappears. Supplier aging and audit log activity cover the whole store (branch filter grayed out). For the **Stock card**, choose an item first.

> **Tip:** each amount stays in its own currency: currencies are never added together.

> **Warning:** cost, margin and cost-value columns only appear if your role can see costs, including in exports. An account limited to certain branches only sees their figures.

Save filters

1. Set the date range, the branch and the parameters.
2. Click **Save filters**, type a **Filter name**, check **Share with the team** if needed, then click **Save**.
3. To reuse it, choose it in **Saved filters…**.

A relative date range like "Last 7 days" stays relative. To delete one of your filters, choose it, then click the trash can.

Export a report (CSV, Excel, PDF)

The export buttons appear at the top of the report if you have the **Export reports** permission.

1. Open the report and set the period and branch.
2. Click **CSV**, **Excel** or **PDF**.
3. The file downloads with the same filters as the screen.

> **Tip:** **CSV** opens in any spreadsheet app, **Excel** keeps number formatting, **PDF** is handy for printing or sending to the accountant.

Export in the background (large reports)

For a long report (a whole year), the file is prepared on the server while you keep working.

1. Choose the format in the small list (**Excel**, **CSV** or **PDF**).
2. Click **Export in background**.
3. At the bottom of the report, **Background exports** shows the task: **Building the file…** then **Ready**.
4. Click **Download**. The trash can removes the export from the list.

> **Warning:** the file stays available for 24 hours (**Available until …**), then becomes **Expired**. Each click on **Download** creates a link valid for 15 minutes: if it has expired, click again.


The list shows your exports from the last 7 days; each person sees only their own. On the **Products** page, **Export CSV** and **Export Excel** export the whole catalog.

Reconciliation and daily summary

Check the reconciliation

Reconciliation checks that every figure matches the source records: sale lines, payments, stock movements, returns and refunds.

1. At the bottom of the report list, click **Reconciliation**.
2. Choose the period and, if needed, the branch.
3. A green banner shows **Everything reconciles for … sale(s) in this period**.
4. Each passed check has a green check mark.



Reconciliation

If a check fails, it has a red cross, and a table lists each record involved (**Expected**, **Found**, **Detail**).

> ⚠ **Warning:** a discrepancy must be reviewed by a manager. Note the reference shown and open the sale or return involved.

Print the daily summary


The **Daily summary (PDF)** sums up the last day of the chosen period (today by default).

1. Choose the branch if needed.
2. At the bottom of the report list, click **Daily summary (PDF)**.
3. The PDF downloads: print it or file it.

Catalog

The product list and labels

The **Products** page (**Catalog** menu) shows your whole catalog: SKU, barcode, category, tax, price, stock, type and status. It requires the permission to manage products (owner, administrator, manager, stock clerk).



The product list

> **Note:** someone limited to some branches (for example a cashier of one shop) only sees the products sold at their branches, and the products sold everywhere. The owner, the administrator and a manager of the whole company (all branches) see the whole catalog. A product's branches are chosen in its form, in the branches part (none ticked: sold everywhere).

1. Type a name, SKU or barcode in **Search by name, SKU or barcode…**.
2. If needed, filter by **Category** (a category includes its sub-categories), **Type**, status (**Active**, **Inactive**, **Discontinued**), **Tags** or **Branch**.
3. Choose the order in **Sort by**: **Newest first** or **Oldest first** (creation date), name, price, stock, category, SKU or **Recently updated**. The choice is kept on this computer.
4. To export the catalog, click **Export CSV** or **Export Excel**.

A product sold without stock (a service, for example) shows — in the Stock column and does not appear in **Inventory**.

Each row has icons on the right:

- the pencil (**Edit**) opens the product's page;
- the layers (**Variants**) appear for products with variants;
- the red trash can (**Discontinue**) takes the product off sale.

> ⚠ **Warning:** a product is never deleted. **Discontinue** sets it to **Discontinued:** it is no longer sold, but its sales and stock history is kept.

At the top of the page, other buttons open: **Units** (products sold by weight), **Attributes** (variants) and **Print labels**.

Print price labels

1. Click **Print labels**.
2. Click **Add** next to each product you want, then enter the number of labels.
3. Choose the **Label language**, then click **Prepare … labels**: the labels are shown as they will print.
4. Click **Print**.

Labels are **1 × 1 inch**. Each one shows the name, the price and the barcode of the product code (the SKU when the product has no barcode).

- **With a label printer set up through JodaPrint**, the labels go straight to it, without the browser's print window. The message **… labels sent to the label printer** confirms it. See Hardware.
- **Without it**, the browser's print window opens: choose the label printer and a 1 × 1 inch paper there.


> 💡 **Tip:** a code made of digits only prints with thicker bars, which scanners read more easily. A very long code does not fit on the label: it is written without a barcode.

> 💡 **Tip:** on a phone, products are shown as cards, with the same buttons.

Create or edit a product

1. On the **Products** page, click **New product**.
2. Fill in **Name** and **SKU** (your internal code, unique).
3. If needed, add a **Description** and a **Barcode** (the one printed on the packaging).
4. Choose the **Type** (see the table).

5. Enter the **Selling price** and the **Unit cost** (purchase price, useful for margins).
6. Choose the **Category** and the **Tax category**. Leave **Store default tax rate** if the product uses the normal rate.
7. If needed, complete **Brand**, **Manufacturer**, **Unit of measure**, and **Tags** (type a word, then Enter).
8. In **Branch assortment**, check branches only if the product is not sold everywhere.
9. Enter the **Min stock level** and the **Reorder point** for low-stock alerts.
10. Leave **Track stock** checked for a physical item; uncheck it for a service. Check **Track serial numbers** for devices sold with a serial number.
11. Click **Create product**.



The New product form

Type	When to use it
Simple	A single item, a single price. The price is entered on the product form.
Variable (has variants)	The same product in several sizes or colors: each variant has its own SKU, barcode, price, and stock.
Composite (bundle)	A bundle or gift set sold as a single item.

> ⚠ **Warning:** the type cannot be changed after creation. For a variable or composite product, the price is entered in the variants after saving.

> 💡 **Tip:** if the check digit of an EAN or UPC barcode is wrong, the app warns you.

Edit a product and add images

1. Click the pencil on the product's row.
2. Change the fields you need. **Status** sets the product to **Active**, **Inactive**, or **Discontinued**.
3. At the bottom, in **Images**, click **Add images**: JPEG, PNG, or WebP up to 5 MB, 10 images per product.
4. Click the star on an image to make it the main image (lists and till).
5. Click **Save changes**.

> 💡 **Tip:** images can only be added after creation: create the product first, then open it again.

Variants, attributes and barcodes

Before creating variants, check your attributes (Size, Color…) with the **Attributes** button at the top of the **Products** page. Each attribute has a name, a code and a comma-separated list of options.

Manage variants

1. On the row of a variable product, click the **Variants** icon (the layers).
2. The **Variants of …** window lists each variant: attributes, SKU, barcode, price, cost, stock and status.
3. To add a variant, click **Add variant**, fill in the row, then confirm.
4. To edit a variant, click its pencil.

Create several variants at once

1. Click **Generate from attributes**.
2. Click the values you want for each attribute (they turn blue).
3. Enter the **Price of new variants** and, if you know it, the **Unit cost**.
4. Click **Preview** to see the combinations, then **Create variants**.

> **Tip:** each combination of the chosen values becomes a variant; combinations that already exist are skipped.

Add barcodes to a variant

A variant can have several barcodes (old and new packaging, for example).

1. In the variants window, click the **Barcodes** icon (the vertical bars).
2. Scan or type the code in **Scan or type a barcode**.
3. Click **Add**. The trash can removes a code.

> **Warning:** a barcode can belong to only one variant. Scanning any of its codes finds the variant at the till.

Units and products sold by weight

To sell rice, sugar, fabric or fuel, first create a unit with decimals.

1. On the **Products** page, click **Units**.
2. Click **New unit**.
3. Enter the **Name** (e.g. Kilogram) and the **Code** (e.g. kg).
4. Check **Allows decimal quantities (e.g. 1.25 kg)** and choose the number of **Decimal places**.
5. Click **Save unit**.


Then, in the product form:

1. Choose this unit in **Unit of measure**. The price you enter becomes the price per unit (per kilo, per meter…).
2. If a scale prints labels, enter its item code in **PLU (scale code)**.
3. Save the product.

> **Tip:** at the till, the cashier enters the weighed quantity (e.g. 1.250 kg). Scale labels (barcodes starting with 20 to 29) are read automatically if they are set up (see Scale labels).

Organize categories

Categories form a tree: a main category (e.g. Food) can contain subcategories (e.g. Drinks). They organize the till and the reports.



The Categories page

1. In the menu, click **Categories**, then **New category**.
2. Enter the **Name** and the **Code** (the code is used in CSV imports).
3. Choose a **Parent category**, or **None (top level)** for a main category.
4. Set the **Sort order** (0 appears first).
5. Leave **Active (shown in the POS and product forms)** checked.
6. Click **Create category**.

> **Tip:** to edit a category, click its pencil. Deactivating a category hides it at the till without changing the products.

Tie a category to branches

In a category's form (new, or an existing one with the pencil), the **Branches** part chooses where it is shown:

- **none ticked**: the category is shown in every branch;


- **some ticked**: only the staff of those branches see it (cashiers, stock clerks of one shop), in the back office and at the till. The owner, the administrator and a manager of the whole company see every category.

The **Branches** column of the list shows each category's setting. At the till, a category with no product sold at the till's branch is not shown.

> **Tip:** someone limited to some branches can only tie a category to their own branches.

Import products (Excel or CSV)

Import creates or updates many products from an Excel file (.xlsx) or a CSV file. You always see the changes before they are saved. You need the **Import products from CSV** permission.



The Import products page

1. In the menu, click **Import**.
2. Click **Excel template** (or **CSV template**) to get a file with the right columns.
3. Fill in the file and save it: as an Excel workbook (.xlsx, only the first sheet is read) or as CSV UTF-8. 5,000 rows and 2 MB maximum.
4. Choose what happens to **Existing products (same SKU)**: **Update their details** or **Leave them unchanged**.
5. Check **Also replace their prices and costs** only if the file contains the new prices.

6. Click **Choose file** and select your Excel or CSV file.
7. Review the summary: **New products**, **Updates**, **No change** and **Rows with errors**.
8. Fix the rows with errors if needed, then click **Import N products**.

Main columns:

- **sku** (required): identifies existing products;
- **name**: required for a new product;
- **category_code** and **tax_category_code**: existing codes;
- **price** and **cost**: simple products only, with a decimal point (e.g. 4.50);
- **product_type**: simple, variable or composite;
- **status**: active, inactive or discontinued.


> **Tip:** an empty cell leaves the existing value unchanged.

> **Tip:** the old Excel format (.xls) is not read: in Excel, use **Save As › Excel Workbook (.xlsx)**. In the Excel template every cell is text, so codes keep their leading zeros.

> **Warning:** the allow_backorder column is ignored: selling below zero stock is never allowed.

Price lists

A price list replaces the base price of some products. The **Price lists & tax** page groups them.



The Price lists & tax page

Type	How it applies
Standard	Applied automatically at the till when it is active.
Promotional	Applied automatically, usually for a limited time (sales).
Wholesale	For customers in a group that has it as its default list.
Member	For customers in a group that has it as its default list.

Create a list

1. Click **New price list**.
2. Enter the **Name** and the **Code**.
3. Choose the **Type**, the **Currency** and the **Branch** (or **All branches**).
4. Set the **Priority**: the highest one wins if several lists apply.
5. Enter **Valid from** and **Valid to** (leave empty to start right away or to have no end).
6. Click **Create price list**.

> ⚠ **Warning:** the end date must be after the start date ("Must be after the start date") and cannot be in the past ("The end date cannot be in the past").

Enter the prices

1. Click the list's row in the table.
2. Click **Add products** and choose the products or variants.
3. Enter the **List price**. Enter a **Min qty** if the price only applies from a certain quantity.
4. Click **Save prices**.

> **Tip:** products not in a list keep their base price. Choose a list as the **Default price list** of a customer group: the till applies it automatically as soon as a customer from the group is chosen. Minimum-quantity prices are not applied at the till yet.

Tax categories


Tax categories let you tax certain products at a different rate (food, tax-exempt products…).

1. In the menu, click **Price lists & tax**.
2. Scroll down to **Tax categories** and click **New tax category**.
3. Enter the **Code** and **Name**, and choose the **Tax rate**. Choose **None (tax exempt)** for a product with no tax.
4. Save, then assign this category to the relevant products in their product details.

> **Tip:** a product with no tax category uses the store's default tax rate. The rates themselves are set in Tax rates.

Create a discount or promo code

The **Discounts** page groups the promotions and promo codes that can be used at the till: type, value, number of uses, and validity.



The discount list

1. Click **New discount**.
2. Enter the **Name** and the **Code**. The cashier types this code at the till; it is saved in uppercase.
3. Choose the **Type**: **Percentage off**, **Fixed amount off**, or **Buy X get Y free**.
4. Choose **Applies to**: **Whole cart**, **Specific products**, or **Specific categories**.
5. Enter the value: percentage, amount, or **Buy quantity** and **Get free quantity**.
6. If needed, set a **Minimum purchase**, a **Maximum discount**, and a **Usage limit**.
7. Set the **Priority**: discounts with a higher priority apply first.
8. Enter the **Valid from** and **Valid until** dates.
9. Click **Create discount**.

> ⚠ **Warning:** the end date must be after the start date and cannot be in the past. A discount whose end date has passed is no longer accepted at the till, even if its status is still **Active**.

> 💡 **Tip:** manual discounts given by the cashier (without a code) are limited by the store settings; above that limit, a manager must approve.


Inventory

View stock and spot low stock

All stock tasks are done in **Admin** > **Inventory**. The tabs are **Stock**, **Movements**, **Counts**, **Transfers**, **Aging** and **Valuation**. The stock clerk, manager, administrator and owner have access; a cashier only checks stock at the till.

The **Stock** tab shows, for each product and each location, the **On hand**, **Reserved**, **Available** and **In transit** quantities, with the **Last counted** and **Last received** dates.

> **Tip:** products sold without stock (services such as printing) are not listed here: untick **Track stock** on the product to leave it out of stock, counts and low-stock alerts.



The Stock tab

1. Type a name, SKU or barcode in the search.
2. Choose a location in **All locations** to see a single store or warehouse.
3. Check **Sellable only** to hide non-sellable locations (quarantine, damaged).

> **Tip:** only stock in a sellable location can be sold. Quarantined or damaged stock is kept apart and has a yellow tag.

Spot low stock

A product is low on stock when its quantity reaches or falls below its **Min stock level** (product profile).

1. Check **Low stock only**. The affected rows have the red **Low** tag.
2. Order these products (see Reorder).


> **Tip:** the app checks stock regularly and sends an alert to the bell for each location with low stock. The alert disappears when the stock is replenished.

> **Tip:** opened from a **Low stock** notification, the list shows only that product, with a **Product: …** label above it. Click the × on that label to see every product again.

Receive stock without a purchase order

Use this feature for a delivery without a purchase order. For a supplier order, use Receive a delivery.

1. In the **Stock** tab, click **Receive stock**.
2. Choose the **Location** receiving the goods.
3. Enter the **Supplier reference** (invoice or delivery note) and, if needed, **Notes**.
4. Search for each product in **Products** and click **Add**.
5. Enter the **Good** quantity, the **Damaged** quantity and the **Unit cost**.
6. Click **Receive stock**.



The Receive stock window


> **Tip:** the unit cost you enter updates the product cost (weighted average cost or FIFO, depending on the store's method). Damaged units go to the warehouse's quarantine or damaged location; if it has none, a non-sellable **Damaged** location is created. Returns brought back damaged go there too.

Correct stock, view movements and check stock

Correct stock (adjustment)

An adjustment corrects stock after breakage, theft, an expired date or a counting error.

1. In the **Stock** tab, click **Count / adjust**.
2. Choose the **Location** and the **Reason: Stock count (recount)**, **Damaged**, **Theft / loss**, **Expired** or **Other**.
3. Choose the **Mode: Set counted quantity** (the difference is calculated) or **Add / remove quantity** (+5 to add, -2 to remove).
4. Explain why in **Notes**.
5. Add the products, enter the quantities, then click **Save adjustment**.



The Count / adjust window

> ⚠ **Warning:** stock can never go negative. If you remove more than the stock, the adjustment is refused and the available quantity is shown. This rule also applies to sales, transfers and imports.

> 💡 **Tip:** adjustments need the **Adjust stock** permission. Each one gets a number (ADJ-…) shown in the **Movements** tab.

View movements

The **Movements** tab shows the last 200 movements: sales, returns, receipts, transfers, adjustments and counts. Filter by location; each row shows the **Type**, the **Quantity** (+ in, − out), the **Reference** and the **Notes**. This history is the reference.


Check and rebuild stock

1. In **Movements**, click **Check stock**.
2. Choose the **Scope**: **Whole store** or one location.
3. Click **Check (dry run)**: nothing is changed.
4. If all is well: **Everything matches the ledger. Nothing to fix.**
5. Otherwise, review the differences, then click **Apply corrections**.

> ⚠ **Warning: Apply corrections** replaces the recorded quantities with those from the history. Leave this action to the manager or administrator.

Transfer stock between locations

A transfer moves stock from one location to another (from the warehouse to a branch, for example). It goes through three steps: draft, dispatch, receipt.



The Transfers tab

Create the transfer

1. Click the **Transfers** tab, then **New transfer**.
2. Choose the **Origin** location and the **Destination** location.
3. Add the products and enter the **Quantity** of each, with **Notes** if needed.
4. Click **Save draft**.

> 💡 **Tip:** a draft does not move stock. You can still **Edit** it or cancel it (**Cancel transfer**).

Dispatch

1. Click the transfer's row to open it.

2. If the **Submit for approval** button appears, click it and wait for a manager to click **Approve**.
3. Click **Dispatch…**, and enter in **Now** the units that are leaving.
4. Check **This is the last dispatch** if the rest will never be sent.
5. Click **Dispatch**. The units leave the origin and become **In transit**.

Receive at the destination


1. On arrival, open the transfer and click **Receive…**.
2. Enter the quantities that arrived as **Good**, **Damaged**, and **Missing**.
3. Click **Receive**. The transfer moves to **Received** status; its **History** keeps every step.

> ⚠ **Warning:** missing units stay in transit until they are found. If they are lost, click **Write off missing** and enter the reason.

> ⚠ **Warning:** in **Transfer settings**, the manager chooses when a transfer must be approved before dispatch: **Never**, **Above a value**, or **Always**. The person who requested the transfer cannot approve it themselves. The **Over-receipt tolerance (%)** sets how many extra units can be received without approval.

Do a stock count

A count compares the real stock with the recorded stock, for a whole location or a single category.



The Counts tab

Start

1. Click the **Counts** tab, then **New count**.
2. Choose the **Location** and a **Category** (or **All products**).
3. Leave **Blind count** checked: counters do not see the expected quantities.
4. Add **Notes** and click **Start count**.

> **Tip:** expected quantities are frozen at the start. You can keep selling during the count: those sales do not count as variances.

Enter and submit

1. Open the count (status **Counting**).
2. Enter the quantity in **Counted** and, if there is a variance, a **Reason**. Leave a line empty if it was not counted: it will not be adjusted.
3. Click **Save counts** to continue later, or **Submit count**.

The app shows the variances, the units over or short, and the net value.

> **Warning:** if all variances stay within the store tolerance, the count is posted right away. Otherwise it goes to **Needs approval**: someone other than the counter, with the **Approve stock count variances** permission, must approve it.

Approve (manager)

1. Open the count in **Needs approval** and check each variance and its reason.
2. Click **Approve & post** to correct the stock, or **Send back** to have it recounted.

Cancel count stops it without changing anything.


Stock aging and valuation

Aging

The **Aging** tab groups stock by age (0 to 30 days, 31 to 60 days… over 180 days) with its value. Use it to spot products that don't sell and plan a promotion.

Valuation

The **Valuation** tab is visible to people who can see costs and can adjust stock or manage settings.



The Valuation tab

- **Costing method**: **Moving average** or **FIFO** (first in, first out). The **Switch to FIFO…** or **Switch to moving average…** button changes the method.
- **Revalue a product**: corrects a product's unit cost (wrong purchase price). Quantities do not change.

To revalue:

1. Click **Revalue…**, then **Choose** next to the product.
2. Enter the **New unit cost** and the **Reason (required)**.
3. Confirm. The value difference is recorded as a revaluation and logged.


> ⚠ **Warning:** changing the costing method is an accounting decision. Talk to your accountant first.

Purchasing

Manage suppliers

The whole purchasing cycle happens in **Admin** > **Purchasing**. The tabs you see depend on your permissions: **Purchase orders**, **Suppliers**, **Reorder**, **Supplier returns** (stock clerk, manager…); **Invoices**, **Payments**, **Payables** (manager, administrator, owner).

The **Suppliers** tab lists your suppliers with their contact, payment terms, currency and status.




The Suppliers tab

1. Click **New supplier**.
2. Enter the **Code** and **Name**, then the **Email**, **Phone** and **Tax number**.
3. Enter the **Payment terms (net days)**, for example 30.
4. Enter the **Lead time (days)**: it sets the expected date of new orders.
5. Enter the **Currency** (USD, HTG…); empty = the store's currency.
6. Fill in the **Address**, **City** and **Contacts** (**Add contact**).
7. Click **Save supplier**.

> ⚠ **Warning:** an **Inactive** or **Blocked** supplier can no longer receive new purchase orders.

> **Tip:** a supplier's **Products** button records, for each product, the supplier code, the last cost, the minimum order quantity and whether it is the **Preferred** supplier. This information is used for reordering.

Create a purchase order and get it approved



The Purchase orders tab

Create the draft

1. In **Purchase orders**, click **New order**.
2. Choose the **Supplier** and the **Deliver to** location.
3. Check the **Expected delivery** (calculated from the supplier's lead time; it cannot be in the past).
4. Search for each product and click **Add**. Enter the **Quantity** and the **Unit cost**, and if needed a discount (**Disc. %**) or a **Tax**.
5. Fill in the **Order tax**, **Shipping** (freight costs) and the **Supplier reference**.
6. Add **Notes (printed on the order)**.
7. Click **Save draft**.

Submit and get approval

1. Open the order by clicking its row, then click **Submit**.

2. Below the store's approval threshold, the order is approved automatically. Above it, the order moves to **Needs approval**.

> ⚠ **Warning:** an order above the threshold must be approved by someone other than its creator, with the **Approve purchase orders** permission. Even the owner cannot approve their own order.

To approve: the manager opens the order from their own account and clicks **Approve**; or, if the manager is present, the creator clicks **Approve** and the manager enters their credentials in the **Manager approval needed** window.

> 💡 **Tip: Send back** returns the order to draft with a reason. After approval, click **Mark as issued** when the order is sent to the supplier. **Print** produces the order as a PDF or on paper.

> 💡 **Tip:** an order is in the supplier's currency (for example HTG). On receiving, costs in gourdes enter stock converted to dollars at the sell rate.

Receive a supplier delivery

1. Open the purchase order with the status **Issued** or **Partly received**.
2. Click **Receive goods**.
3. In **Received now**, enter the units that arrived in good condition.
4. In **Damaged**, enter the damaged units. Check **Accept into stock** only if you keep them.
5. Check the **Unit cost** and enter the **Delivery note / invoice number**.
6. Click **Receive**.

> 💡 **Note:** a **Unit cost** more than 10% away from the order's cost needs someone with **Approve purchase orders**.


If not everything arrived, the order changes to **Partly received**: the rest will be received with the next delivery. Each receipt gets a number (GRN-…) shown in **Goods receipts**.

> ⚠ **Warning:** receiving more than the ordered quantity is only accepted within the store's tolerance. Above it, a person with the **Approve purchase orders** permission must authorize it.

> **Tip:** if the supplier will never deliver the rest, click **Short-close** and give the reason. For a delivery without a purchase order, use **Unplanned receipt** in the **Purchase orders** tab (specific permission).

Record a supplier invoice

The invoice is compared with the purchase order and the quantities received (three-way match).



The Invoices tab

1. Click the **Invoices** tab, then **New invoice**.
2. Choose the **Supplier** and the **Type** (**Invoice** or **Opening balance**).
3. Enter the **Supplier invoice number** and the **Invoice date** (not in the future).
4. Leave the **Due date** empty to use the supplier's terms; otherwise, it cannot be before the invoice date.
5. Choose the **Purchase order**: its received lines appear. Check the invoiced lines and verify quantities and prices.
6. For charges outside the order (shipping…), click **Add a line**.
7. Click **Save invoice**.

The invoice's page shows the **Price variance** and **Qty variance** compared with the order, then what is **Still owed**.

⚠ **Warning:** an invoice with no variance (or within tolerance) is approved right away. Beyond that, it stays **Needs approval**: someone other than the person who entered it must click **Approve**. Only an approved invoice can be paid.

Tip: a wrong invoice cannot be deleted: click **Void invoice** and enter the reason.

Pay a supplier and track payables


Pay a supplier

1. Click the **Payments** tab, then **New payment**.
2. Choose the **Supplier**.
3. Enter the **Amount**, the **Date** (not in the future) and the **Method** (**Cash**, **Bank transfer**, **Cheque**, **Card**, **Mobile money** or **Other**).
4. Enter the **Reference** (check or transfer number).
5. In **Allocate to invoices**, enter the amount paid for each invoice, or click **Oldest first**.
6. Click **Record payment**.

Tip: a payment can be partial. Anything not allocated stays on account with the supplier and can be allocated later with **Allocate**. **New credit** records a credit note received from the supplier.

Track payables

The **Payables** tab shows what you owe each supplier, sorted by how late it is: **Not yet due**, **1–30 days**, **31–60 days**, **61–90 days**, **Over 90 days**.



The Payables tab

1. Change the **Aging as of** date if needed.
2. Click a supplier to open their **Statement**: invoices, credits and payments with the running balance.
3. Click **Print** to print the statement.

> **Tip:** you can pay a supplier in another currency than theirs. Choose the currency next to the **Amount**: gourdes paid against a dollar balance are converted at the sell rate; dollars paid against a gourde balance are converted at the buy rate. The line under the amount shows what it settles.


Return goods to a supplier

1. Click the **Supplier returns** tab, then **New return**.
2. Choose the **Supplier**, then the original **Receipt**.
3. In the **Return** column, enter the number of units sent back (at most the **Can return** quantity).
4. Enter the **Reason** and, if the supplier gave one, the **Return authorisation (RMA)** number.
5. Click **Record return**.

> **Tip:** the returned units leave the stock of the receiving location. A supplier credit for their value is created automatically and reduces what you owe.

Prepare a reorder

The **Reorder** tab lists the products whose stock is below the **Reorder point,** with the quantity already on order and a suggested quantity.



The Reorder tab


1. Choose the location in **Stock at**.
2. Adjust each product's quantity in the **Order** column.
3. Click **Create draft PO**: a draft is created for the preferred supplier.
4. Check it and submit it in the **Purchase orders** tab.

> **Tip:** a product without a supplier appears under **No supplier yet.** Add it to a supplier (the supplier's **Products** button) so you can order it from here.

Customers

Find and create a customer

The **Admin** > **Customers** page is reserved for people who can edit customers (owner, administrator, manager). Cashiers search for and add customers from the till. The tabs are **Customers**, **Possible duplicates**, **Groups** and **Custom fields**.



The customer list


Search

1. Type a name, code, email or phone number in the search box.
2. If needed, filter by status (**Active**, **Inactive**, **Blocked**) or by group.
3. The table shows the group, the **Points** and the **Last purchase** date.
4. Click the eye to open the customer profile, or the pencil to edit it.

Create a customer

1. Click **New customer**.
2. Choose the **Type**: **Individual** or **Company**. Leave the **Code** empty: it is created automatically.
3. Enter the **First name**, **Last name** (or the company name), **Email** and **Phone**. The date of birth is optional and cannot be in the future or before 1900.

4. For a customer who buys on credit, enter the **Credit limit** and the **Payment terms (days)**.
5. Choose the customer's **Group** (its group prices will apply at the till).
6. Under **Marketing consent**, check **Agrees to marketing emails** and/or **Agrees to marketing SMS** only if the customer agrees, then fill in **How was consent given?**.
7. Click **Create customer**.




The New customer form

> ⚠ **Warning:** never send an advertising message to a customer who has not given consent. Every consent change is dated and kept in the consent **History**.

> **Tip:** if a customer with the same email or phone number already exists, the app warns you before creating it.

The customer profile (notes, addresses, custom fields)

The profile has five tabs: **Details**, **Account** (depending on your permissions), **Addresses & contacts**, **Notes** and **Activity**.



A customer's profile

- **Details:** contact info, balance, credit limit, group, marketing consent, loyalty points and **Recent purchases**.
- **Account:** the credit account.
- **Addresses & contacts**: **Billing** or **Shipping** addresses and people to contact (useful for a business).
- **Activity:** the full history (sales, payments, points, notes).

> **Tip:** the date of birth, tax number and address are visible only to people who manage customers or can see balances.

Add an internal note

1. Open the **Notes** tab.
2. Write the note. It is never shown to the customer.
3. Choose who can see it: **Everyone who can see customers** or **Managers only**.
4. Click **Add note**.

Custom fields

The **Custom fields** tab of the **Customers** page adds your own information about customers (preferred contact, size…):

1. Click **New field**.
2. Enter the **Label** (the **Key** is created automatically if you leave it empty) and choose the **Type**. For a list, enter the **Options** separated by commas.
3. Check **Required** if needed and set the **Order**.
4. Click **Create field**. It appears on each customer's form and profile; set it to **Hidden** to hide it without deleting it.

Adjust a customer's loyalty points

Customers earn points on every purchase and can use them to pay at the till. The rules are set in Loyalty program.


To correct a balance (mistake, goodwill gesture):

1. Open the customer's profile, **Details** tab, **Loyalty points** section.
2. Enter the number of points to add (e.g. 50) or remove (e.g. -50).
3. Enter the **Reason (required)**.
4. Click **Adjust**.

> ⚠ **Warning:** points are worth money. Only people who can adjust customer accounts (owner, administrator, manager) can change them; for everyone else, the **Manager approval needed** window opens. Every adjustment is logged.

Customer credit accounts and payments

A customer with credit can buy "on account" and pay later, within their credit limit. The **Customer accounts** page requires the permission to view balances.



Customer balances by aging

View all balances

1. In the menu, click **Customer accounts**.
2. The **Aging** tab lists customers who owe money, sorted by how late they are.
3. Choose **With a balance** or **All accounts**.

> **Tip:** follow up first on the 61–90 days and 90+ days columns.

A customer's account

1. Open the customer's profile, **Account** tab.
2. Read the **Balance**, **Credit limit**, **Available credit**, and **Payment terms**.
3. The aging table shows **Current**, then amounts late by **1–30 days**, **31–60 days**, and so on.
4. **Account entries** lists each sale on account and each payment.

> **Tip:** check **Credit hold (no new sales on account)** on the profile of a customer who doesn't pay.

Take a payment on the account

1. In the **Account** tab, click **Receive payment**.

2. Enter the **Amount**, choose **Paid with** and, if needed, a **Reference**.
3. For cash, choose the **Register**: the payment goes into its open shift.
4. Click **Record payment**.

The payment counts in the **Payments by method** report (all branches only).

> ⚠ **Warning:** a non-cash payment over 500 that clears a debt requires approval from a second person. **Adjust balance** (+ the customer owes more, − they owe less, reason required) is reserved for the manager or administrator.


Print a statement

1. In **Account**, **Statement** section, choose the **From** and **To** dates (the start date cannot be after the end date).
2. Click **Show statement**: **Opening balance**, transactions, **Closing balance**.
3. Click **Print** (or save as PDF) and give it to the customer.

> 💡 **Tip:** a customer can pay their account in gourdes. In **Receive payment**, choose **HTG** next to the amount and type the amount in gourdes: the app shows its dollar value at the sell rate, and that is what comes off the balance. In cash, the gourdes go into the gourdes in the drawer.

Customer groups

Groups (Retail, VIP, Wholesale…) bring together customers who get the same terms.




The Groups tab

1. In **Customers**, click the **Groups** tab, then **New group**.
2. Enter the **Code** and **Name**.
3. Choose a **Default price list** and a **Discount %** if needed.
4. Enter the **Payment terms (days)** for the group's on-account sales.
5. Click **Create group**.
6. To put a customer in the group, edit their profile and choose the **Group**.

> ⚠ **Warning:** as soon as a customer in the group is chosen at the till, the group's price list and discount apply automatically, with no approval. The discount shows on the cart and on the receipt as "Group discount". Removing the customer brings back the normal prices (see Group prices and discount).

Merge duplicate customers

1. In **Customers**, click the **Possible duplicates** tab.
2. The app suggests pairs (same email, same phone, or similar name).
3. Click **Review & merge**, choose the profile to keep, then confirm.



The Possible duplicates tab


> **Tip:** merging keeps a single profile, moves the purchase history, adds up points and balances, and keeps both consent histories. You need the **Merge duplicate customers** permission.

Gift cards and store credit (admin)

- A **Gift card** is sold at the till (see Sell and use a gift card).
- **Store credit** is created, for example, when a return is refunded as store credit; the customer uses it as a payment method.

To view or correct a card or store credit:

1. In the menu, click **Customer accounts**, then the **Gift cards & store credit** tab.
2. Filter by type or type the last 4 characters of the card.
3. Click **Adjust** on the row you want.
4. Enter the amount (+25.00 to add, -10.00 to remove) and the **Reason**.
5. Click **Adjust**.



The Gift cards & store credit tab

> ⚠ **Warning:** adding more than 500 to a gift card or store credit needs a second person's approval, even if you have the permission: the **Manager approval needed** window opens.

> 💡 **Tip:** cards expire after the number of months set in General settings (**Gift cards expire after (months)**).

Anonymise a customer (right to erasure)

If a customer asks for their personal data to be erased, you can anonymise them.

1. Open the customer profile.
2. At the bottom of the profile, click **Anonymise**.
3. Read the confirmation: the name, contact details, addresses and notes will be permanently erased.
4. Confirm with **OK**, or click **Cancel** to do nothing.

The profile becomes inactive and shows **This customer was anonymised on …**. Sales and account history are kept for accounting.


> ⚠ **Warning:** anonymisation is permanent. It is refused while the customer owes money or still has a balance in their favor. You need the permission to manage customers.

Staff

Manage employees

An **Employee** is a person who works for the store (job title, branches, hours). A **User** is a sign-in account with a role (see Add a user). An employee may or may not have an account: a cleaner has a profile for their hours, a cashier has both, linked.

> ⚠ **Warning:** the **Employees** page requires the permission to manage employees (owner, administrator, manager). To link a user account, you also need the **Manage staff accounts** permission.



The employee list

Add an employee

1. Click **Add employee**.
2. Fill in **First name** and **Last name** (required).
3. If needed, add **Job title**, **Employee code** (unique), **Phone**, **Email** and **Hire date** (at most one year ahead).
4. In **User account**, choose the account the person signs in with, or **No account**.
5. Under **Branches**, check the branches where the person works and choose the **Primary** one.

6. Add **Notes (optional)**, then click **Save**.

> ⚠ **Warning:** a user account can be linked to only one employee. A manager limited to certain branches can assign an employee only to their own branches.

Search and edit

Type a name, employee code or email in **Search by name, code or email**, filter by status or branch, then click the pencil on the row.

Deactivate an employee who is leaving

You never delete an employee: you deactivate them.

1. Click the red icon (crossed-out person) on the row.
2. Enter the **Last day** (not in the future, and not before the hire date) and a **Reason (optional)**.
3. Click **Deactivate**.

Any open clock-in is closed. If the employee has an account, that account is suspended and signed out of all devices. To bring them back, filter on **Inactive**, then click **Reactivate**.

Time clock and attendance

Clock in at the till

An employee whose employee record is linked to their account clocks in themselves:

1. Sign in to the till with your account.
2. At the top of the screen, click **Clock in** at the start of the day (on a phone: ⋯ then **Clock in**).
3. The button turns green and shows **Clock out**; hover over it to see **Clocked in since …**.
4. At the end of the day, click **Clock out**.

> 💡 **Tip:** the button does not appear if your account is not linked to an active employee record. You can only clock in at a branch you are assigned to.


Record hours for an employee

1. In **Employees**, open the **Attendance** tab, then click **Record hours**.
2. Choose the **Employee**.

3. Enter the date and time in **Clock in** and **Clock out**.
4. Write the **Reason**, for example "Forgot to clock in".
5. Click **Save**.

> ⚠ **Warning:** the time cannot be in the future, clock-out must be after clock-in, and a shift cannot be longer than 24 hours. You cannot record a new clock-in for an employee who is already clocked in: close their open clock-in first. **Note:** nobody records hours for themselves: another manager records yours.

The attendance report




The Attendance tab

1. In **Attendance**, choose the start date and end date.
2. Choose an employee, or **All employees**.
3. The table shows the **Shifts worked** and the total **Hours**. Click a row for details, and **Hide** to close it.

Each shift shows where it came from (**at the till** or **recorded by a manager**, with the reason). If an employee is still clocked in, **clocked in** appears next to their name; a manager can click **Clock out now**.


Add or invite a user

The **Users** page requires the **Manage staff accounts** permission (owner and administrator by default). The list shows **Name, Email, Role, Branches, Status, MFA** and **Last login**; your row is marked **(you)**.



The user list

1. Click **Add user**.
2. Type the **Email**, then the **First name** and **Last name**.
3. Choose the **Role**, for example **Cashier**.
4. Under **Branch access**, choose **All branches** or **Only some branches** and check them.
5. Click **Add user**. You don't type a password: the person chooses their own.



The Add user form

Case	What happens
The email does not have an account yet	The person gets a **Choose my password** e-mail (the link works for 72 hours). Choosing their password confirms their e-mail address; then they can sign in. Until then their status is "Waiting for the password (e-mail not confirmed)".
The email already has an account (in another store)	The person gets an **invitation**; their status is "Invited — waiting for acceptance".

An invited person gets access to the store only after accepting the invitation, in **Account security** or on the dashboard (see Invitations and switching stores).

⚠ **Warning:** no one can give more permissions than they have themselves. Only an owner can make someone else an owner.

Tip: the e-mail did not arrive? Check the address and the spam folder, then click the send icon on their row (**Send the link to choose a password again**). A new link replaces the old one.

Edit or suspend a user, or reset their password

Limit access to certain branches

A limited user only sees the sales, shifts, stock and reports of their branches, and only the products sold there (see Products); customers stay shared.

1. Click the pencil on the person's row.
2. Under **Branch access**, choose **Only some branches** and check at least one branch.
3. Click **Save changes**.

> **Tip:** if the person has an employee record, **Use employee branches** copies the branches from their record. An owner always has access to everything.

Change the role or suspend

1. Click the pencil on the row.
2. Change the **Role**, or choose **Suspended (no access)** in **Status**.
3. Click **Save changes**.

As soon as you save, the person is signed out of all their devices in this store: the change applies immediately. To restore access, set the **Status** back to **Active**.

> **Warning:** you cannot change your own role or your own status.

Disconnect a user

An account can only be signed in on one device at a time. If someone left their session open on another device (browser closed without signing out, lost phone), disconnect them:

1. Click the **Disconnect** icon (an arrow leaving a door) on their row.
2. Confirm. They are signed out of every device and can sign in again where they are.

Work not yet saved on the other device is lost. You cannot disconnect yourself here: use **Sign out**.

Reset a member's password

As long as a person has not chosen their password (status "Waiting for the password"), you cannot set it for them: send them the link again with the send icon on their row. That is how every e-mail address gets confirmed.

1. Click the key icon on the row.

2. Type the **New password**, then type it again in **Confirm password**.
3. Click **Reset password** and share it securely.

The person is immediately signed out everywhere and signs back in with the new password.

> ⚠ **Warning:** you cannot reset your own password here: change it in Account security. If the account is also used in another store, the reset is refused: the person must change their password themselves.

To cut off someone's access everywhere (lost phone…), suspend them or reset their password: all their sessions in the store are closed.

Reset two-factor authentication


If someone lost their phone, or their 6-digit codes are refused (the account locks after several tries), the **owner** clicks the **crossed-out shield** icon on their row (**Reset two-factor authentication**) and confirms.

- Their two-factor authentication is turned off and their account **unlocked**; they are signed out everywhere.
- They sign in with their password. If their role requires it, they are asked to set two-factor up again with a new QR code.
- The action is recorded in the Audit log.

> ⚠ **Warning:** only an owner can do it, and not for their own account (see Two-factor authentication). An account used in another store must turn it off itself.

Roles and permissions

A role is a set of permissions. The four built-in roles (Owner, Admin, Manager, Cashier) are marked **Built-in** and cannot be deleted. The page requires the **Manage roles and permissions** permission.



The Roles and permissions page

View and edit a role's permissions

1. In the list on the left, click a role. The number of people who have it appears under its name.
2. Permissions are grouped by area: **Point of Sale**, **Sales**, **Cash**, **Customers**, and so on.
3. Check or uncheck permissions. **Select all** and **Clear all** act on a whole area.
4. Click **Save** (or **Discard**).

Changes apply the next time each person loads a page.

> ⚠ **Warning:** you cannot edit a role that has permissions you don't have, or add a permission you don't have. The **Owner** role always has every permission.

> 💡 **Tip: View sales (their own)** shows the person the sales they rang up; add **View every sale (all cashiers)** for them to see everyone's. The **Cashier** role has only the first one.

Create a custom role

1. Click **New role**.
2. Type the **Name** (the **Key** is created automatically) and a **Description**.
3. In **Copy permissions from**, choose the starting role, for example **Cashier**.
4. Click **Create role**, check the permissions to add, then **Save**.

5. Assign this role to the right people in **Users**.


To delete a custom role, open it and click **Delete**. Deletion is refused as long as someone still has this role.

> **Tip:** the **Accountant** and **Inventory clerk** roles are examples of custom roles: adapt them to your store.

Settings

General store settings

The **Settings** page needs the **Manage store settings** permission (owner, administrator, manager). Its tabs: **General**, **Business information**, **Receipts & printing**, **Loyalty**, **Tax rates**, **Payment methods**, **Branches & registers**, **Warehouses & locations**, **Offline & security** and **History**.



The General tab

1. In the **General** tab, check the **Store name** and the main **Currency** (3-letter code).
2. Choose the **Default tax rate**, applied to every sale.
3. Set the **Low-stock threshold** and the store's default **Language**.
4. Enter the number of months in **Gift cards expire after (months)**.
5. Check **Prices include tax** if the displayed prices already include tax, and **Allow sales with a total of 0.00** if needed. **Require an open cash session to sell** (on by default) stops the till from charging on a register with no open shift.
6. Click **Save settings**.

Further down in the same tab:

- the **Inventory & purchasing** block: approval thresholds (purchase orders, stock counts), tolerances and **Transfer settings**;

- the Scale labels;
- the Exchange rate card.

> **Tip:** if the **Finish setting up your store** banner appears, click **Create default setup** to set up a branch, a register and payment methods.

> **Tip:** every change is recorded in the History tab, with the date and who made it.

The USD / HTG exchange rate

The store has two rates between the dollar and the gourde. The **Exchange rates** card is at the top of the **Dashboard** and on the **General** tab of the settings. It shows both rates.



The Exchange rates card

Rate	Used to	Example
Sell rate	Turn **gourdes into dollars**: a customer paying in HTG (the amount asked and the value received), a paid-in or a variance in HTG.	1 USD = 135 HTG: a 10 USD item costs 1,350 HTG.
Buy rate	Turn **dollars into gourdes**: change given in HTG when the customer paid in dollars.	1 USD = 130 HTG: 10 USD of change is 1,300 HTG.

When the customer pays in gourdes and gets change in gourdes, the change is worked out directly in gourdes, with no rate spread: 2,000 HTG given for 1,350 HTG due gives back 650 HTG.

When the store works in gourdes

The rates are always written with the store's currency first:

Store currency	The rate is written	Paying in the other currency
Dollars (USD)	1 USD = 135 HTG	A customer paying in HTG: **sell rate**. Change given in HTG: **buy rate**.
Gourdes (HTG)	135 HTG = 1 USD	A customer paying in USD: **buy rate**. Change given in USD: **sell rate**.

The names do not change: the sell rate turns gourdes into dollars, the buy rate turns dollars into gourdes. In a gourde store, a customer who pays 10 USD at a buy rate of 130 HTG = 1 USD has paid 1,300 HTG.

Change the rates

1. On the **Exchange rates** card, click **Update rate**.
2. Type the **Sell rate** and the **Buy rate**, for example 135 and 130: the number of gourdes for one dollar, whatever the store's currency. Leave one empty to use the same rate for both.
3. To accept another currency, click **Another currency** (or **Add a currency** if only one currency is accepted).
4. Click **Save rates** (or **Cancel**).


New rates apply to new sales right away. Sales already made keep their rates; a return follows the rate of the original sale.

> ⚠ **Warning:** check the rates every morning before opening the tills. A wrong rate makes the amounts asked and the change given in HTG wrong.

> 💡 **Tip: History** shows past sell and buy rates, with the date and who changed them.

Business information and logo

This information is printed on every receipt and every invoice.



The Business information tab


1. Open the **Business information** tab.
2. In **Store logo**, upload a JPEG, PNG or WebP image of 2 MB or less.
3. Fill in the **Store (trading) name**, the **Legal / company name**, the **Tax ID (NIF / VAT / TIN)** and the **Business registration no.**
4. Complete the address, phone, email and website.
5. Write your **Return policy**.
6. Click **Save changes**.

> **Tip:** a black-and-white logo prints better on thermal paper. Leave the address empty to use each branch's address.

Receipts and printing

1. Open the **Receipts & printing** tab.
2. Choose the **Receipt model**: **Classic**, **Compact**, or **Modern**.
3. Choose the **Paper** (80 mm or 58 mm roll, A4 or Letter) and the **Text size**.
4. Enter the **Copies per sale** (2 for a customer copy and a store copy). With JodaPrint, each copy is cut before the next one.
5. Write the **Receipt header** and the **Receipt footer**.

6. Under **Show on the receipt**, check what should appear: logo, cashier, customer, loyalty points, barcode, return policy…
7. Look at the **Preview**: it updates with every change.
8. Click **Save**.



The Receipts & printing tab

> **Tip:** when the logo already shows the company name, set **Name under the logo** to **Branch name**: each receipt then shows the branch where the sale was made (for example "TOP Printing"). Estimates, pro forma invoices and credit notes follow the same choice, and show the logo too. The branch name is set in **Settings › Branches & registers**.


> **Tip:** check **Print automatically when a sale is completed** to save time. **Print test receipt** checks the result on paper.

> **Tip:** keep the sale-number barcode: scanning it finds the sale during a return.

> **Tip:** the other documents (estimates, purchase orders, customer and supplier statements, report PDFs) print on **US Letter** paper. To use A4, change **Paper for other documents**. The Z-report and the credit note follow the receipt paper.

Branches, registers and sale numbering

A branch is a physical store. Each register belongs to a branch.



The Branches & registers tab

Create a branch

1. In the **Branches & registers** tab, click **New branch**.
2. Fill in the **Name**, the **Code**, the address, the **Timezone** (America/Port-au-Prince) and the **Currency**.
3. Click **Create branch**.

The **Code** is used as the prefix for sale numbers: MAIN-000123, DT-000045… Each branch has its own sequence. Choose short, clear letters. Older sales keep their original number (for example S-000544).

Create a register


1. Under **Registers**, click **New register**.
2. Choose the **Branch** and the **Stock location** the register takes sold items from.
3. Choose the **Drawer policy**: **One cashier per drawer** or **Shared drawer**.
4. Click **Create register**.

In a register's details, the **Cash drawers** section lists its drawers: **Add drawer**, **Activate** or **Deactivate**.

> ⚠ **Warning:** a register without a stock location cannot sell.

Warehouses and stock locations

Stock is kept in **locations** (shelf, stockroom, aisle) inside a **warehouse**.



The Warehouses & locations tab


1. Open the **Warehouses & locations** tab.
2. Click **New warehouse** to add a stockroom or depot.
3. Under **Branch warehouses**, check the warehouses each branch works with, then click **Save** on the row. Only people with access to all branches can change this.
4. Under **Stock locations**, click **New location**. Choose its type (**Zone**, **Aisle**, **Bin**, **Sales floor**, **Transit**) and its stock state (**Sellable**, **Damaged**, **Quarantine**).

> 💡 **Tip:** only stock in sellable locations can be sold. Quarantine or damaged-goods locations hold stock that is not sold.

Tax rates

1. Open the **Tax rates** tab.
2. Click **New tax rate**.

3. Enter the code, name and rate as a percentage.
4. Save. Then choose the default rate in the **General** tab.




The Tax rates tab

> **Tip:** to tax some products at a different rate (or exempt them), create a tax category and assign it to the products.

The loyalty program

1. Open the **Loyalty** tab.
2. Check **Run a loyalty programme**.
3. Set **Points earned (% of each sale)**, the **Value of one point**, the **Minimum points to spend at once** and the **Max share of a sale paid with points**.
4. Read the **Example** at the bottom: it updates with your numbers.
5. Click **Save**.




The Loyalty tab

> **Tip:** if you turn off the program, customers keep their points; they simply can no longer earn or use them.

Payment methods

1. Open the **Payment methods** tab.
2. Click **New payment method**, or the pencil of an existing method.
3. Choose the type: cash, card, mobile payment (MonCash), bank transfer, store credit…
4. Say whether the method **Opens the cash drawer** and whether it **Requires a reference** (a MonCash transaction number, for example).
5. Save.




The Payment methods tab

> **Tip:** an inactive method disappears from the till but stays in the sales history. The name shown at the till is the one entered here.

Offline and security

1. Open the **Offline & security** tab.
2. Set the **Offline selling window (hours):** after this time without a connection, the till locks.
3. If needed, set **Largest offline sale**, **Offline sales per window** and **Offline sales total per window** (0 = no limit).
4. Check **Require two-factor authentication for admins** if you want to enforce it.
5. In **Takes effect**, leave it empty to apply right away, or choose a future date.
6. Add a **Note (optional)**, then click **Save**.



The Offline & security tab

Setting	Meaning
Offline selling window (hours)	How long a till can sell without a connection.
Largest offline sale	Above this, the sale is recorded but sent to the Review queue.
Offline sales per window	Maximum number of offline sales before the till must reconnect.
Offline sales total per window	Maximum total amount sold offline.

When two-factor authentication is required, people who manage users, roles, settings or the audit log must turn it on: until they do, they land on **Account security** when they sign in.


> ⚠ **Warning:** tell the administrators before checking this box: each of them needs an authenticator app on their phone (see Turn on two-factor authentication).

Schedule a change and view the history

Several settings offer a **Takes effect** field: the change applies automatically at the chosen date and time.

> ⚠ **Warning:** the effective time must be in the future, or empty to apply right away ("Choose a time in the future, or leave empty").

1. Open the **History** tab.
2. Each row shows the **Version**, the **Status** (**applied**, **scheduled** or **cancelled**), **Effective**, the **Changed** settings and the author (**By**).
3. Click **View** to see the details of a version.
4. To drop a **scheduled** change, click **Cancel** on its row.



The History tab

Scale labels (weighed items)

A label scale prints a barcode that contains the item code (PLU) and the weight or the price. The till can read it if the format is set.

1. Open **Settings**, **General** tab, **Scale labels (weighed items)** section.
2. In **Prefixes read as scale labels**, select the prefixes your scale uses (barcodes starting with 20 to 29). No prefix selected: scale labels are turned off.
3. Choose what **The label holds**: **The weight** or **The price**.
4. Set the **PLU digits** (after the prefix) and the **Decimals of the value** (2 = cents; 3 = grams read as kg), as in the scale's manual.
5. Click **Save settings**.


In each product sold by weight, enter the same code in **PLU (scale code)** (see Units and products sold by weight).

> **Tip:** do a test: weigh an item, scan the label at the till and check the line's quantity and price.

Hardware and system

Hardware: printer, cash drawer and scanner

Receipts print straight to the thermal printer through **JodaPrint**, a small program installed on the till computer. It works with USB and network printers and opens the cash drawer. Without it, receipts go through the browser's print dialog. The **Hardware** page needs the right to manage hardware (owner, administrator, manager).



The Hardware page

Print with JodaPrint

The JodaPrint agent is installed and activated once on each till computer. Then:

1. In the admin area, click **Hardware**.
2. Under **Receipt printer (JodaPrint)**, check the status **Connected · version …**.
3. Choose the receipt printer in the list and its **Paper width** (80 mm or 58 mm). The printer with the alias "receipt" in the JodaPrint dashboard is chosen by default.
4. Click **Print a test receipt**.
5. The test receipt starts with a small framed picture. If it prints as symbols instead, choose **Logo format** > **Column (older printers)** and print the test again: the store logo then prints the same way.

Status	Meaning
Connected · version …	All good: receipts print without the print dialog.
Not found on this computer	The agent is not installed or not started. Click **Download JodaPrint**, install it, then **Refresh**.
Installed, not activated	Activate the agent with your JodaPrint account.
Refused by the agent	The till's address is not allowed: add it in the JodaPrint dashboard (**Developers › Origins & security**).
Not set up on the POS server	The technician must add the JodaPrint signing key on the server.

⚠ **Warning:** without an Internet connection the till cannot get the print signed: receipts then go through the browser's print dialog, and the drawer opens with its key.

💡 **Tip:** the printer and paper width are kept in the till's browser: choose them on each till.

Label printer

Product labels (1 × 1 inch) print on a label printer through JodaPrint, without the browser's print window.

1. In the JodaPrint dashboard, give the label printer the alias **label**. It is then chosen by default.
2. On the **Hardware** page, under **Label printer**, check that the right printer is chosen, or choose it in the list.
3. Load a roll of 1 × 1 inch labels and click **Print a test label**.

Labels are printed from the product list: see The product list and labels.

💡 **Tip:** the label printer is chosen on each computer. Do it once on every computer that prints labels.

Older method: the print bridge

The **print bridge** is the older way to print, for network printers only. Tills that use JodaPrint do not need it.

Your technician installs the bridge once. Then, on the till PC:

1. Start the print bridge: its window shows a 6-digit **Pairing code**.

2. In the admin area, click **Hardware**.
3. Under **Receipt printer (print bridge)**, type the code in **Pairing code**.
4. Leave the **Bridge address** as is (http://127.0.0.1:17777), unless your technician says otherwise.
5. Click **Pair**. The status changes to **Paired**.
6. Click **Print a test receipt**.

Status	Meaning
Not running	The bridge is not running on this PC. Start it.
Running, not paired with this browser	Type the pairing code.
Paired · version …	Everything works.

⚠ **Warning:** pairing is specific to each browser and each till: do it again if you change PC or browser. **Unpair** removes the pairing.

Tip: after several wrong codes, the bridge shows a new code. After 10 errors from the same page, that page can no longer pair (the POS still can); after 50 errors in all, you must restart the bridge in pairing mode.


Drawer, scanner and display

- **Cash drawer**: **Test drawer kick** sends a single pulse. Make sure nobody is standing in front of it.
- **Barcode scanner**: set the suffix (**Enter**, **Tab** or none), the minimum number of characters and the timings, then click **Save scanner settings**. Test in **Scanner test**.
- **Customer display**: **Open customer display** opens a second window to place on the screen facing the customer (see The customer display).

These settings are kept in the till's browser: set them on each till. The page also lists the **Supported devices**.

Devices (registered tills)

Each browser that opens the till registers itself as a **Device**. The **Devices** page (owner, administrator) shows their status.



The Devices page

1. At the top, three counters: **Active devices**, **Offline sales waiting** and **Devices needing attention**.
2. **Sync status** shows, per till, the unsynced sales, the retries, the sales to check and the cases to review.
3. Click **Refresh** to update the figures.

Further down, each device shows its **Status**, **Last seen**, **Last sync**, its **Pending** sales and the **Offline until** date (end of its permission to sell without Internet). **Expired** means the till has not connected for too long; each reconnection renews the permission.

> **Tip:** an unsent amount other than 0 means a till is holding offline sales. Reconnect it as soon as possible.

Import unsynced sales

If a till can no longer connect, a manager exports its sales from the till (**Offline sales** window, **Export unsynced sales**).

1. Click **Import unsynced sales**.
2. Choose the exported file and the original till in **Till the sales come from**.
3. Click **Import**. A summary shows the sales recorded, already received, to check and to retry.


Rename, revoke, mark lost

Button	When	Effect
Rename	Give a clear name ("Till 1 - counter")	No other effect.
Revoke	A till must no longer sell offline (PC replaced, doubt)	It loses this right at once; people signed in on it are signed out. **Restore** undoes the revocation.
Mark lost	PC or tablet stolen, lost or abandoned	Permanent revocation, sessions closed, unsent sales refused; a "Till marked lost" case opens in the Review queue.

> ⚠ **Warning: Mark lost** cannot be undone. First check whether unsent sales remain and try to export them.

The audit log

The audit log records every sensitive action: who did it, who approved it, and what changed. Entries can never be edited or deleted.



The audit log

1. In the menu, click **Audit log**.

2. Type an action in **Filter by action, e.g. sale.voided**.
3. Choose an **Event type** if needed.
4. Click the arrow on a row to see the details (**Before** / **After**, IP address, amounts, sale number…).


The **Who**, **Approved by**, **Target** and **Reason** columns answer the usual questions of an audit.

> **Tip:** useful actions: sale.voided (sale voided), user.password_reset (password reset), role.updated (role changed), session.created (sign-in), auth.login_failed (wrong password).

> **Warning:** the full log is only available to people with access to all branches.

System events

This page is for the owner, administrators, and technical support.



The System events page

1. The counters at the top show the delivery lag and the events that are **Pending**, **Failed (retrying)**, or **Dead-lettered**.
2. **Outbox events** lists these events; **Retry** or **Replay** runs an event again.
3. **Reconciliation checks** lists the automatic checks run every day: **Passed**, **Issues found**, or **Running**.

4. Click **Run checks now** to run the checks again, and **Refresh** to update the page.

> ⚠ **Warning:** if a **Dead-lettered** counter or an **Issues found** check is not zero, contact your technical support.


My account

Account security, password and sessions

The **Account security** page holds your personal settings. Everyone can open it:

- at the till: the shield icon at the top right (on a phone: ⋯ then **Account security**);
- in admin: **Account security** at the bottom of the menu.

It contains: **Two-factor authentication**, **Store invitations** (if you have any), **Stores** (if your account has several), **Change password** and **Where you're signed in**.



The Account security page

Change your password

1. In **Current password**, type your current password.
2. In **New password**, type the new one (at least 8 characters).
3. Type it again in **Confirm password**.
4. Click **Change password**.

You stay signed in on this device; all your other devices are signed out.

> ⚠ **Warning:** the old password is always required. If you forgot it, ask an administrator to reset it (see Account locked or forgotten password).

> **Tip:** choose a phrase that is easy to remember but hard to guess (three words and a number). Never write your password down near the till.

See your sessions and sign out other devices

Where you're signed in lists each device where your account is open: browser, system, sign-in date and last activity. The current device is marked **This device**.

1. Look for a device you don't recognize.
2. Click **Sign out this session** on its row.
3. To close everything except the current device, click **Sign out everywhere else** (the number shows how many sessions will be closed).

> **Tip:** do this if you forgot to sign out on a shared PC or after losing a phone, and change your password too.

Turn on two-factor authentication (2FA)

Two-factor authentication adds a 6-digit code shown by an app on your phone. Even if someone steals your password, they cannot sign in without your phone.

First install an authenticator app, for example Google Authenticator, Microsoft Authenticator or 1Password.

1. In **Account security**, in the **Two-factor authentication** section, click **Turn on**.
2. Enter your current password, then click **Continue**.
3. Open the app on your phone and scan the QR code shown.
4. If you cannot scan, type into the app the key shown under **Can't scan? Enter this key manually:**.
5. Type the 6-digit code the app shows.
6. Click **Verify and turn on**.

The **Status** changes to **On**. Each time you sign in, the code is asked for after your password (see Enter the code).

> ⚠ **Warning:** never show the QR code or the key to anyone else, and never take a photo of them.

> **Tip:** to stop before the end, click **Cancel**: nothing is turned on until you click **Verify and turn on**.

To turn it off, click **Turn off** and type a current code from the app. To change phones, turn it off with the old phone, then turn it on with the new one.

> ⚠ **Warning:** if the store requires two-factor authentication for administrators (see Offline and security), those people land on this page when they sign in, with the message **Two-factor authentication is required**, and must turn it on before doing anything else.

Invitations and switching stores

Accept or decline an invitation

When another store adds your email address and you already have an account, you receive an invitation. It appears in **Store invitations** (on the **Account security** page) and at the top of the **Dashboard**, with the store name and the role offered.

1. Read the store name and the **Role** offered.
2. Click **Accept** to work in this store, or **Decline** if you don't know it.

You keep your password: the store that invites you does not know it.

> 💡 **Tip:** if two-factor authentication is required for you, turn it on first: the invitations then appear.

Switch stores

If your account belongs to several stores, the **Stores** section appears on **Account security**: "Your account belongs to several stores. Choose the one to work in."

1. Open **Account security**.
2. In **Stores**, the active store is marked **Current**.
3. Click **Switch** next to the other store.
4. The app reloads your permissions for that store and opens the till or the admin area.

> 💡 **Tip:** to change branch or register within the same store, use the register list at the top of the till screen instead.

FAQ

FAQ: at the till

The cashier cannot apply a discount

A cashier can give a discount up to the store limit; above that, they must write a reason, and the **Manager approval needed** window opens at checkout. A manager who is present types their email and password, then clicks **Approve** (see Get approval). If no manager is around, lower the discount or put the cart on hold.

The approval window rejects the manager

- The manager must have the requested permission themselves: another cashier cannot approve.
- They must not be the person signed in: you cannot approve yourself.
- If they use two-factor authentication, they must type the 6-digit code.
- An approval lasts 2 minutes and covers one action only: start again if the time has run out.

"Not enough stock" or "Only … in stock"

The till will not sell more than the available stock. Check the shelf and the stockroom. If the real stock is higher, a manager adjusts the stock, then the sale can continue. Offline, the sale is accepted but a case opens in the Review queue.

The till will not sell

- The shift is not open and the store requires one: open the shift.
- The shift is in **Counting**: click **Back to selling** or finish closing.
- The **Offline selling is paused** screen: see Sell offline.

"No product found for …"

The scanned barcode is not linked to any product. Search for the item by name; a manager can add this code to the variant (see Barcodes).

FAQ: offline

The till is offline

The badge at the top changes from **Online** to **Offline.** Don't panic: the till keeps selling for the allowed time (24 hours by default). Sales are kept on the device and then sent automatically when the Internet comes back.

Check the cable, the Wi-Fi or the router. As soon as the connection comes back, leave the till open for a few minutes so it can send its sales. The manager follows the upload on the Devices page.

The till is blocked and refuses to sell offline

The offline selling time has run out, or an offline sales limit has been reached. Reconnect the till to the Internet: the permission renews at once. If the screen says the clock went backward, fix the device's date and time.

If the till really cannot connect anymore, export its sales (**Offline sales** window, **Export unsynced sales**). A manager imports them from the **Devices** page.

An offline sale is "Needs review"

The server refused the sale and shows the reason (stock, price, shift…). Have a manager fix the cause, then click **Retry** in the **Offline sales** window.

Account locked, forgotten password, access denied

My account is locked

After 5 wrong passwords (or 2FA codes) in a row, the account is locked for 15 minutes. The sign-in page shows: "Too many failed attempts. This account is locked for a few minutes."

1. Wait 15 minutes without trying again: each new wrong attempt extends the lock.
2. Check that Caps Lock is not on.
3. Try again with the correct password.

> ⚠ **Warning:** if your account locks when you did not try to sign in, someone may have tried to get in. Tell the owner and change your password.

I forgot my password

On the sign-in page, click **Forgot password?**: you receive an email with a link to choose a new password (see Forgot your password). No email? The owner or an administrator can click the key icon on your row in **Users** and give you a new password (see Reset the password); then change it yourself in **Account security**.

A new employee cannot sign in

Check in **Users**:

- their **Status: Suspended** blocks access;
- the note "Invited — waiting for acceptance": the person already had an account and must accept the invitation in **Account security** (see Invitations);
- their email: a typo prevents sign-in.

The role change does not apply

A change of role or permissions applies the next time the page loads. The person is also signed out when their role changes: they just need to sign in again.

A page or button is missing

Your role does not give access to that page or action. Ask the administrator to check your permissions (see Understanding roles).

FAQ: sales and currencies

I can't void a sale

Voiding needs the **Void sales** permission (manager, administrator, owner); a cashier can do it with a manager's approval. It is also refused when:

- the sale's shift is already closed (or, with no shift, the sale is more than 24 hours old);
- the sale already has a return or a refund;
- the sale was paid through a connected card terminal.

In these cases, do a return: it puts the stock back and refunds the customer while keeping a clean record.

> **Tip:** a refusal message may read, for example, "This sale's shift is closed: use a return instead of a void": the shift is closed, so do a return.

The exchange rate changed

A manager updates the rate on the **Exchange rates** card (see Exchange rate). The new rate applies right away to new sales. Sales already made keep their rate: an old receipt never changes, and a return follows the amount of the original sale.

I can't see another branch's sales

Your account is probably limited to certain branches. Ask an administrator to change your **Branch access** in **Users**.

FAQ: printer and cash drawer

The printer does not respond

Open **Admin** > **Hardware** and read the print bridge **Status**:

- **Not running**: the bridge is not started on this PC. Start it or restart the PC.
- **Running, not paired with this browser**: type the pairing code shown by the bridge, then click **Pair**.
- **Paired**: check that the printer is on, has paper and is properly plugged in.

Then click **Print a test receipt**. In the meantime, receipts print through the browser's print window.

The cash drawer does not open

The drawer opens through the receipt printer: check the printer first. It only opens for payments set to **Opens the cash drawer** in Payment methods. To test it, use **Test drawer kick** in **Hardware**: click only once, the drawer kick is never repeated automatically.

The barcode scanner adds the wrong items

Set the suffix and the minimum number of characters in **Hardware** > **Barcode scanner**, then check in **Scanner test** that the scanned code is complete.

FAQ: reports and exports

A report doesn't show cost or margin

These columns require the permission to view costs. The owner, administrator, and manager have it by default; an accountant does not, unless it is added in Roles and permissions.

An export's download link no longer works

Each link is valid for 15 minutes. Go back to **Reports**, **Background exports** area, and click **Download** again. If the export is more than 24 hours old, it is **Expired**: run it again.

The report shows only part of the sales

- Check the selected period and branch.
- An account limited to certain branches sees only their figures.
- The business day can start after midnight (see Business day): a sale at 2 a.m. can count for the previous day.

Why is a date rejected?

To prevent typing mistakes, the app checks dates. Often, the calendar does not even offer the dates that are not allowed.

Where	Rule	Message
Expense: **Date**	Not in the future	"The expense date cannot be in the future"
Supplier invoice: **Invoice date**	Not in the future	"The invoice date cannot be in the future"
Supplier invoice: **Due date**	Not before the invoice date	"The due date cannot be before the invoice date."
Supplier payment or credit	Not in the future	"The date cannot be in the future"
Purchase order: **Expected delivery**	Not in the past	"The expected delivery date cannot be in the past"
Customer: date of birth	Not in the future, not before 1900	"The date cannot be before 1900"
Discount, price list: end of validity	After the start and not in the past	"Must be after the start date", "The end date cannot be in the past"
Estimate: **Valid until**	Not in the past	"The valid-until date cannot be in the past"
Settings: **Takes effect**	In the future, or empty	"Choose a time in the future, or leave empty"
Employee: hire date	At most one year ahead	"The hire date cannot be more than a year ahead"
Employee: last day	Not in the future, not before hire	"The termination date is before the hire date"
Attendance: entered times	Not in the future, clock-out after clock-in, 24 h maximum	"The time cannot be in the future"…
Periods (reports, sales, shifts, statements)	Start ≤ end	The end cannot be before the start

Tip: a date already saved that is now in the past (for example the end of an old estimate) can be kept as is; the rule applies when you enter or change the date.