Introduction to Computer Organization


DIS 1H – Week 9

Agenda

- I/O
- Virtual Memory
- Linking
- OpenMP lab

The more hardware-ish viewpoint

A hypothetical logical interconnection:



- Things to note:
- Despite the variety of components (CPU, memory, devices), most things are linked together via a "bus".
- A bus is essentially a collection of wires that can be used to transfer data.
- In this example the processor is not connected to the cache via the bus. Generally, we want at least the L1 cache to be as close to the processor as possible.

- Things to note:
- Devices are not directly connected to the bus.
 They are connected via an I/O controller.
- What are the trade-offs of having everything connected via a single bus?

 What are the trade-offs of having everything connected via a single bus?

Pros:

- Simple from a hardware standpoint. Requires few components/little space.
- Transparency between devices. Each device can snoop on the bus and know exactly what's going on. This is a very nice property if you have multiple processors sharing memory via a bus.

· Cons?

 What are the trade-offs of having everything connected via a single bus?

Cons:

- You could potentially have many devices competing for a single resource. The bus becomes a huge bottleneck.
- Bus arbitration logic. If a device wants to use a bus, it needs to fight the other devices for the right to use the bus. There is only one winner.

- Things to note:
- The wires of the bus fall into several categories and serve different purposes (data, address, control).
- Through the bus, each of the controllers can communicate with the other controllers (depending on the complexity of the controller)

- Computer architecture and interconnection is not standardized because different goals require different interconnections.
- There are, however, common features that you should be aware of so that you will be able to understand more practical/realistic arrangements.

- At the processor, how are commands given to I/O devices?
- Memory Mapped I/O: Portions of the address space are assigned to represent an I/O device.
 - movl (0x1234), %eax
 - The address and operation are sent over the bus.
 The memory system recognizes that the address corresponds to an I/O device and doesn't respond.
- Special I/O assembly instructions.

- Now that the processor has issued a request to a device, how does the I/O device respond back to the processor?
 - Polling
 - Interrupt driven I/O
 - Direct Memory Access

Polling

- When the I/O device has a result ready for the CPU, it indicates it or puts the result in a register.
- When the CPU expects a result, it must manually go and check the registers to see if it has a delivery.
 If there is, the CPU goes and gets the result.
- If the CPU must wait before continuing, it can issue a request and do nothing other than continually poll the register until a result is received.
- What about if a CPU isn't explicitly waiting for something (like a mouse/keyboard action)?

Polling

- What about if a CPU isn't explicitly waiting for something (like a mouse/keyboard action)?
- The CPU will have to spend a lot of time checking the status register to make sure there isn't some result that it has to handle.
- This is a waste of time.

Interrupt Driven:

- When an I/O device has a result. It will modify a status and cause register and inform the CPU by explicitly sending an interrupt.
- Once the currently running instruction completes, the CPU will handle the exception and read the registers if necessary to decide how to handle the I/O.

- Both interrupt-driven and polling simply inform the CPU of when it can fetch data and the CPU is ultimately responsible for getting the data.
- If the CPU is spending time fetching data from I/O devices, it's not running the program that it's supposed to be running. Program execution is halted.
- As a result, these methods work fine for small data transfers but don't work very well for large and slow data transfers (like reading from disk).

- When the processor reads to disk, the processor will be copying from disk to RAM.
- What a bore.
- If only the CPU could spend it's time running the program and the "disk controller" could access memory... directly.

- Direct Memory Access (DMA)
- Turns the I/O controllers into small CPUs, each of which can access the bus and do work such as transferring data.
 - 1.Processor issues request informing the DMA controller what to do.
 - 2.Processor goes back to doing it's job. Meanwhile the DMA controller arbitrates for the bus and attempts to do the data transfer to memory.
 - 3. When the DMA is done, it informs the CPU via an interrupt.

 In this way, the processor can do the haughty processor work without having to sully itself with the petty matters of the proletariat (I/O devices).

What this means for you

 When it comes to applications, how can they make use of this I/O structure?

What this means for you

- Initiate the low level interactions by simply calling syscalls:
- open()
- read()
- write()
- · close()

Memory

- We covered caches and why it was necessary to have them.
- Recap: We need DRAM/Main Memory since we need some "large memory" in order to adequately contain our program's addressable space.
- Unfortunately, this large memory is too slow to be our primary source of satisfying memory accesses.
- Cache to the rescue.

Memory

- We now have an adequate model for describing how a program is executed.
- Instruction addresses are fed into the processor and memory accesses generally must be satisfied by the cache.
- Memory addresses range from 32, 48, and 64
 (?) bits. If we consider the 32 bit case, this
 implies that our memory must have a capacity
 of 2^32 bytes.

Memory

- That suggests that main memory must be at least 2^32 or approximately 4 GB.
- But that can't be right, computers can function just fine with less memory than that.
- ...for that matter even if you had 4 GB of memory, how could you run multiple processes if each process expects to have 4 GB of personal memory space.
- What if a computer was running 100 processes?

- Addresses that are known to a program are actually virtual addresses in a scheme known as virtual memory.
- Each process expects to be the sole owner of 2^32 bytes of memory, but it would be impractical to have actually that much DRAM
- Instead, we can simply allow each process to believe that they own the entire addressable space.

- In reality, the physical memory must be shared between all of the processes.
- The actual contents of each process' memory must actually be stored on the much larger (but much slower) disk.
- Main memory thus becomes a "cache" for the virtual memory on disk.

- Memory (both virtual and physical) is split up into a number of "pages".
- Each page is just a contiguous chunk of memory of a set size.
- When a process accesses memory, it uses a virtual address. If the physical memory contains the "page" that the virtual address belongs to, get the value from memory.
- If not, page fault, you'll have to find the page on disk, then copy it to physical memory.

 Wait... so each process expects ~4 GB of memory which is stored on disk instead. That means if I have 100 processes, I need ~400 GB of disk space, just to store the memory spaces of all of the programs?

- Not all pages are actually "allocated". This means they don't exist anywhere. This allows processes to only take up as much space as they need.
- For example, if pages are 4KB and the program has not defined any use for memory address range 0x01000000 to 0x01001000, then there's no need to have that page allocated in memory.

- If physical memory is a "cache" for the virtual memory on disk, where in physical memory is each physical page assigned?
- IE: Consider the page that spans virtual addresses:
- $0x0000 \rightarrow 0x1000$
- Where in physical address should that belong to?

- Physical memory is like a "fully set associative" cache. This means that any page that belongs to virtual memory can be located anywhere in physical memory.
- As a result, a real view of physical memory would show that it's a big mess, interleaved with scattered pages from various processes.

- Like a cache, if main memory is full and you need to bring a different page from disk into main memory, some page is going to have to be a victim.
- Keep this in mind for later.
- If the virtual page can be anywhere in physical memory, how do we find it?
- It would be obnoxious to have to search every page in physical memory as we would with a set associative cache.


- When we need to look through main memory for a virtual page, we don't want to have to manually search every page.
- Instead, we maintain a Page Table which maps virtual addresses to physical addresses.
- We will use (part of) the virtual address to index into the table. Each entry in the page table will contain (part of) the physical address that it maps to.

 Consider a page size of ~4 KB or 2^12 bytes. If the addressable space is 32 bits. How many pages could there possibly be in the virtual address space?

- Consider a page size of ~4 KB or 2^12 bytes. If the addressable space is 32 bits. How many pages could there possibly be in the virtual address space?
- 2^{32} bytes * $1/2^{12}$ pages/byte = $2^{32}/2^{12}$ = 2^{20} pages
- Each page is of size 2¹² bytes.

- Virtual Address decomposition.
- [VPN][VPO]
- VPN: Virtual Page Number
 - The index into the page table
- VPO: Virtual Page Offset
 - The byte offset into the page
- Index into the page table with the VPN. The value stored in the page table is the PPN or physical page number.

- Virtual Address decomposition.
- [VPN][VPO]
- Physical Address decomposition.
- [PPN][PPO]
- The VPO and PPO are same since page size are consistent in both virtual and physical address space.



- Ex: Consider a 14-bit virtual address space and a 12-bit physical address space.
- Each page is 256 bytes.
- How is the Virtual Address split in order to index into the Page Table?


- Ex.
- How is the Virtual Address split in order to index into the Page Table?
- Each page has 256 = 2^8 bytes. This means we need 8 bits to represent the page offset (VPO and PPO).
- This means the VPN is 6-bits and the PPN is 4bits.

- Ex.
- Suppose that you're given the following virtual address:
- 011001 00101000
- How many entries in the page table? (note: this
 is the same as asking how many pages there
 are in the memory space)

- Ex.
- Suppose that you're given the following virtual address:
- 011001 00101000
- There are 2^6 different pages in the memory space (2^6 = 2^14/2^8)
- This particular address will access the page table with index 25 (011001).

- Ex.
- Say the entry at the page table entry 25 has the following as the PPN:
 - 0110.
- The reconstructed physical address is:
- [PPN]:[VPO] = 0110 00101000


- Consider 8 bit virtual addresses with a page size of 2^5 bytes. This mean 5 bits for the virtual page offset and 3 bits for the virtual page number.
- There are 2³ pages in this addressable space and thus, the there are 8 page table entries indexed from 0 (000) to 7 (111).
- Each page table entry would contain the mapping to the physical address (PPN).



- Some notes:
- The Page Table is an entity stored in memory, it's not hardware.
- The physical address of the current process' page table is stored in a register (which is backed up in the context switch).
- Each process has its own page table.
- A page table entry will either indicate:
 - Virtual page is in memory at location [PPN: VPO]
 - or Virtual page is not in memory (valid bit = 0). Go to disk
 - The page is either allocated in disk or unallocated.

- More notes:
- The page table look-up process inherently provides one of the other great benefits of virtual memory: isolation between processes.
- Processes can't see the memory of any other process by virtue of the fact that all processes have the same virtual address space.
- Ex. Process 1 has a variable at address 0x10.
 For process 2, address 0x10 refers to something completely different.

- More notes:
- Virtual memory paging, however, also allows for simple explicit memory sharing.
- If you want two processes to share some value of memory, have their page tables point to the same physical address.



More notes:

If a virtual page isn't in main memory, when the page is pulled in from disk, the page table of the process is updated.

However, consider the case when we need to evict a page. The OS can choose to throw out any page belonging to any process.

This means that evicting a page potentially means updating multiple or all page tables, whoever had a reference to that page.


- The fact that the page table is stored in memory should be a red flag.
- For every memory access, we actually need to make two memory accesses?!
 - One to access page table to find where the memory is actually located.
 - One to actually access memory.
- Well actually...

- Because the page table is simply a data structure in memory, it can be cached just like anything else, sharing the instruction or data cache.
- How does this entire process look?

An overview:


- The CPU wants to access memory. It issues a memory address to the Memory Management Unit (MMU). This address is a *virtual address*.
- The MMU takes the virtual address and using the address of the page table, attempts to find the Page Table Entry. This means issuing a request to memory.
- If the MMU receives a valid PTE, then the Physical Address is extracted and the Physical Address is forwarded to the cache + memory etc.
- If the MMU receives an invalid PTE, it means that the data that corresponds to the virtual address is not in RAM. An exception is thrown to get the data from disk into RAM.

Page Table Entry in cache




- 1. CPU issues virtual address to memory management unit.
- 2. MMU issues address of relevant page table entry to cache.
- 3. L1 cache return the page table entry to MMU.
- 4. MMU constructs physical address and sends it to cache

Page Table Entry **not** in cache




- 1. CPU issues virtual address to memory management unit.
- 2. MMU issues address of relevant page table entry to cache.
- 3. Page table entry not in cache. Cache passes page table entry address to memory.
- 4. Memory sends page table entry to cache. PTE is cached in... cache.
- 5. Cache sends page table entry to MMU... and so on.

- Despite being able to cache the page table, we really want to ensure that we don't have to go to RAM in order to get the page table entry.
- As a result, we would like a specialized cache that will only hold page table entries.
- Enter... the translation lookaside buffer.
- Instead of having to go to the cache and then memory to get the page table, lets have a special cache for just the page table.



- Accessing the TLB is the same as accessing a cache; the (virtual) address is split into three components Tag (TLB), Index (TLB), and Offset (VPO).
- Instead of memory data, the TLB simply contains the page table entry corresponding to that virtual address.




Set	Tag	PPN	Valid									
0	03	_	0	09	0D	1	00	_	0	07	02	1
1	03	2D	1	02	-	0	04	-	0	0A	-	0
2	02	-	0	08	-	0	06	-	0	03	-	0
3	07	-	0	03	0D	1	0A	34	1	02	-	0


- Each entry contains the tag, a valid bit, and a PPN.
- At a high level, how does this look?

- Index of abbreviations:
 - VA: Virtual Address
 - VPN: Virtual Page Number (ie the index into the page table)
 - PTE: Page Table Entry (the actual data within a page table entry)
 - PA: Physical Address
 - PTEA: Page Table Entry Address (the address of a particular page table entry)

TLB Hit (the page table is in the TLB)



TLB Miss (the page table is not in the TLB)



Virtual addresses are 14 bits wide
Physical addresses are 12 bits wide

Page table is single-level, with page size of 64 bytes

TLB is four-way set associative w/ 16 total entries.

Question:

How many bits are in VPO? VPN?

Answer: Since page size is 64 bytes, we need log2(64) = 6 bits for VPO.

VPN is (14 - 6) = 8 bits.

Question:

How many bits are in PPO?

PPN?

Answer: Since

VPO=PPO, need 6

bits for PPO.

Need (12-6)=6 bits

for PPN.

Virtual addresses are 14 bits wide

Physical addresses are 12 bits wide

Page table is single-level, with page size of 64 bytes

TLB is four-way set associative w/ 16 total entries.




Figure 9.19 Addressing for small memory system. Assume 14-bit virtual addresses (n = 14), 12-bit physical addresses (m = 12), and 64-byte pages (P = 64).

Virtual addresses are 14 bits wide Physical addresses are 12 bits wide Page table is single-level, with page size of 64 bytes

TLB is four-way set associative w/ 16 total entries.

Question: How many TLB set-index bits do I need? How many TLB tag bits?

Answer: Since there are four sets, we need log2(4) = 2 set-index bits.
There are (8-2)=6 tag bits.

Set	Tag	PPN	Valid									
0	03	_	0	09	0D	1	00	_	0	07	02	1
1	03	2D	1	02	_	0	04	_	0	0A	_	0
2	02	_	0	80	_	0	06	_	0	03	_	0
3	07	_	0	03	0D	1	0A	34	1	02	_	0

(a) TLB: Four sets, 16 entries, four-way set associative


Virtual addresses are 14 bits wide Physical addresses are 12 bits wide Page table is single-level, with page size of 64 bytes

TLB is four-way set associative w/ 16 total entries.

Question: How many TLB set-index bits do I need? How many TLB tag bits?


Answer: Since there are four sets, we need log2(4) = 2 set-index bits.

There are (8-2)=6 tag bits.



(a) TLB: Four sets, 16 entries, four-way set associative

Exercise: Suppose CPU requests to load a value from vaddr **0x03d4**. List the steps. What is the result of translating vaddr?



(a) TLB: Four sets, 16 entries, four-way set associative

VPN	PPN	Valid
00	28	1
01		0
02	33	1
03	02	1
04		0
05	16	1
06		0
07		0

VPN	PPN	Valid
80	13	1
09	17	1
0A	09	1
0B	1	0
0C	1	0
0D	2D	1
0E	11	1
0F	0D	1

(b) Page table: Only the first 16 PTEs are shown


Exercise: Suppose CPU requests to load a value from vaddr **0x03d4**. List

the steps. What is the result of translating vaddr?

Answer: TLB -> Hit, PPN=0x0D.

paddr is: 0x354.

Exercise: Suppose CPU requests to load a value from vaddr **0x023A**. List the steps. What is the result of translating vaddr?



(a) TLB: Four sets, 16 entries, four-way set associative

VPN	PPN	Valid
00	28	1
01		0
02	33	1
03	02	1
04		0
05	16	1
06		0
07		0


VPN	PPN	Valid
80	13	1
09	17	1
0A	09	1
0B	1	0
0C	1	0
0D	2D	1
0E	11	1
0F	0D	1

(b) Page table: Only the first 16 PTEs are shown

Exercise: Suppose CPU requests to load a value from vaddr **0x023A**. List the steps. What is the result of translating vaddr?

Answer: TLB miss, PageTable(0x08) -> Hit, PPN=0x13. paddr = 0x4FA.

Exercise: Suppose CPU requests to load a value from vaddr **0x005F**. List the steps. What is the result of translating vaddr?



(a) TLB: Four sets, 16 entries, four-way set associative

VPN	PPN	Valid
00	28	1
01		0
02	33	1
03	02	1
04		0
05	16	1
06		0
07		0


VPN	PPN	Valid
80	13	1
09	17	1
0A	09	1
0B	1	0
0C	1	0
0D	2D	1
0E	11	1
0F	0D	1

(b) Page table: Only the first 16 PTEs are shown

Exercise: Suppose CPU requests to load a value from vaddr **0x005F**. List the steps. What is the result of translating vaddr?

Answer: TLB -> Miss! PageTable(0x01) -> Miss, pagefault!

Exercise: Suppose CPU requests to load a value from vaddr **0x003A**. List the steps. What is the result of translating vaddr?



(a) TLB: Four sets, 16 entries, four-way set associative

VPN	PPN	Valid
00	28	1
01		0
02	33	1
03	02	1
04		0
05	16	1
06		0
07		0

VPN	PPN	Valid
80	13	1
09	17	1
0A	09	1
0B	1	0
0C	1	0
0D	2D	1
0E	11	1
0F	0D	1

(b) Page table: Only the first 16 PTEs are shown

Exercise: Suppose CPU requests to load a value from vaddr **0x003A**. List the steps. What is the result of translating vaddr?

Answer: TLB -> Miss (Invalid). PageTable(0x00) -> Hit, PPN=0x28. paddr = 0xA3A

Virtual Memory: Hierarchical Page Tables


- The page tables take up a pretty hefty chunk of memory.
- Additionally, the page table pretty much needs to be in memory at all times.
- However, the entire page table corresponds to the entire virtual addressable space. Most programs don't use up that much of the addressable space. As a result, most programs don't need to use most of the Page Table.

- The solution is to use a table structure that allows for only part of the table to be allocated at any given time.
- In the original case, the virtual address was split up as follows:
- Now we split it up like this:
- [VPN1][VPN2][VPO]

- [VPN1][VPN2][VPO]
- This system requires a two-level page table hierarchy.
- As with the traditional case, there is a register that points to the page table except now this register points to the first level page table.
- As before, VPN1 is an index into the L1 Page Table (the use of "L1" here is just a short-hand and not actually a notation that is used).

- Now however, instead of the L1 Page Table containing the physical address that corresponds to virtual address, it contains a physical address to an L2 Page Table.
- VPN2 is used to index into the L2 Page Table.
 Now, the entry in the L2 Page Table will have the PPN.
- Let's see this in action.

The sky is the limit.



- Consider the following:
 - 32-bit physical addresses
 - 10-bit virtual addresses (yes, it's a weird example)
 - [3-bit VPN1][2-bit VPN2][5-bit VPO]
- L1 Page Table located at address 0x10.
- We are issued the address:
- 010 01 00100
- We consult the L1 Page Table.
- How many entries are in the L1 Page Table?

- Consider this example of an L1 page table.
- Because we index into the L1 page table with a 3-bit value, there are 2^3 = 8 entries.
 Each entry is 4 bytes long because they contain an address to another page table in physical memory.
- VPN1 = 010 = 2
- This means we're accessing the entry at address 0x10 (base address of table) + 2(VPN1)*4(sizeof each table entry)

Addr	Entry
0x10	0x1230
0x14	0x1240
0x18	0x1250
0x1c	0x1260
0x20	0x1270
0x24	0x1280
0x28	0x1290
0x2c	0x12a0

- Thus, the L2 page table is at 0x1250. Now we use the VPN2. Because we index into the L2 page table with 2 bits, there are $2^2 = 4$ entries.
- VPN2 = 01 = 1
- L2 Page Table:

Addr	Entry
0x1250	_
0x1254	0xAB
0x1258	_
0x125c	0xCD

The corresponding PPN is 0xAB

- How does this help the problem of page tables taking too much memory?
- In the non-hierarchical case, the 5-bit VPN would result in a 2⁵ = 32 entry table.
- In this example, the L1 page table had addresses for each of its 8 entries, but perhaps only entry 2 is valid.
- This means, we only need to allocate space for one L2 page table to correspond to entry 2.

- This means in order to store this hierarchy, we only need 2³ entries (1 L1 page table) + 1*2² (1 L2 page table) = 12 entries total, instead 32.
- Note however, if every page table was allocated, we'd need 2³ + 8*2² = 40 entries.
- This only helps if we're not using up ALL of our page table entries... which is most of the time.
- Also note, the entries of the L1 Page Table will contain different data from the L2 Page table, which may mean different entry sizes.

- Unlike the other labs, the objective of this lab is simple.
- Premise: You have code that's slow.
- Goal: Make it go fast.
- The End.

- Getting started:
 - Download the openmplab.tgz file from CCLE
 - Copy it to Inxsrv09.seas.ucla.edu (more than ever, USE Inxsrv09 and gcc version 5.2.0)
 - Unzip it.
- To run the unaltered code, use:
 - make seq
 - This will produce an executable called "seq"

- In order to speed it up, you are to use two tools, one familiar and one new (probably):
 - To determine what to speed up: gprof.
 - To speed it up: OpenMP, an API for shared memory, thread based parallelism.

- To use gprof:
- Compile with GPROF=1
 - ex. make seq GPROF=1
- Execute the executable (this produces gmon.out)
 - ex. ./seq
- Run gprof with the executable as the argument
 - ex. gprof seq | less
 - The command gprof seq normally prints out a wall of text. The "| less" redirects the output as input into the "less" command, which allows you to read it more easily.
 - Quit "less" with q.

- The code provided performs a computation using six functions (func0 to func5) located in the func.c.
- You are to speed up the execution of the program by speeding up these six functions.
- How?

- You could use the normal Chapter 5 style optimizations, but we want something powerful that makes uses of multiple processors.
- This means using threads and doing multithreading.
- However, we want to use something a little more powerful and exotic than POSIX threads.
- So exotic that you might never see it again...

- As a result, we use OpenMP
- OpenMP is an extension to C/C++ (and Fortran) that allows for a simple and convenient way of launching threads to do work in parallel among multiple processors.
- Surprisingly, you won't be personally using a bunch of new functions.
- You'll be specifying a bunch of pre-processor directives.

- Yup, these: "#".
- As a refresher, preprocessor directives are statements that are marked with "#".
- Statements marked with these are instructions that tell the processor what to do:
 - #define min(a, b) (a < b ? a : b)</pre>
 - #include <stdio.h>

- The first step of compilation is the preprocessing step where the compiler will find all of the directives and follow the instructions.
- OpenMP exposes an interface for multithreading that is almost purely based on these preprocessor instructions.
- Other than some helper functions defined in omp.h. Ex.
 - omp_set_num_threads(int);
 - omp_get_thread_num();

```
    Ex:
        int main()
        {
            int a = 0;
            printf("%d\n", a);
        }
```

 Say you want to parallelize this so that 4 threads run this code.

```
Ex:
int main()
 omp_set_num_threads(4); //Use 4 threads
 #pragma omp parallel //Define the following
                        //block as parallel code
  int a = 0; //run by each thread
  printf("%d\n", a);
```

```
Ex:
int main()
 #pragma omp parallel
  int a = 0;
  printf("%d\n", a);
```

 If the number of threads is not specified, the default is used. On SEASnet Inxsrv09, this means 32 (the number of processors).

- Upon hitting the block specified by the #pragma omp directive, the single thread of execution branches off into several parallel threads.
- When each thread reaches the end of the block:

```
#pragma omp parallel {
...
```

} ← Here

 ...each thread will wait for all of the other threads before continuing. This is known as a "barrier".

- The "parallel" keyword means "launch threads in parallel"
- This the basis how OpenMP works.
- Synchronization and control can also be done via these directives. Within a parallel block, you can also have other directives that specify things.
- · Such as...

- Only one thread can enter the critical section at a time. Other threads must wait (like semaphores)
- atomic:

#pragma omp atomic
{
 tmp += 1;
}

Only one thread can perform a particular read/write.
 This only applies to single variable that is read/write.

- barrier:
 - +pragma omp barrier
 - All threads must wait here for all threads to complete before continuing.

And much more...

 Back to this example: int main() #pragma omp parallel int a = 0; printf("%d\n", a);

What if a were declared outside of the parallel section?

 Back to this example: int main() int a = 0; #pragma omp parallel a++; printf("%d\n", a);

Is 'a' shared among the 32 threads?

Data sharing:

- By default, a variable declared inside of a parallel block is private to each block.
- By default, a variable declared outside of a parallel block is shared among all of the threads of a parallel block that accesses the variable. In the previous example, "a" was the same "a" among all threads.
- "a" was also the same "a" that was declared before entering the parallel block
- What do we expect to see as an output?

Data sharing:

- Utter chaos
- Because there is no protection of the shared variable and because writes are not atomic, the results are going to be crazy.
- If we want to share the variables in a way that's more graceful and predictable, we'll have to use critical or atomic but then, we'll essentially be doing code in serial.

 A variable within a parallel block can be made private to each thread by using the "private" keyword int main() int a = 0; #pragma omp parallel private(a) a++; printf("%d\n", a);

 Warning: the variable will also be private relative to the original declaration.

```
int main()
{
  int a = 123;
  #pragma omp parallel private(a)
  {
    a++;
    printf("%d\n", a);
  }
}
```

 The "a" inside the block will not be initialized to 123. It will be uninitialized.

 If you do want to make the private variable in the block initialized to the value specified in the original thread, use "firstprivate".

```
int main()
{
  int a = 123;
  #pragma omp parallel firstprivate(a)
  {
    a++;
    printf("%d\n", a);
  }
}
```

The "a" inside the block will now be initialized to 123.

- Loops
- Consider:

```
for(i = 0; i < N; i++)
{
    <PARALLELIZABLE CODE>
}
```

 You can do this with an "#pragma omp parallel" block, but you'll have to manually assign threads to iterations of the loop.

- Loops
- Or you can do this:

```
#pragma omp parallel for
for(i = 0; i < N; i++)
{
    <PARALLELIZABLE CODE>
}
```

...which magics it up for you.

Helpful link-

http://bisqwit.iki.fi/story/howto/openmp/

Final Notes:

- The run times will vary each time you call filter.
- As it turns out, as the SEASnet processor become more burdened, it will actually slow itself down, which will lead to a slower execution time.
- If you think you have a solution, double check your time by running your code repeatedly.
- You are supposed to speed up the "FUNC TIME" as reported by the print statement by 3.5x.

Final Notes:

 When you run the code with GPROF=1, the times will slow down. Example output:

FUNC TIME: .670985

TOTAL TIME: 2.772028

- This suggests that the total amount of time spent by the functions in func.c take up ~20-25%.
- If you actually look at the gprof print out, you may see this:

Final Notes:

```
%
   cumulative
            self self
                          total
time
      seconds seconds calls ms/call ms/call
                                      name
                                      func1
        0.44
               0.44
                      15
                          29.37
                                31.65
61.19
25.03 0.62 0.18 5177344 0.00 0.00
                                      rand2
2.78 0.64 0.02 491520 0.00 0.00 f...
2.78 0.66 0.02 2 10.01
                                      init
                                10.01
```

- This suggests that func1 alone is taking 61% of the time.
- I'm no expert, but I think 20 is like, not the same as 61.

- As it turns out, gprof doesn't take into account blocking I/O time, which is the bulk of what the non-func.c functions do.
- Use your own measurements (get_time)

- Final Notes: Memory Leaks
- According to checkmem, OpenMP loves to leak memory.

```
int a;
#pragma omp parallel
{
  a = 0;
}
```

Even this "leaks memory".

- Final Notes:
- If the memory error printed out by "make checkmem" is "Memory not freed", don't worry about it. Otherwise, go back and double check.
- Make sure to use "make check" to confirm that the output.txt generated by the program is the same as correct.txt. If silent, the files are the same.