
Inhoud

1	Netwerk topologie	2
	1.1 VLAN TABEL	3
	1.2 Subnets	3
	1.3 Addresseringschema	4
	1.4 HSRP schema	5
	1.5 VM schema	6
2	Implementatie-opstelling	6
	2.1 Vlans aanmaken	6
	2.1.1 Algemene configuratie	6
	2.2 Switchports (trunk & access)	6
	2.2.1 SW1	6
	2.2.2 SW2	7
	2.2.3 MLS1	8
	2.2.4 MLS2	8
	2.3 Intervlan routering	8
	2.3.1 MLS1	8
	2.3.2 MLS2	9
	2.4 Routed ports	9
	2.4.1 MLS1	9
	2.4.2 MLS2	9
	2.4.3 R1	9
	2.4.4 R2	9
	2.5 HSRP	10
	2.5.1 MLS1	10
	2.5.2 MLS2	10
	2.6 Remote management & Security instellen	.10
	2.6.1 Algemene configuratie	10

1 Netwerk topologie



1.1 VLAN TABEL

Vlan id	Naam	Beschrijving	Subnet
10	servers	servers	192.168.10.0/24
20	clients	Clients & devices	192.168.20.0/24
99	management	management	192.168.99.0/28
100	native	Native network traffic	1
999	blackhole		

1.2 <u>Subnets</u>

Subnets	Subnetmasker	Gateway	Beschrijving
192.168.10.0/24	255.255.255.0	192.168.10.1	Servers vlan
192.168.20.0/24	255.255.255.0	192.168.20.1	Clients vlan
192.168.99.0/28	255.255.255.24 0	192.168.99.0	Management vlan
192.168.101.0/3 0	255.255.25 2	192.168.101.1	MLS1 <> R1 routed port
192.168.101.4/3 0	255.255.25 2	192.168.101.5	MLS1 <> MLS2 routed port
192.168.101.8/3 0	255.255.25 2	192.168.101.9	MLS2 <> R2 routed port
192.168.101.12/ 30	255.255.25 2	192.168.101.13	R1 <> R2 routed port

1.3 <u>Addresseringschema</u>

Device	Interface / Port	Connect ed device	IPv4 ADDRESS	Subnet Mask	Default Gateway
R1	VLAN 99				
	G0/0	R2	192.168.101.13	255.255.25 5.252	
	G0/1	MLS1	192.168.101.2	255.255.25 5.252	
R2	VLAN 99				
	G0/0	R1	192.168.101.14	255.255.25 5.252	
	G0/1	MLS2	192.168.101.10	255.255.25 5.252	
SW1	VLAN99		192.168.99.4	255.255.25 5.240	
	F0/1	MLS1			
	F0/2	Proxmox -1			
	F0/3	MLS2			
	F0/4	SW2			
	F0/5	Manage ment-pc			
SW2	VLAN 99		192.168.99.5	255.255.25 5.240	
	F0/1	MLS2			
	F0/2	Proxmox -2			
	F0/3	MLS1			
	F0/4	SW1			
	F0/5	SW1			
MLS1	VLAN 99		192.168.99.2	255.255.25 5.240	
	VLAN 10		192.168.10.254	255.255.25 5.0	
	VLAN 20		192.168.20.1	255.255.25 5.0	

	VLAN				
	100	D.1	100 100 101 1	255 255 25	
	F0/1	R1	192.168.101.1	255.255.25 5.252	
	F0/2	MLS2	192.168.101.5	255.255.25 5.252	
	F0/3	SW1			
	F0/4	SW2			
MLS2	VLAN 99		192.168.99.1	255.255.25 5.240	
	VLAN 10		192.168.10.253	255.255.25 5.0	
	VLAN 20		192.168.20.2	255.255.25 5.0	
	VLAN 100				
	F0/1	R2	192.168.101.9		
	F0/2	MLS1	192.168.101.6		
	F0/3	SW2			
	F0/4	SW1			
Manageme nt pc	F0	SW1	192.168.99.8	255.255.25 5.240	192.168.99. 3
Client -1	F0	SW2	192.168.20.10	255.255.25 5.0	192.168.20. 3
Proxmox-1	F0	SW1	192.168.10.20	255.255.25 5.0	192.168.10. 252
DC-1		Proxmox -1	192.168.10.2	255.255.25 5.0	192.168.10. 252
FS-1		Proxmox -2	192.168.10.3	255.255.25 5.0	192.168.10. 252
Proxmox-2		SW2	192.168.10.21	255.255.25 5.0	192.168.10. 252
VM – SM- backup		Proxmox -1	192.168.10.4	255.255.25 5.0	192.168.10. 252

1.4 HSRP schema

Group	Interfa	Virtual IP	Priorit	Preem	Active	Standby
	ce		У	ption	router	router
10	VLAN	192.168.10.25	150	Enable	192.168.	192.168.1
	10	2		d	10.254	0.253
20	VLAN	192.168.20.3	150	Enable	192.168.	192.168.2
	20			d	20.1	0.2
99	VLAN	192.168.99.3	150	Enable	192.168.	192.168.9
	99			d	99.1	9.2

1.5 VM schema

hostname	ip-address	OS	description
DC-1	192.168.10.2	WS2022	Domain-controller
FS-1	192.168.10.3	WS2022	File-server
vm-backup	192.168.10.4	WS2022	Backup-server

2 <u>Implementatie-opstelling</u>

2.1 Vlans aanmaken

2.1.1 Algemene configuratie

vlans is voor alle switches hetzelfde.

```
SW1 # vlan 10
SW1 (config-vlan) # name servers
SW1 # interface vlan 10
SW1(config-if) # description servers
SW1 # vlan 20
SW1 (config-vlan) # name clients
SW1 # interface vlan 20
SW1(config-if) # description clients
SW1 # vlan 99
SW1 (config-vlan) # name management
SW1 # interface Vlan 99
SW1(config-if) # description management vlan
SW1(config-if) # ip address 192.168.99.4 255.255.255.240
SW1 # vlan 100
SW1 (config-vlan) # name native
SW1 # interface vlan 100
SW1(config-if) # description native-vlan
SW1 # vlan 999
SW1 (config-vlan) # name blackhole
SW1 # interface vlan 999
SW1 # ip default-gateway 192.168.99.3
default-gateway & ip-address SVI is verschillend voor SW2
SW2 # ip default-gateway 192.168.99.3
SW2 # ip address 192.168.99.5 255.255.255.240
```

2.2 <u>Switchports (trunk & access)</u>

2.2.1SW1

```
SW1 # interface FastEthernet0/1
SW1(config-if) # switchport mode trunk
```

```
SW1(config-if) # switchport trunk native vlan 100
SW1(config-if) # switchport nonegotiate
SW1 # interface FastEthernet0/2
SW1(config-if) # switchport mode access
SW1(config-if) # switchport access vlan 10
SW1 # interface FastEthernet0/3
SW1(config-if) # switchport mode trunk
SW1(config-if) # switchport trunk native vlan 100
SW1(config-if) # switchport nonegotiate
SW1 # interface FastEthernet0/4
SW1(config-if) # switchport mode trunk
SW1(config-if) # switchport trunk native vlan 100
SW1(config-if) # switchport nonegotiate
SW1 # interface FastEthernet0/5
SW1(config-if) # switchport mode access
SW1(config-if) # switchport access vlan 99
SW1 # interface range F0/6 - 24
SW1(config-if) # switchport mode access
SW1(config-if) # switchport access vlan 999
SW1 # interface range G0/1 - 2
SW1(config-if) # switchport mode access
SW1(config-if) # switchport access vlan 999
```

2.2.2SW2

```
SW2 # interface FastEthernet0/1
SW2(config-if) # switchport mode trunk
SW2(config-if) # switchport trunk native vlan 100
SW2(config-if) # switchport nonegotiate
SW2 # interface FastEthernet0/2
SW2(config-if) # switchport mode access
SW2(config-if) # switchport access vlan 10
SW2 # interface FastEthernet0/3
SW2(config-if) # switchport mode trunk
SW2(config-if) # switchport trunk native vlan 100
SW2(config-if) # switchport nonegotiate
SW2 # interface FastEthernet0/4
SW2(config-if) # switchport mode trunk
SW2(config-if) # switchport trunk native vlan 100
SW2(config-if) # switchport nonegotiate
SW2 # interface FastEthernet0/5
SW2(config-if) # switchport mode access
SW2(config-if) # switchport access vlan 20
SW2 # interface range F0/6 - 24
SW2(config-if) # switchport mode access
SW2(config-if) # switchport access vlan 999
SW2 # interface range G0/1 - 2
```

```
SW2(config-if) # switchport mode access
SW2(config-if) # switchport access vlan 999
```

2.2.3MLS1

```
MLS1 # interface F0/3
MLS1(config-if)#switchport trunk encapsulation dotlg
MLS1(config-if) # switchport mode trunk
MLS1(config-if) # switchport trunk native vlan 100
MLS1(config-if) # switchport nonegotiate
MLS1 # interface F0/4
MLS1(config-if)#switchport trunk encapsulation dotlq
MLS1(config-if) # switchport mode trunk
MLS1(config-if) # switchport trunk native vlan 100
MLS1(config-if) # switchport nonegotiate
MLS1 # interface range F0/5 - 24
MLS1(config-if-range) # switchport mode access
MLS1(config-if-range) # switchport access vlan 999
2.2.4MLS2
MLS2 # interface F0/3
MLS2(config-if) # switchport mode trunk
MLS2(config-if) # switchport trunk native vlan 100
MLS2(config-if) # switchport nonegotiate
MLS2 # interface F0/4
MLS2(config-if) # switchport mode trunk
MLS2(config-if) # switchport trunk native vlan 100
MLS2(config-if) # switchport nonegotiate
MLS2 # interface range F0/5 - 24
MLS2(config-if-range) # switchport mode access
MLS2(config-if-range) # switchport access vlan 999
```

2.3 Intervlan routering

2.3.1MLS1

```
MLS1 # interface Vlan20
MLS1(config-if) # ip address 192.168.20.1 255.255.255.0

MLS1 # interface Vlan99
MLS1(config-if) # ip address 192.168.99.1 255.255.255.240

MLS1 # interface Vlan10
MLS1(config-if) # ip address 192.168.10.254 255.255.255.0

MLS1(config) # ip routing
```

2.3.2MLS2

```
MLS2 # interface vlan 99
MLS2(config-if) # ip address 192.168.99.1 255.255.255.240
MLS2(config) # ip routing
```

2.4 Routed ports

2.4.1MLS1

```
MLS1 # interface F0/1
MLS1(config-if) # no switchport
MLS1(config-if) # ip address 192.168.101.1 255.255.252
MLS1 # interface F0/2
MLS1(config-if) # no switchport
MLS1(config-if) # ip address 192.168.101.5 255.255.252
```

2.4.2MLS2

```
MLS2 # interface F0/1
MLS2(config-if) # no switchport
MLS2(config-if) # ip address 192.168.101.9 255.255.252

MLS2 # interface F0/2
MLS2(config-if) # no switchport
MLS2(config-if) # ip address 192.168.101.6 255.255.252
```

2.4.3R1

```
R1 # interface GigabitEthernet0/0
R1(config-if) # ip address 192.168.101.13 255.255.252
R1 # interface GigabitEthernet0/1
```

R1(config-if) # ip address 192.168.101.2 255.255.255.252

2.4.4<u>R2</u>

```
R2 # interface GigabitEthernet0/0
R2(config-if) # ip address 192.168.101.14 255.255.255.252
R2 # interface GigabitEthernet0/1
R2(config-if) # ip address 192.168.101.10 255.255.255.252
```

2.5 HSRP

2.5.1MLS1

```
MLS1 (config)# interface vlan 10
MLS1 (config-if)# standby version 2
MLS1 (config-if)# standby 10 ip 192.168.10.252
MLS1 (config-if)# standby 10 priority 150
MLS1 (config-if)# standby 10 preempt
MLS1 (config)# interface vlan 99
MLS1 (config-if)# standby version 2
MLS1 (config-if)# standby 99 ip 192.168.99.3
MLS1 (config)# interface vlan 20
MLS1 (config) standby version 2
MLS1 (config-if)# standby 20 ip 192.168.20.3
2.5.2MLS2
MLS2 (config)# interface vlan 10
MLS2 (config-if)# standby version 2
MLS2 (config-if)# standby 10 ip 192.168.10.252
MLS2 (config)# interface vlan 99
MLS2 (config-if)# standby version 2
MLS2 (config-if)# standby 99 ip 192.168.99.3
MLS2 (config-if)# standby 99 priority 150
MLS2 (config-if)# standby 99 preempt
MLS2 (config)# interface vlan 20
MLS2 (config-if)# standby version 2
MLS2 (config-if)# standby 20 ip 192.168.20.3
```

2.6 Remote management & Security instellen

2.6.1Algemene configuratie

```
SW1 # hostname SW1
SW1 # enable secret ****
SW1 # ip domain-name servermaffia.test
SW1 # crypto key generate rsa general-keys modulus 2048
SW1 # username servermaffia secret ****
SW1 # line vty 0 15
SW1(config-line) # password ****
SW1(config-line) # login
SW1(config-line) # login local
SW1(config-line) # transport input ssh
SW1 # line console 0
SW1(config-line) # password ****
SW1(config-line) # login
SW2 # service password-encryption
SW2 # banner motd Unauthorized access is forbidden!
SWZ copy running-config startup-config
Deze configuratie is voor elk netwerk device hetzelfde
```