## P. Partial Differential Equations

An important application of the higher partial derivatives is that they are used in partial differential equations to express some laws of physics which are basic to most science and engineering subjects. In this section, we will give examples of a few such equations. The reason is partly cultural, so you meet these equations early and learn to recognize them, and partly technical: to give you a little more practice with the chain rule and computing higher derivatives.

A partial differential equation, PDE for short, is an equation involving some unknown function of several variables and one or more of its partial derivatives. For example,

$$x\frac{\partial w}{\partial x} - y\frac{\partial w}{\partial y} = 0$$

is such an equation. Evidently here the unknown function is a function of two variables

$$w = f(x,y) ;$$

we infer this from the equation, since only x and y occur in it as independent variables. In general a **solution** of a partial differential equation is a differentiable function that satisfies it. In the above example, the functions

$$w = x^n y^n$$
 any  $n$ 

all are solutions to the equation. In general, PDE's have many solutions, far too many to find all of them. The problem is always to find the one solution satisfying some extra conditions, usually called either *boundary conditions* or *initial conditions* depending on their nature.

Our first important PDE is the Laplace equation in three dimensions:

$$\frac{\partial^2 w}{\partial x^2} + \frac{\partial^2 w}{\partial y^2} + \frac{\partial^2 w}{\partial z^2} = 0.$$

Any steady-state temperature distribution in three-space

(2) 
$$w = T(x, y, z),$$
  $T = \text{temperature at the point } (x, y, z)$ 

satisfies Laplace's equation. (Here *steady-state* means that it is unchanging over time, here reflected in the fact that T is not a function of time. For example, imagine a solid object made of some uniform heat-conducting material (say a solid metal ball), and imagine a steady temperature distribution on its surface is maintained somehow (say with some arrangement of wires and thermostats). Then after a while the temperature at each point inside the ball will come to equilibrium — reach a steady state — and the resulting temperature function (2) inside the ball will then satisfy Laplace's equation.

As another example, the gravitational potential

$$w = \phi(x, y, z)$$

resulting from some arrangement of masses in space satisfies Laplace's equation in any region R of space not containing masses. The same is true of the *electrostatic potential* resulting from some collection of electric charges in space: (1) is satisfied in any region which is free of charge. This potential function measures the work done (against the field) carrying a unit test mass (or charge) from a fixed reference point to the point (x, y, z) in the gravitational (or electrostatic) field. Knowing  $\phi$ , the field itself can be recovered as its negative gradient:

$$\mathbf{F} = -\nabla \phi$$
.

All of this is just to stress the fundamental character of Laplace's equation — we live our lives surrounded by its solutions.

The two-dimensional Laplace equation is similar — you just drop the term involving z. The steady-state temperature distribution in a flat metal plate would satisfy the two-dimensional Laplace equation, if the faces of the plate were kept insulated and a steady-state temperature distribution maintained around the edges of the plate.

If in the temperature model we include also heat sources and sinks in the region, unchanging over time, the temperature function satisfies the closely related **Poisson equation** 

(3) 
$$\frac{\partial^2 w}{\partial x^2} + \frac{\partial^2 w}{\partial y^2} + \frac{\partial^2 w}{\partial z^2} = f(x, y, z),$$

where f is some given function related to the sources and sinks.

Another important PDE is the **wave equation**; given below are the one-dimensional and two-dimensional versions; the three dimensional version would add a similar term in z to the left:

(4) 
$$\frac{\partial^2 w}{\partial x^2} = \frac{1}{c^2} \frac{\partial^2 w}{\partial t^2}; \qquad \frac{\partial^2 w}{\partial x^2} + \frac{\partial^2 w}{\partial y^2} = \frac{1}{c^2} \frac{\partial^2 w}{\partial t^2}.$$

Here  $x, y, \ldots$  are the space variables, t is the time, and c is the velocity with which the wave travels — this depends on the medium and the type of wave (light, sound, etc.). A solution, respectively

$$w = w(x,t), \qquad w = w(x,y,t),$$

gives for each moment  $t_0$  of time the shape  $w(x, t_0)$ ,  $w(x, y, t_0)$  of the wave.

The third PDE goes by two names, depending on the context: **heat equation** or **diffusion equation**. The one- and two-dimensional versions are respectively

(5) 
$$\frac{\partial^2 w}{\partial x^2} = \frac{1}{a^2} \frac{\partial w}{\partial t}; \qquad \frac{\partial^2 w}{\partial x^2} + \frac{\partial^2 w}{\partial y^2} = \frac{1}{a^2} \frac{\partial w}{\partial t}.$$

It looks a lot like the wave equation (4), but the right-hand side this time involves only the first derivative, which gives it mathematically and physically an entirely different character.

When it is called the (one-dimensional) heat equation, a solution w(x,t) represents a time-varying temperature distribution in say a uniform conducting metal rod, with insulated sides. In the same way, w(x,y,t) would be the time-varying temperature distribution in a flat metal plate with insulated faces. For each moment  $t_0$  in time,  $w(x,y,t_0)$  gives the temperature distribution at that moment.

For example, if we assume the distribution is steady-state, i.e., not changing with time, then

$$\frac{\partial w}{\partial t} = 0$$
 (steady-state condition)

2 18.02 NOTES

and the two-dimensional heat equation would turn into the two-dimensional Laplace equation (1).

When (5) is referred to as the diffusion equation, say in one dimension, then w(x,t) represents the concentration of a dissolved substance diffusing along a uniform tube filled with liquid, or of a gas diffusing down a uniform pipe.

Notice that all of these PDE's are second-order, that is, involve derivatives no higher than the second. There is an important fourth-order PDE in elasticity theory (the bilaplacian equation), but by and large the general rule seems to be either that Nature is content with laws that only require second partial derivatives, or that these are the only laws that humans are intelligent enough to formulate.

Exercises: Section 2K