



TEMENOS
The Banking Software Company

Triple'A Plus™ Web

Release 14.03

Report Launcher User Guide



TA
Triple'A Plus™

© 2014 Odyssey Financial Technologies SA

All rights reserved. No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, photocopying, recording, or otherwise, without the prior written permission of Odyssey Financial Technologies.

Odyssey Triple'A Plus™ is a registered trademark of TEMENOS Group. All other trademarks referenced herein are the property of their respective owners.

The Odyssey product suites use a number of third-party software products that are distributed under free or other open source licence agreements. These products are the copyright of their respective owners and are governed by their own licensing terms as indicated in the applicable licence, copying, read-me and/or help files for such products. Copies of the relevant licence agreements for these products can be found in the *Triple'A Plus Open Source Software Licences Reference Guide*.

In its continuous concern for customer satisfaction, Odyssey welcomes your opinion of the contents of this manual. Please send any comments to manuals@odyssey-group.com, including, if necessary, the manual title and page references

Document Revision History

Version	Date	Description
1.20.6	20060713	All MMS references removed
1.30.4	20060325	Screenshots updated Section "Batch Job Details" updated Chapter "6 Using the Report Launcher SOAP API" updated
1.30.5	20080422	Disclaimer updated
	20080909	New API descriptions added (chapter 6)
1.30.6	20090515	Changed title page only to reflect new version. No revisions to other sections of document.
1.30.6 SP1	20091027	Added section for PDF encryption.
11	20110718	OCS-38596: In section Adding jobs , removed information about "Publish to WUI" and "Shared in WUI" as these features are not available.
	20110901	OCS-38301: Updated the following sections by removing information that is no longer relevant: - Subsection Definitions of section Using Report Launcher-Job List, and subsection Definitions of section Using Report Launcher-Batch Monitoring. - Section Using Report Launcher – System Data, including removing sections "Triple'A Plus Universe and Triple'A Plus List job types", "Descriptions of job parameters", and "Triple'A Plus Universe Job Types". - Section API Methods.
12	20120820	Updated title page to reflect new version.
13	20130628	Updated title page to reflect new version.
14.03	20140328	Updated title page to reflect new version.

Contents

1	Introduction	5
2	Using Report Launcher–Job List	6
2.1	Definitions.....	6
2.2	Search criteria	7
2.3	Search results	8
2.4	Managing the Job List data	8
2.4.1	Adding jobs.....	8
2.4.2	Updating jobs.....	9
2.4.3	Deleting jobs	10
2.4.4	Starting selected jobs	10
2.4.5	Starting all jobs	10
2.4.6	Generating jobs	11
3	Using Report Launcher–Batch Monitoring.....	12
3.1	Definitions.....	12
3.2	Batch monitoring.....	12
3.2.1	Batch navigation	12
3.2.2	Batch Logging information.....	13
3.2.3	Batch job details	13
4	Using Report Launcher–Processed Job List	17
4.1	Search criteria	17
4.2	Search results.....	17
5	Using Report Launcher – System Data.....	19
5.1	Financial Servers tab	19
5.2	System Parameters tab	19
5.3	Job Parameters tab.....	20
5.3.1	Portfolio and List Job types.....	20
5.4	Database Cleanup tab	21
6	Using the Report Launcher-SOAP API.....	22
6.1	SOAP API Client	22
6.2	API Methods	26

1 Introduction

There are four sub-modules in the Report Launcher module:

- Job List sub-module
- Batch Monitoring sub-module
- Job List history sub-module
- System data sub-module

2 Using Report Launcher–Job List

The Job List is a sub-module of the Report Launcher module. The Job List prepares the work for report launching. To run the sub-module, click the icon .

2.1 Definitions

Fields	Definition
Job	The generation of Triple'A Plus documents in accordance with the criteria you enter. There are two kinds of jobs: - Recurring jobs. When a job is recurring, it remains in the Job List. The start date of the recurring job is automatically updated according to its <i>frequency</i> after the job has been processed. - Non-recurring jobs. When a non-recurring job is started, the job is removed from the Job List after processing.
Start Date	Indicates when a job can be started manually or if it is scheduled (scheduling is not yet implemented).
Job Type	Can be: <i>portfolio</i> or <i>portfolio list</i>, as defined in Triple'A Plus Core <i>Third Party</i>
Code	Can be: - the code of the portfolio or the portfolio list, as defined in Triple'A Plus Core - the code of the third party, as defined in Triple'A Plus Core
Report Name	The executable report name in Actuate. It is the name of the report (ROX file) to be run for a job type <i>portfolio</i> or <i>portfolio list</i> . In this case, the drop-down list is automatically completed from the existing <code>rox</code> files on the Actuate server.
Calculation Mode	As defined in Triple'A Plus Core. The possible values are: - Merged: all like positions are consolidated. The original portfolios are not kept (useful for management reports on lists, for example). - Detailed: positions are displayed by financial instrument and by portfolio. - Tiled: one report section per portfolio. - Burst: one report per portfolio in the list object. Burst is the most interesting for the bank when launching reports generation for customers.
From Date	An optional field. If not present, it is calculated according to the frequency.
Till Date	An optional field. If not present, it is calculated from the frequency to perform calculations over the last frequency period (last year, last quarter and last month).
Start Date	Starting date of the job. The start date is automatically updated according to the job frequency.
Frequency	Can be one of the following: - Yearly: the report is run in January (for the previous year). - Bi-Yearly: the report is run in January and July. - Quarterly: the report is run in January, April, July and October. - Monthly: the report is run every month. - Daily: the report is run every day.


Fields	Definition
Generation	Can be one of the following: - No print: only ROI files are generated in the encyclopaedia. - Print to defined printer: the printer is defined in the printer_device_device property value in the system parameters. - Print to file through defined printer: generates an output file using a printer driver or a native export to Actuate. - Print and Archive: (i.e., generate a PDF file). Print and generate files.
Destination User	Usually used to generate addresses to which to send the reports. A bean shell script can redefine each calculated parameter value (e.g., if the value of a parameter depends on the values of other parameters). For example, if you need to print the report to a particular printer that is linked to the name of a portfolio, then Report Launcher Server can run a script to determine the value of the parameter "Printer Name". So each value can be defined using a script that returns new parameter values that directly depend on other parameter values.
Job List	Your to-do list
Batch Reference	Reference number that defines a set of jobs started at the same time.

2.2 Search criteria

You can enter the following criteria in the Search pane to search for your jobs:

Criteria	Description
Start Date	Lets you select job lists by their start date. Finds which jobs are started at a specific date.
Code	Finds Jobs whose code starts with the text you enter.
Object Type	Retrieves <i>List</i> or <i>Portfolio</i> type Jobs.
Report Name	rox file name filter.

The example below returns every job whose start date is later than or equal to the date entered:



SearchParameters

Job List

☒ Start Date Jan 13, 2004 ▼

☐ Code

☐ Portfolio ▼

☐ Report Name 3


Search

Search parameters for a job list

2.3 Search results

After you have entered your criteria and clicked **Search**, the results are returned as a table in the query data area. A tree view is created to filter the data area. If you select the Job List node in the filter pane, all search results are displayed in the data pane. If you select the Daily node, for example, only the jobs whose frequency is Daily are displayed.

IMPORTANT: Depending on the settings of the Report Launcher, the results are grouped into pages. Use the arrows of the browsing tool to view the different pages:



Multi-page search result

2.4 Managing the Job List data

When your Search is finished, the results are displayed in the **Data** pane (Job List sub-module). A list of jobs is shown as follows:


+ Add Job <input checked="" type="button" value="Update Job"/> Delete Job Start Job Start All Jobs Generate Jobs						
Recurring	Object Type	Code	Report Name	Frequency	Generation Mode	Calculation Mode
☒	OCS Universe	T_AI_AC_PTF4	Triple'A Private Banking Report (sprea...	Daily	No Print. Only ROI ...	Burst
☒	List	T_AI_BASIC_LI...	std_live_new_pbr_	Daily	No Print. Only ROI ...	Merged
☒	List	T_AI_BASIC_LI...	std_live_new_pbr_	Daily	No Print. Only ROI ...	Merged
☒	Third party	T_AI_Client2	std_live_aimr_	Daily	No Print. Only ROI ...	Merged
☒	OCS List	T_AI_BASIC_LI...	Triple'A Private Banking Report (sprea...	Daily	No Print. Only ROI ...	Burst
☒	Portfolio	T_AI_AC_PTF2	std_live_pa_port_	Daily	No Print. Only ROI ...	Merged
☒	OCS List	T_AI_BASIC_LI...	RLS Standard Valuation Report	Daily	No Print. Only ROI ...	Merged
☒	List	T_AI_BASIC_LI...	std_ocs_pa_port_	Daily	No Print. Only ROI ...	Merged
☒	OCS Universe	T_AI_AC_PTF1	RLS Standard Valuation Report	Daily	No Print. Only ROI ...	Merged

Data pane

2.4.1 Adding jobs

To use this feature, you must have the **Manage Jobs** access right (see the SCD security module).

To add a job, click the **Add Job** button. A dialogue box is displayed with the required fields:



Dialogue box of Add a Job with General tab and User-defined Data tab

Some values in the **General** tab must be validated. The job will not be added if one of the mandatory fields is left uncompleted or if one of the values, such as the Code, is invalid.

The job added must be unique; the combination of the list below must also be unique:


- Calculation Mode
- Object Type
- Generation Mode
- Object Code
- Frequency
- Report Name

If it is not unique, a warning message is displayed in a separate window indicating that the job already exists and therefore, the job will not be created.

2.4.2 Updating jobs

To use this feature, you must have the **Manage Jobs** access right (see the SCD security module).

To update a job, double-click the job that you want to modify in the Job List table or select the job and click **Update**:



Dialogue box of Update a Job with General tab and User-defined Data tab

2.4.3 Deleting jobs


To delete a job, select the job that you want to delete and click the **Delete** button. A message is displayed to confirm the delete.

2.4.4 Starting selected jobs

To start one or more specific jobs, you can select multiple jobs in the data area and click the **Start Job** button. To select multiple jobs, hold down the <Shift> key as you click the jobs.

The start date must be *now or passed* or the job will not be started.

A dialogue box lets you confirm the number of jobs that you are going to start. In the following example, two jobs are selected but only one job can be started at this particular time:



Re...	Object T...	Code	Repor...	Frequ...	Genera...	Calcul...	Language	Currency
☒	List	ALL	std_live...	Daily	No Print. ...	Burst	en	EUR
☒	Portfolio	Becker	std_liv...	Monthly	Print to f...	Merged	en	EUR
☒	Portfolio	FUND_REFER...	std_liv...	Quarterly	Print to f...	Tiled	en	EUR

Start Batch Confirmation message

2.4.5 Starting all jobs

You do not have to select all jobs to use the Start All Jobs feature. It is recommended to use the **Start All Jobs** button so as not to forget to start reports.

The start date must be *now or passed* for the job to start. A dialogue box lets you confirm the number of jobs that you are going to start. When you confirm the start, you receive the number batch reference of what you have pooled.

2.4.6 Generating jobs

To generate jobs, click the **Generate Jobs** button. This command automates the creation of jobs from the Triple'A Plus Core client database.

Note: You can only generate jobs for one frequency at a time due to the potential volume of portfolios. If you want to generate Daily jobs and Quarterly jobs, you must go through the process twice:



Generate job list

`JobParameters` can be used in the Generate Jobs process if set up in the System Data. These values are passed into the Generate Jobs Beanshell.

3 Using Report Launcher–Batch Monitoring

The Batch Monitoring is a sub-module of the Report Launcher module. This sub-module has two objectives:

- Checks the status of the report launching
- Allows easy interaction for user in the case of problems.

To run the Batch Monitoring sub-module, click the icon ()

3.1 Definitions

An **Actuate Request** is a command generated by the Report Launcher to manage Actuate reporting tasks. A Report Launcher job can have one or more Actuate Requests. A job with the **Object Type** *Portfolio* has one or more Actuate requests. A job with the object type *List* in **Burst** calculation mode can have many Actuate requests, depending on the number of portfolios in the list and the requested actions. There is one Actuate Request per portfolio.

3.2 Batch monitoring

To create a Report Launcher Batch, you must start at least one job. Each time that you start a job or a job pool, a new Batch Reference is created.

3.2.1 Batch navigation

By default, the batch navigation marker is set to the latest batch you started. You can use the drop-down list to go to a specific batch.

The **Refresh** button updates the progress of the current batch.

Batch Reference	12 ▼	Refresh (F5)
-----------------	------	--------------

Batch Reference window

3.2.1.1 Global Batch Status view

In the Global Batch Status view, you have a direct, global status view of your batch. The Pending Workload progress bar shows the number of requests that are still waiting (pending).

The Running Actuate Request progress bar shows the number of requests that are currently in progress.

The Completion Rate progress bar shows the completion state of the Actuate requests:

Global Batch Status	
Pending Workload :	
Running Actuate Request :	
Completion Rate :	
2004/01/15 9:39:32	2004/01/15 9:54:59
Start Time	End Time

Global Batch Status

The batch **Start Time** is the exact date and time that you started a job pool.

The batch **End Time** is the time that the process finished or was cancelled.

3.2.1.2 Actuate Request Details view

Actuate Request Details		
	0	Pending
	0	Running
	0	Failed
	0	Canceled
	173	Completed
▶ Total	173	

Actuate Request Details

The Actuate Request Details view shows the batch status in detail.

3.2.1.3 Running state

The following buttons are used to control the run of batch jobs:

- You can **Pause** a batch that is being processed. The **Pause** action temporarily stops the processing of pending actions. However, the running queue continues its work until all the running actions are completed.
- To continue processing the batch from where it was paused, click the **Continue** button.
- The **Cancel** button immediately stops the processing of all the pending actions. The pending actions are then marked as cancelled. However, the running queue will continue its work until all the running actions are completed. Completed and failed jobs are not affected by the **Cancel** command.

3.2.2 Batch Logging information

Batch logs are displayed in table format with a Status column, Creation Date column, and Log column. This batch log table provides you with more information on the batch status. The log statuses are:

	Information: Displays information on what the Report Launcher Server is doing.
	Warning: The Report Launcher Server has detected a possible anomaly but continues its work.
	Error: The Report Launcher Server has failed. This can be because of a script program error, a configuration setting or missing data. The server keeps running but flags the Actuate request job as failed.

3.2.3 Batch job details

In the data table area, all jobs in the batch are displayed:

☐ Status Filter	Completed	Redo Selected Failed Jobs		Redo All Failed Jobs		
Status	Object Type	Code	Report Name	Generation Mode	Calculation Mode	AAA Message
Failed	List	ALL	std_live_new_pbr_	No Print. Only ROI g...	Burst	S:\exniveje\DVpt...
Completed	Portfolio	AAA-EUR-SCHUMAC...	std_live_new_pbr_	No Print. Only ROI g...	Merged	S:\exniveje\DVpt...
Completed	Portfolio	AAA-EUR-WOODS	std_live_new_pbr_	No Print. Only ROI g...	Merged	S:\exniveje\DVpt...
Completed	Portfolio	400160/03	std_live_new_pbr_	No Print. Only ROI g...	Merged	S:\exniveje\DVpt...

Batch job details

You can check the **Status Filter** checkbox and select a status from the drop-down field to display a list of jobs filtered by the chosen status. In most cases, you will want to use it to retrieve the batch jobs that have failed so you can restart them. The goal is to have all the jobs in the batch with the completed green status:

☒ Status Filter	Failed	Redo Selected Failed Jobs		Redo All Failed Jobs		
Status	Object Type	Code	Report Name	Generation Mode	Calculation Mode	AAA Message
Failed	List	ALL	std_live_new_pbr_	No Print. Only ROI g...	Burst	S:\exniveje\DVpt...

Batch job details with status filter set to 'failed'

Before you restart a failed job, you can change the Actuate request status and analyse why the job failed by double-clicking in the data table. The following dialogue box is displayed, showing the settings of the processed job:

Job Detail

Job Detail

Actuate Request Details

Status

Completed

Recurring

☒

Publish to WUI

☒

Shared in WUI

☐

Priority

0

Job Type

Portfolio

Code

T_AI_AC_PTF1

Report Name

RLS Standard Valuation Report

Calculation Mode

Detailed

Generation Mode

No Print. Only ROI generated

Frequency

Daily

Start Time

2007/09/04 00:00:00

Stop Time

2007/09/04 10:39:47


From Date

Till Date

Ok

Job Detail dialogue box with Job Detail tab

The second tab, **Actuate Request Details**, displays the Actuate Return details:



Job Detail dialogue box with Actuate Request Details tab

Within the Actuate Request Details tab, there are also two sub-tabs:\$

- **Completed Request** tab displays the values of all requests sent to Actuate and the status of the requests.
- **Return** tab displays return details.

The request navigation bar lets you browse the requests:




Request navigation bar

You can use the Status Filter checkbox to return only the failed requests:



Status Filter checkbox

Double-click in the data table area to change the calculated values:



The dialog box is titled "Update Job Parameterter" with a close button (X) in the top right corner. It contains the following fields and options:

- PropertyName : currency
- Default Property Value : EUR
- Description :
- Mandatory : ☐
- User definable : ☐
- Use with Job Generation : ☐

At the bottom, there are two buttons: "Ok" (with a checkmark icon) and "Cancel" (with an X icon).


Update job parameter dialogue

Note: A **Cancelled job cannot be re-run**. A new batch is required to start the reports from Triple'A Plus Core.

4 Using Report Launcher–Processed Job List

The Processed Job List is a sub-module of the Report Launcher module. The main objective of this sub-module is to keep track of all processed jobs. To run the Processed Job List sub-module, click the icon .

4.1 Search criteria



The **SearchParameters** dialog box contains the following search criteria:

- ☐ Status: A dropdown menu.
- ☐ Start Date: A date field showing "May 1, 2006" with a dropdown arrow.
- ☐ Stop Date: A date field showing "Jun 13, 2007" with a dropdown arrow.
- ☐ Batch Ref.: A text field showing "0".

A **Search** button is located at the bottom right of the dialog box.

Search criteria view

The following criteria on the **Search Parameters** dialog box can be used to find your processed jobs:

Criterion	Description
Status	This field allows selection the processed job list by status.
Start Date	This field allows selecting batch started at a specific date.
Stop Date	This field allows selecting batch finished at a specific date.
Batch Ref	This field allows selection a batch number.


4.2 Search results

The Search Results tree view groups the search results by batch reference and shows the batch start date:



Search Results tree view

In the batch node, the processed jobs are classified by object type first and then by destination user. The tree leaf displays the processed job code:



Search Results tree view with opened leafs

The leaf selection displays the processed job details in the data pane on the right.

Status	Object Type	Code	Report Name	Generation Mode	Calculation Mode
Completed	Portfolio	T_AI_AC_PTF8	std_live_new_pbr_	No Print. Only ROI generated	Detailed
Completed	Portfolio	T_AI_AC_PTF8	Triple'A Private Banking Report (spreadsheet)	Print to file through defined Printer	Detailed
Completed	Portfolio	T_AI_AC_PTF6	Triple'A Private Banking Report (spreadsheet)	Print to file through defined Printer	Detailed
Completed	Portfolio	T_AI_AC_PTF8	Triple'A Private Banking Report (spreadsheet)	Print to file through defined Printer	Detailed
Completed	Portfolio	T_AI_AC_PTF8	Triple'A Private Banking Report (spreadsheet)	No Print. Only ROI generated	Detailed
Completed	Portfolio	T_AI_AC_PTF4	std_live_new_pbr_	No Print. Only ROI generated	Detailed
Completed	Portfolio	T_AI_AC_PTF8	std_live_aimr_	Print to file through defined Printer	Merged
Completed	Portfolio	T_AI_AC_PTF4	RLS Standard Valuation Report	No Print. Only ROI generated	Merged
Completed	Portfolio	T_AI_AC_PTF6	RLS Standard Valuation Report	No Print. Only ROI generated	Merged
Completed	Portfolio	T_AI_AC_PTF6	Triple'A Private Banking Report (spreadsheet)	No Print. Only ROI generated	Detailed
Completed	Portfolio	T_AI_AC_PTF1	RLS Standard Valuation Report	No Print. Only ROI generated	Merged
Failed	Portfolio	T_AI_AC_PTF3	RLS Standard Valuation Report	No Print. Only ROI generated	Merged
Canceled	Portfolio	T_AI_AC_PTF3	RLS Standard Valuation Report	No Print. Only ROI generated	Merged
Canceled	Portfolio	T_AI_AC_PTF3	RLS Standard Valuation Report	No Print. Only ROI generated	Merged
Canceled	Portfolio	T_AI_AC_PTF1	RLS Standard Valuation Report	No Print. Only ROI generated	Merged
Completed	Portfolio	T_AI_AC_PTF1	RLS Standard Valuation Report	No Print. Only ROI generated	Merged
Completed	Portfolio	T_AI_AC_PTF3	RLS Standard Valuation Report	No Print. Only ROI generated	Merged
Failed	Portfolio	T_AI_VA_PTF3	RLS Standard Valuation Report	Print to file through defined Printer	Detailed
Failed	Portfolio	T_AI_AC_PTF1	std_live_new_pbr_	Print to file through defined Printer	Merged

Processed Job details.

5 Using Report Launcher – System Data

The System Data is a sub-module of the Report Launcher module. The goal of this sub-module is to help the system administrator configure the Report Launcher system default parameters. This module is only for the administrator's use and can be accessed by clicking the System Data icon ().

The System Data sub-module has the following Report Launcher Configuration tabs:


- [Financial Servers](#)
- [System Parameters](#)
- [Job Parameters](#)
- [Database Cleanup](#)

5.1 Financial Servers tab

The Financial Servers tab lets you add or delete financial servers. The Report Launcher server creates a pool for each financial server and splits the batch between the pools.

5.2 System Parameters tab

The system parameters listed on the System Parameter tab are specific to the Report Launcher tool, the Actuate environment, and the Triple'A Plus Core environment.



System parameters

Parameter Value	Description
ActuateCommandParallelProcessLimit=2	Value representing how many actuate commands can run in parallel.
aaaPdfEncryption=false	Enables/disables encryption for pdf files generated on "Portfolio", "List" or "Third party" contexts.
aaaPdfEncryptionScriptPath=/CONFIG/aaa_pdf_encryption.bsh	Path of the beanshell script with encryption algorithm. This file is on the Actuate server.
csvDelimiter=,	Set up the delimiter of the index file
day_from_daily=today	From date calculation method for daily reports for from and till dates. (today, yesterday)
Default_output_filepath	Default repository for output files
Default_output_type=PDF	Default output type (PDF, PS, etc.)
Default_printer_device=IT_broad_street	Default printer name
FdxEngineEnabled	Determines if the FDX module is enabled or not. Note: The usage of FDX is normally not recommended and is only used in some specific cases. Contact Temenos for more information on this feature.
FdxFinServerMaxFailed	Integer representing the maximum number of consecutive failed requests accepted for a financial server. When this limit is reach, the related financial server is removed from the list of financial servers used.
FdxProcessesByFinServer	Integer representing the maximum number of parallel processes by a financial server.
methode_from_date=end_month	From date calculation method for non-daily reports: end_month or begin_month
PortfolioList_SublistProcessingSize=10	Value that determines the size of the chunks when splitting portfolio lists for processing.
ShowAAARSCCommandStats	For internal use only. Enabling this will show a lot of logs and slow down the processing time.
ShowCommandGenerationStats	For internal use only. Enabling this will show a lot of logs and slow down the processing time.

5.3 Job Parameters tab

5.3.1 Portfolio and List Job types

The job parameters are the default values for each Actuate request. **The client is responsible for the values.**

To modify the values of the data table, double-click it in the table. This operation is only accessible if you have **System data access**:

Financial Servers	System Parameters	Job Parameters	Database CleanUp			
Property Name	Value	Description	Mandatory	User definable	Use in Generate...	
aaamsg	/advantage/REF_TEST_4...		☐	☐	☐	
calc_freq_d	01/06/2006		☐	☐	☐	
calc_from_d	01/06/2006		☐	☐	☐	
calc_ref_d	01/06/2006		☐	☐	☐	
calc_strat_d	01/06/2006		☐	☐	☐	

Job parameters tab

- The **Mandatory** column is used in the Report Launcher client to validate the presence of data manually.
- The **User definable** column is used in the Report Launcher Client to allow end users to modify the value for a new job. When the user definable checkbox is selected, the Description is mandatory.
- The **Use in Generate Jobs** column is used to define which parameters will be used in the Generate Jobs Panel. Parameters with this option checked will be available on this panel and can be modified. They will then be passed into generate jobs beanshell script.

5.4 Database Cleanup tab

You can use the Database CleanUp tab to clean the Report Launcher database. The different cleanup modes are:

Mode	Description
Until this batch date	Removes all the batches up to and including the stop batch date.
Until this batch ID	Removes all the batches up to and including the batch ID entered.
One batch ID	Removes a single batch. Enter the ID of the batch that you want to remove.

6 Using the Report Launcher-SOAP API

The main features of the Report Launcher can be accessed from any external tool or application by its Simple Object Access Protocol (SOAP) Application Programming Interface (API) or by using the provided Java API client.

6.1 SOAP API Client

The HTTP API can also be accessed using the `ReportLauncherAPIClient.jar`. This jar can be executed in command line or from a script to call these Report Launcher features.

To see the list of available commands enter the following on a command line:

```
java -jar ReportLauncherAPIClient.jar -?
```

This will print the following information:

```
Usage:
    java -U <user> -P <password> -H http://<hostname>:<HTTP port> -C <command>
    java -U <user> -P <password> -H http://<hostname>:< HTTP port> -F <command_file>
    <command> is one of the following:
        StartAllJobs 'priority'
        GenerateJobs <frequency>,<generation_mode>
        StopBatch
        PauseBatch
        ContinueBatch
        GetBatchStatistics <BatchId>
        GetRunningBatchId
        PurgeBatchesUntilDate <date>
        PurgeBatches
            <BatchId1,BatchId2,...BatchIdn>
        StartJob
            AddJob
            <ObjectCode>,<ReportName>,<CalcMode>,<TripleAObjectType>,<GenerationMode>,<frequency>
            ,<StartDate>,
            <FromDate>,<TillDate>,<Recurring>,<Priority>,<PublishToWUI>,<SharedInWUI>, <Optional
            User-defined fields delimited by ##>
            updatejob
            <jobid>,<objectcode>,<reportname>,<calcmode>,<tripleaobj
            ecttype>,<generationmode>,<frequency>,<startdate in dd/mm/yyyy format>,<fromdate in
            dd/mm/yyyy format>,<tilldate in dd/mm/yyyy
            format>,<recurring>,<priority>,<publishtowui>,<sharedinwui>,<optional user-defined
            fields delimited by ##>
            deletejob <jobid>
            deletejobs <jobid1,jobid2,...jobidn>
            getfinancialservers
            addfinancialserver    <serverid>,<servername>
            updatefinancialserver <serverid>,<servername>
            deletefinancialserver <serverid>
```

```

getsystemparameters
addsystemparameter    <name>,<value>
updatesystemparameter <name>,<value>
deletesystemparameter <name>

getjobparameters
addjobparameter       <name>,<value>
updatejobparameter    <name>,<value>
deletejobparameter    <name>

findjoblist<startdate>,<code>,<jobtype>,<reportname>
startjobsfromids <jobid>

```

<command_file> is the complete path of a file containing a list of valid Commands (one <command> by line)

This client jar can be called either using a single command or a command file containing a list of commands. This is shown below.

```
java -jar ReportLauncherAPIClient.jar -U <user> -P <password> -H
http://<hostname>:< HTTP port> -C <command>
```

or

```
java -jar ReportLauncherAPIClient.jar -U <user> -P <password> -H
http://<hostname>:< HTTP port> -F <command_file>
```

<command> is one of the following:

- startalljobs
- generatejobs <frequency>,<generation_mode>
- stopbatch
- pausebatch
- continuebatch
- getbatchstatistics <BatchID>
- getrunningbatchid
- purgebatchesuntildate <date>
- purgebatches <BatchId1,BatchId2,...BatchIdn>
- startjobs
 <tripleaobjectcode>,<reportname>,<calcmode>,<tripleaobjecttype>,<generationmode>,<frequency>
- addjob
 <ObjectCode>,<ReportName>,<CalcMode>,<TripleAObjectType>,<GenerationMode>,<frequency>,<StartDate>,<FromDate>,<TillDate>,<Recurring>,<Priority>,<PublishToWUI>,<SharedInWUI>,<Optional User-defined fields delimited by ##>
- updatejob
 <JobId>,<objectcode>,<ReportName>,<calcmode>,<tripleaobjecttype>,<generationmode>,<frequency>,<startdate in dd/mm/yyyy format>,<fromdate in dd/mm/yyyy format>,<tilldate in dd/mm/yyyy format>

format>,<recurring>,<priority>,<publishtowui>,<sharedinwui>,<optional user-defined fields delimited by ##>

- deletejob <jobid>
- getfinancialservers
- addfinancialserver <serverid>,<servername>
- updatefinancialserver <serverid>,<servername>
- deletefinancialserver <serverid>
- getsystemparameters
- addsystemparameter <name>,<value>
- updatesystemparameter <name>,<value>
- deletesystemparameter <name>
- getjobparameters
- addjobparameter <name>,<value>
- updatejobparameter <name>,<value>
- deletejobparameter <name>
- findjoblist <startdate>,<code>,<jobtype>,<reportname>
- startjobsfromids <jobid>

<command_file> is the complete path of a file containing a list of valid Commands (one <command> by line). When an invalid command line is specified, the return code is -1.

Examples:

- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **StartAllJobs**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **StopBatch**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **PauseBatch**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **ContinueBatch**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **GetRunningBatchId**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **PurgeBatches 7,8,9**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **PurgeBatchesUntilDate 15/09/2004**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **GenerateJobs D,1**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **StartJobs 60699905861477N,"leu_live_new_pbr",1,1,1,D**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **GetBatchStatistics 1**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **addjob
T_AI_Client2,std_live_new_pbr_,1,1,1,D,06/11/2007,06/11/2007,06/11/2007,07,1,0,1,1, currency=USD##debt_f=1**

- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **deletjobs 250,251,500,300,150**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **getfinancialservers**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **addfinancialservers 200,FinServer1**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **updatefinancialservers 200,FinServer2**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **deletefinancialservers 200**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **getsystemparameters PdfFolder**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **addsystemparameter DocFolder,c:\DocFld**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **updatesystemparameter DocFolder,d:\DocFld**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **deletesystemparameter DocFolder**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **getjobparameters**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **addjobparameter jobtype,5**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **updatejobparameter jobtype,3**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **deletejobparameter jobtype**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **findjoblist 03/08/2008,T_AI_AC_PTF1,2,"std_live"**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -C **startjobsfromids 4a9d37d90a28644054b352a600000080, a615f82b0a28646301d6e3d2000002a8, a82238e30a190353002cd7280000000b**
- java -jar ReportLauncherAPIClient.jar -U bfo -P bfo -H http://localhost:8080 -F **C:\\MyDocs\\Commands.txt**

Commands.txt contains for example:

```
StartJobs 60699905861477N,leu_live_new_pbr,1,1,1,D
PauseBatch
ContinueBatch
StopBatch
PurgeBatchesUntilDate 16/09/2004
```

6.2 API Methods

The features that are accessible with this API are:

Feature	Method	Returns
Start all the jobs defined in the Report Launcher	<code>startAllJobs(String userId, String password, int priority)</code>	Batch ID.
Generate all the jobs in the Report Launcher from Triple'A Plus	<code>generateJobs(String userId, String password, String frequency, int generationMode)</code>	Status information of the operation. (1 if operation failed, 0 if succeeded.)
Stop the current batch in the Report Launcher	<code>stopBatch(String userId, String password)</code>	Status information of the operation. (1 if operation failed, 0 if succeeded.)
Pause the current batch in the Report Launcher	<code>pauseBatch(String userId, String password)</code>	Status information of the operation. (1 if operation failed, 0 if succeeded.)
Continue the batch which has been paused in the Report Launcher	<code>continueBatch(String userId, String password)</code>	Status information of the operation. (1 if operation failed, 0 if succeeded.)
Get statistics of the batch specified by the batch ID	<code>getBatchStatistics(String userId, String password, int batchID)</code>	Statistics. (table of strings)
Get running Batch ID from the Report Launcher	<code>getRunningBatchId(String userId, String password)</code>	Batch ID.
Purge all batches older than a specified date	<code>purgeBatchesUntilDate(String userId, String password, String date)</code>	Status information of the operation. (1 if operation failed, 0 if succeeded.) The date must be in <i>dd/mm/yy</i> format.
Purge from the Report Launcher the batch specified by the Batch ID	<code>purgeBatch(String userId, String password, String batchID)</code>	Status information of the operation. (1 if operation failed, 0 if succeeded.)
Purge all the batches (from a table of IDs)	<code>purgeBatches(String userId, String password, String[] batchIds)</code>	Status information of the operation. (1 if operation failed, 0 if succeeded.)

Feature	Method	Returns																
Start a job already present in the Report Launcher	startJob(String userId, String password, String tripleaObjectCode, String reportName, String calcMode, String tripleAObjectType, String generationMode, String frequency)	Batch ID.																
		<table><tr><th>Parameter</th><th>Description</th></tr><tr><td>tripleaObjectCode</td><td>The portfolio / list / third party define in the job.</td></tr><tr><td>reportName</td><td>Important The reportName must be enclosed in "" if it has a space in the name or else the API client will not be able to parse the arguments correctly.</td></tr><tr><td>calcMode</td><td>Must be one of the following values: 1: Merged 2: Detailed 3: Tiled 4: Burst</td></tr><tr><td>tripleAObjectType</td><td>Must be one of the following values: 1: List 2: Portfolio 4: Third Party</td></tr><tr><td>generationMode</td><td>Must be one of the following values: 1: No Print. Only ROI generated 2: Print to defined printer 3: Print to file 4: Print & Archive</td></tr><tr><td>frequency</td><td>Must be one of the following values: D: Daily M: Monthly X: Semesterly Y: Yearly</td></tr><tr><td></td><td></td></tr></table>	Parameter	Description	tripleaObjectCode	The portfolio / list / third party define in the job.	reportName	Important The reportName must be enclosed in "" if it has a space in the name or else the API client will not be able to parse the arguments correctly.	calcMode	Must be one of the following values: 1: Merged 2: Detailed 3: Tiled 4: Burst	tripleAObjectType	Must be one of the following values: 1: List 2: Portfolio 4: Third Party	generationMode	Must be one of the following values: 1: No Print. Only ROI generated 2: Print to defined printer 3: Print to file 4: Print & Archive	frequency	Must be one of the following values: D: Daily M: Monthly X: Semesterly Y: Yearly		
		Parameter	Description															
		tripleaObjectCode	The portfolio / list / third party define in the job.															
		reportName	Important The reportName must be enclosed in "" if it has a space in the name or else the API client will not be able to parse the arguments correctly.															
		calcMode	Must be one of the following values: 1: Merged 2: Detailed 3: Tiled 4: Burst															
		tripleAObjectType	Must be one of the following values: 1: List 2: Portfolio 4: Third Party															
		generationMode	Must be one of the following values: 1: No Print. Only ROI generated 2: Print to defined printer 3: Print to file 4: Print & Archive															
		frequency	Must be one of the following values: D: Daily M: Monthly X: Semesterly Y: Yearly															

Feature	Method	Returns																
Add a job	addJob(String userId, String password, String tripleaObjectCode, String reportName, String calcMode, String tripleAObjectType, String generationMode, String frequency, Date startdate, Date fromdate, Date tilldate, recurring, priority, publishToWui, sharedinwui, Optional User-defined fields)	Status.																
		Is a functionality that is already present in the Report Launcher. It allows you to add a new job.																
		<table><tr><th>Parameter</th><th>Description</th></tr><tr><td>tripleaObjectCode</td><td>The portfolio / list / third party define in the job.</td></tr><tr><td>reportName</td><td>Important The reportName must be enclosed in "" if it has a space in the name or else the API client will not be able to parse the arguments correctly.</td></tr><tr><td>calcMode</td><td>Must be one of the following values: 1: Merged 2: Detailed 3: Tiled 4: Burst</td></tr><tr><td>tripleAObjectType</td><td>Must be one of the following values: 1: List 2: Portfolio 4: Third Party</td></tr><tr><td>generationMode</td><td>Must be one of the following values: 1: No Print. Only ROI generated 2: Print to defined printer 3: Print to file 4: Print & Archive</td></tr><tr><td>frequency</td><td>Must be one of the following values: D: Daily M: Monthly X: Semester Y: Yearly</td></tr><tr><td>startDate</td><td>Must be a valid date in this format: dd/mm/yyyy Default: Null (Default today's date)</td></tr></table>	Parameter	Description	tripleaObjectCode	The portfolio / list / third party define in the job.	reportName	Important The reportName must be enclosed in "" if it has a space in the name or else the API client will not be able to parse the arguments correctly.	calcMode	Must be one of the following values: 1: Merged 2: Detailed 3: Tiled 4: Burst	tripleAObjectType	Must be one of the following values: 1: List 2: Portfolio 4: Third Party	generationMode	Must be one of the following values: 1: No Print. Only ROI generated 2: Print to defined printer 3: Print to file 4: Print & Archive	frequency	Must be one of the following values: D: Daily M: Monthly X: Semester Y: Yearly	startDate	Must be a valid date in this format: dd/mm/yyyy Default: Null (Default today's date)
		Parameter	Description															
		tripleaObjectCode	The portfolio / list / third party define in the job.															
		reportName	Important The reportName must be enclosed in "" if it has a space in the name or else the API client will not be able to parse the arguments correctly.															
		calcMode	Must be one of the following values: 1: Merged 2: Detailed 3: Tiled 4: Burst															
		tripleAObjectType	Must be one of the following values: 1: List 2: Portfolio 4: Third Party															
		generationMode	Must be one of the following values: 1: No Print. Only ROI generated 2: Print to defined printer 3: Print to file 4: Print & Archive															
frequency	Must be one of the following values: D: Daily M: Monthly X: Semester Y: Yearly																	
startDate	Must be a valid date in this format: dd/mm/yyyy Default: Null (Default today's date)																	

Feature	Method	Returns	
		fromDate	Must be a valid date in this format: dd/mm/yyyy Default: Null (Default today's date)
		tillDate	Must be a valid date in this format: dd/mm/yyyy Default: Null (Default today's date)
		recurring	Permitted values: 0: non recurring 1: recurring
		priority	Must be any number greater than 1.
		publishToWui	Permitted values: 0: do not publish to WUI 1: publish to WUI
		shareInWui	Permitted values: 0: do not share in WUI 1: share in WUI
		Optional User-Defined Fields	Permitted value in Triple'A Plus reports: Service Id: User defined data parameter = Value The service id can be found in the Report XML while the user defined parameters can be found in the MML definition file. Example: <code>java -jar ReportLauncherAPIClient.jar -U T_AI_Manager2 -P aaaaaa2005 -H http://luxwindev2:45200 -C AddJob T_AI_ICSPE_PTF_LIST, "RLS Standard Valuation Report",1,5,1,D,12/11/2007,12/11/2007,12/11/2007,1,0,1,1,2:minStatus=1</code> Permitted value in Triple'A Plus reports: Default Job parameter = Value Example: <code>java -jar ReportLauncherAPIClient.jar -U T_AI_Manager2 -P aaaaaa2005 -H</code>

Feature	Method	Returns						
		http://luxwindev2: 45200 -C AddJob T_AI_Client2,std_live_notes_, 1,4,1,D,12/11/2007,12/11/2007,12/11/2007, 1,0,1,1,currency=USD##debt_f=1 Only default parameters marked as user definable can be overridden.						
Update a job	updateJob(sUserName, sPassword, sJobId , sObjectCode, sReportName, sCalcMode, sObjectType, sGenerationMode, sFrequency, sStartDate, sFromDate, sTillDate, recurring, priority, publishtoWUI, sharedinWUI, userDefinedValues)	Status. It allows you to update an existing job. <table><tr><th>Parameter</th><th>Description</th></tr><tr><td>sJobId</td><td>The job ID. Must be a valid job ID.</td></tr></table> For the other parameters, see Add a Job.	Parameter	Description	sJobId	The job ID. Must be a valid job ID.		
Parameter	Description							
sJobId	The job ID. Must be a valid job ID.							
Delete job	deleteJob(sUserName, sPassword, sJobIds)	Status. It allows you to delete an existing job. <table><tr><th>Parameter</th><th>Description</th></tr><tr><td>JobId</td><td>The job ID. Must be a valid job ID. Mandatory.</td></tr></table>	Parameter	Description	JobId	The job ID. Must be a valid job ID. Mandatory.		
Parameter	Description							
JobId	The job ID. Must be a valid job ID. Mandatory.							
Delete jobs	deleteJobs(sUserName, sPassword, sJobIds)	Status. It allows you to update existing job(s) from a comma separated job id list. <table><tr><th>Parameter</th><th>Description</th></tr><tr><td>JobId</td><td>The job ID. Must be a valid job ID list. Mandatory.</td></tr></table>	Parameter	Description	JobId	The job ID. Must be a valid job ID list. Mandatory.		
Parameter	Description							
JobId	The job ID. Must be a valid job ID list. Mandatory.							
Get Financial Servers	getFinancialServers(sUserN ame, sPassword)	Table of strings. Lists financial servers ID and Name.						
Add Financial Server	addFinancialServer(sUserNa me, sPassword, serverId, sServerName)	Status information of the operation. (1 if operation failed, 0 if succeeded.) Creates new financial server in the Report Launcher <table><tr><th>Parameter</th><th>Description</th></tr><tr><td>serverId</td><td>The server ID (a numeric value).</td></tr><tr><td>sServerName</td><td>The new server name.</td></tr></table>	Parameter	Description	serverId	The server ID (a numeric value).	sServerName	The new server name.
Parameter	Description							
serverId	The server ID (a numeric value).							
sServerName	The new server name.							

Feature	Method	Returns						
Update Financial Server	updateFinancialServer(sUserName, sPassword, serverId, sServerName)	Status information of the operation. (1 if operation failed, 0 if succeeded.) Updates new financial server in the Report Launcher <table><tr><th>Parameter</th><th>Description</th></tr><tr><td>serverId</td><td>The server ID (a numeric value).</td></tr><tr><td>sServerName</td><td>The server name.</td></tr></table>	Parameter	Description	serverId	The server ID (a numeric value).	sServerName	The server name.
Parameter	Description							
serverId	The server ID (a numeric value).							
sServerName	The server name.							
Delete Financial Server	deleteFinancialServer(sUserName, sPassword, serverId)	Status information of the operation. (1 if operation failed, 0 if succeeded.) Deletes an existing financial server in the Report Launcher <table><tr><th>Parameter</th><th>Description</th></tr><tr><td>serverId</td><td>The server ID (a numeric value).</td></tr></table>	Parameter	Description	serverId	The server ID (a numeric value).		
Parameter	Description							
serverId	The server ID (a numeric value).							
Get System Parameters	getSytemParameters(sUserName, sPassword)	Table of strings. Lists parameter names and values.						
Add System Parameter	addSystemParameter(sUserName, sPassword, sPropertyName, sValue)	Status information of the operation. (1 if operation failed, 0 if succeeded.) Creates a new system parameter in the Report Launcher. <table><tr><th>Parameter</th><th>Description</th></tr><tr><td>SPropertyName</td><td>The new system parameter name.</td></tr><tr><td>sValue</td><td>The parameter value.</td></tr></table>	Parameter	Description	SPropertyName	The new system parameter name.	sValue	The parameter value.
Parameter	Description							
SPropertyName	The new system parameter name.							
sValue	The parameter value.							
Update System Parameter	updateSystemParameter(sUserName, sPassword, sPropertyName, sValue)	Status information of the operation. (1 if operation failed, 0 if succeeded.) Updates an existing system parameter in the Report Launcher. <table><tr><th>Parameter</th><th>Description</th></tr><tr><td>SPropertyName</td><td>The existing system parameter name.</td></tr><tr><td>sValue</td><td>The new parameter value.</td></tr></table>	Parameter	Description	SPropertyName	The existing system parameter name.	sValue	The new parameter value.
Parameter	Description							
SPropertyName	The existing system parameter name.							
sValue	The new parameter value.							
Delete System Parameter	deleteSystemParameter(sUserName, sPassword, sPropertyName)	Status information of the operation. (1 if operation failed, 0 if succeeded.) Deletes an existing system parameter in the Report Launcher. <table><tr><th>Parameter</th><th>Description</th></tr><tr><td>SPropertyName</td><td>The existing system parameter name.</td></tr></table>	Parameter	Description	SPropertyName	The existing system parameter name.		
Parameter	Description							
SPropertyName	The existing system parameter name.							

Feature	Method	Returns						
Get Job Parameters	getjobparameters (sUserName, sPassword)	Table of strings. Lists parameter names and values.						
Add Job Parameter	addJobParameters(UserName, sPassword, sPropertyName, sValue)	Status information of the operation. (1 if operation failed, 0 if succeeded.) Creates a new job parameter in the Report Launcher.						
		<table><tr><th>Parameter</th><th>Description</th></tr><tr><td>SPropertyName</td><td>The new job parameter name.</td></tr><tr><td>sValue</td><td>The parameter value.</td></tr></table>	Parameter	Description	SPropertyName	The new job parameter name.	sValue	The parameter value.
		Parameter	Description					
		SPropertyName	The new job parameter name.					
sValue	The parameter value.							
Update Job Parameter	updateJobParameter(sUserName, sPassword, sPropertyName, sValue)	Status information of the operation. (1 if operation failed, 0 if succeeded.) Updates an existing job parameter in the Report Launcher.						
		<table><tr><th>Parameter</th><th>Description</th></tr><tr><td>SPropertyName</td><td>The existing job parameter name.</td></tr><tr><td>sValue</td><td>The new parameter value.</td></tr></table>	Parameter	Description	SPropertyName	The existing job parameter name.	sValue	The new parameter value.
		Parameter	Description					
		SPropertyName	The existing job parameter name.					
sValue	The new parameter value.							
Delete Job Parameter	deleteJobParameter(sUserName, sPassword, sPropertyName)	Status information of the operation. (1 if operation failed, 0 if succeeded.) Deletes an existing job parameter in the Report Launcher.						
		<table><tr><th>Parameter</th><th>Description</th></tr><tr><td>SPropertyName</td><td>The existing job parameter name.</td></tr></table>	Parameter	Description	SPropertyName	The existing job parameter name.		
		Parameter	Description					
SPropertyName	The existing job parameter name.							
Find Job List	findJobList(sUserName, sPassword, sStartDate, sCode, sJobType, sReportName)	Table of strings. Gets job list. If no parameters are defined, get all the existing jobs.						
		<table><tr><th>Parameter</th><th>Description</th></tr><tr><td>sStartDate</td><td>Must be a valid date in this format: dd/mm/yyyy Optional</td></tr><tr><td>sCode</td><td>Must be an existing code Valid code example: T_AI_AC_PTF1 Optional</td></tr></table>	Parameter	Description	sStartDate	Must be a valid date in this format: dd/mm/yyyy Optional	sCode	Must be an existing code Valid code example: T_AI_AC_PTF1 Optional
		Parameter	Description					
		sStartDate	Must be a valid date in this format: dd/mm/yyyy Optional					
sCode	Must be an existing code Valid code example: T_AI_AC_PTF1 Optional							

Feature	Method	Returns	
		sJobType	Must be an existing job type Valid type example: List Optional
		sReportName	Must be an existing report. Valid report name example: std_live_new_pbr Optional
Start Jobs From Ids	startJobsFromIds(sUserName, sPassword, JobId)	Status information of the operation. (1 if operation failed, 0 if succeeded.) Starts job(s) from a comma separated job ID list.	
		Parameter	Description
		JobId	A comma separated job ID list of valid job IDs. Mandatory