# Azure VM Failover

- Overview
- Problem
- Process
- Solution
- Related articles

# Overview

Platform:	Azure
Owner of this SOP:	Fully Managed POD A
Cloud Services:	Azure VM DR ASR

# Problem

When requesters are asking to failover VM from primary to secondary region

tester	Reviewer
@ Senthilkumaran Gurusamypandian	


### **Process**


# **Raise a Normal Change Request**

Please open a Normal change request and get it approved before executing the VM region failover activity, And respective stake holders and application owners should be informed prior to this activity as downtime is required.

# Solution

• Try RDP login to the Azure VM, Check the Drives and files





• Login to Azure portal. Select the VM


Home > Virtual machines >

Change tracking


- · Go to VM and click on Disaster Recovery
- https://bhptechsi.atlassian.net/wiki/spaces/CLOUD/pages/2470707680/VM+Disaster+Recovery+-+Region+Failover+-+ASR

MAUE10ETPOD009 Virtual machine Ø Connect ∨ ▷ Start C Restart ☐ Stop Ø Capture 📋 Delete 💍 Refresh 👢 Open in Search (Ctrl+/) Configuration f) Advisor (1 of 4): Log Analytics agent should be installed on virtual machines → % Identity ↑ Essentials Properties Resource group (move) Operating system Australia-East-rg3-primary Windows (Windows Serve Locks Status Operations Running Standard DS1 v2 (1 vcpu, 1 Public IP address S Bastion Australia East Auto-shutdown Subscription (move) Virtual network/subnet it-npe-toolingdev it-aue1-npe-vnt-10.125.12 Backup Subscription ID DNS name Disaster recovery 01818878-c294-4617-a15a-8b7934a433c4 Guest + host updates Tags (edit) ✓ More (11) BusinessUnit: Fully Managed PODA Inventory


• In that Check the OS disk and Data disk in protected status




 If Data disk is not showing - Go to Recovery services Vault Select the particular Vault name Recovery Services vaults



• In that go to replicated items and select the disk and enable replication



- Do test failover ( Select the VM and click on Disaster Recovery)
- Validate the test failover settings compute, Network and Disks



### Home > MAUE10ETPOD009 > MAUE10ETPOD009 >

# Test failover MAUE10ETPOD009 Failover direction From ①


To ①

Australia Southeast

## **Recovery Point**

Australia East


Recovery Point ① Latest processed (low RTO) Thu Feb 17 2022 12:44:05 GMT+0530 (India Standard Time) Choose a recovery point




1 It is recommended that for a test failover you use a network different from production network (as specified under Compute and Network settings of the virtual machine). Learn more.

OK


• Once the Test Failover process complete, you can see the test VM will get deployed.




- Try RDP login, Check the Drives and files as expected
- In Secondary region, we could see the the data and files replicated
- · Once the test failover is validated, click on clean up test failover





· For failover, click on Failover and verify the primary and secondary region settings and recovery piont and vnet




After failover, Secondary region vm will be running and primary vm will be in shutdown state.









• Try RDP login, Check the Drives and files as expected






- When satisfied with the failed over VM, select Commit on the overview page, to finish the failover.
- Commit deletes all the available recovery points for the VM in Site Recovery, and you won't be able to change the recovery point.



- now click on re-protect the VM in the secondary region, so that it replicates back to the primary region.
- On the VM Overview page, select Re-Protect.
- In Re-protect, verify the replication direction (secondary to primary region), and review the target settings for the primary region. Resources marked as new are created by Site Recovery as part of the re-protect operation.
- Select OK to start the re-protect process. The process sends initial data to the target location, and then replicates delta information for the VMs to the target.



Resource group, Network, Storage and Availability 
Customize By default, Site Recovery will pick the original source resource group, virtual network, storage accounts and availability sets as below. Click 'Customize' above to change the configuration. The re appended with "asr" suffix. Target resource group ① Target virtual network ① Australia-East-rg3-primary it-aue1-npe-vnt-10.125.121.0 Cache storage accounts ① Replica managed disks ① (new) 0 premium disks(s), 2 standard disk(s) i7nqyhitaue2npasrcache Target availability sets ① Not Applicable Target proximity placement group ① Not Applicable Columns Tilter Last refreshed at: 3/24/2022, 11:43:10 AM Finished loading data from service.

Status

Protected

Active location

Australia Southeast

Replication errors




MAUE10ETPOD009-r... ♥ Healthy

Replication Health

Name

 After VM DR site recovery we have to lock the Terraform workspace to avoid the changes to the resources. (Since resources are moved to secondary region otherwise terraform try to provision the resources)





### To Failback From Secondary to Primary region

- 1. As like failover steps we need to follow the same steps for failback
- 2. Do the Failover, Commit and Re-Protect
- 3. After failback we can unlock the workspace and make changes to TF code if any changes required.

# Related articles

- AWS VPC Endpoints configuration change
- Renewal / Upload SSL certificate for existing Application
- Monitoring GitLab Access Audit Report
- Azure Storage Account Blueprint SOP BPAZR022
- Azure App Service FTP Credential Sharing and Reset Procedure