
## Lektion 4

## Lydens opførsel i lukkede rum



1. Beregn de første 10 rum-resonanser i lyttestuen. Angiv hvilke der er aksiale. Beregn også Schröder-frekvensen og estimer efterklangstiden T60.

$$f_r = \frac{nc}{2L}$$
Frequency =  $\frac{c}{2}\sqrt{\frac{p^2}{L^2} + \frac{q^2}{W^2} + \frac{r^2}{H^2}}$ 

$$T_{60} = 0.16\frac{V}{S}$$

$$f_S \approx 2000\sqrt{\frac{T_{60}}{V}}$$

f1 = 34.4000

$$f2 = (c/2) * (sqrt(((0^2)/Lx^2) + ((1^2)/Ly^2) + ((0^2)/Lz^2)))$$

f2 = 43

$$f3 = (c/2) * (sqrt(((1^2)/Lx^2) + ((1^2)/Ly^2) + ((0^2)/Lz^2)))$$

f3 = 55.0669

$$f4 = (c/2) * (sqrt(((0^2)/Lx^2) + ((0^2)/Ly^2) + ((1^2)/Lz^2)))$$

f4 = 68.8000

$$f5 = (c/2) * (sqrt(((1^2)/Lx^2) + ((0^2)/Ly^2) + ((1^2)/Lz^2)))$$


f5 = 76.9207

$$f6 = (c/2) * (sqrt(((0^2)/Lx^2) + ((1^2)/Ly^2) + ((1^2)/Lz^2)))$$

```
f6 = 81.1322
f7 = (c/2) * (sqrt(((2^2)/Lx^2) + ((0^2)/Ly^2) + ((0^2)/Lz^2)))
f7 = 68.8000
f8 = (c/2) * (sqrt(((1^2)/Lx^2) + ((1^2)/Ly^2) + ((1^2)/Lz^2)))
f8 = 88.1238
f9 = (c/2) * (sqrt(((0^2)/Lx^2) + ((2^2)/Ly^2) + ((0^2)/Lz^2)))
f9 = 86
f10= (c/2) * (sqrt(((2^2)/Lx^2) + ((1^2)/Ly^2) + ((0^2)/Lz^2)))
f10 = 81.1322
% Indeks
fLx = zeros(1,2);
fLy = zeros(1,2);
fLz = zeros(1,2);
% Aksiale resonanser
for n = 1:2
   fLx(n) = (n*c)/(2*Lx);
   fLy(n) = (n*c)/(2*Ly);
   fLz(n) = (n*c)/(2*Lz);
end
fLx
fLx =
   34.4000
            68.8000
fLy
fLy =
    43
         86
fLz
fLz =
   68.8000 137.6000
V = Lx*Ly*Lz;
                             % Rummets volume (m3)
S = (Ly*Lz);
                             % Lydabsorberende areal S (alpha for gardin)
T60 = 55.3*(V/(S*c))
                             % Efterklangstiden (s)
T60 = 0.8038
fs = 2000*sqrt(T60/V)
                             % Schröder frekvensen
fs = 253.5790
```

- 2. Giv et bud på delay og relativ styrke for alle 1. ordens reflektioner (for faste kilde/lytter placeringer). Tegn impulsresponsen som søjler langs en tidsakse, hvor lyddæmpningen medtages efter afstandsreglen og eventuelt en vurdering af dæmpningen ved refleksion i fx loftplader.
- 3. Beregning af efterklangstiden T60 efter Sabine for forskellige rum. Vurdering af absorption ved brug af kurverne i "Elektroakustik" (50 51) eller "Report 2 Absorber" fra Campus, eller formler fundet på nettet.

$$T_{60} = \ln(10^6) \frac{4V}{Sc}$$
  $T_{60} = 55,3 \frac{V}{Sc}$   $T_{60} = 0,16 \frac{V}{S}$   $S = \alpha_1 S_1 + \alpha_2 S_2 + ...$ 



T60 for skum, rockwool 25mm, gardin

```
T60 = 0.8000 0.9639 2.2857
```

- 4. Bestem de rumakustiske parametre T60, EDT, og C80 ud fra impulsresponsen i filen roomir.mat.
  - Reverberation Time: RT: RT60 or T60: the time it takes for the sound pressure level to fall by 60 dB after the sound has been turned off.
  - Early Decay Time: EDT is derived from the Reverberation Time decay curve the section between 0 dB and 10 dB below the initial level.

```
load roomir.mat
N = length(room);
f_axis = ((1:N)*48000/N);

plot(f_axis, room)
title('RIR - Room Impulse Response')
xlabel('Samples'), ylabel('Level (dB)')
```

