

[GETNET] ADICIONAR MOUNTPOINT VM LINUX

Em alguns deploys de VMs, são necessários pontos de montagem específicos para instalação de alguma solução que foge os padrões da GETNET. Para bancos de dados Oracle, por exemplo, é criado o /u01 e /u02 e por vezes o /ggs, para bancos MongoDB, é criado o /data.

No caso abaixo, foi solicitado um host para instalar o SAP onde era necessário os seguintes pontos de montagem:

```
/install = 200Gb
/sapmnt/PPO = 30Gb
/usr/sap = 30Gb
```

Neste caso, para atender os 3 pontos de montagem, fizemos 2 abordagens diferentes.

1- Fizemos o deploy do host com o /data de 200gb e, ao subir a VM, alteramos o mount point para /install conforme abaixo:

```
[root@GNCASHPL06128 ~]# cat /etc/fstab

#
# /etc/fstab
# Created by anaconda on Wed Dec 21 09:31:39 2016
#
# Accessible filesystems, by reference, are maintained under '/dev/disk'
# See man pages fstab(5), findfs(8), mount(8) and/or blkid(8) for more info
#
UUID=98988495-77c4-4285-b1ea-86cdd8b46efb / xfs defaults 0 0
UUID=c9aaa7d9-f9a9-4618-9e33-b0612ea1ac72 swap swap defaults 0 0
/dev/vg_data/lv_data /data xfs defaults 0 0

[root@GNCASHPL06128 ~]# mkdir /install
[root@GNCASHPL06128 ~]# chmod 777 /install
[root@GNCASHPL06128 ~]# umount /data
[root@GNCASHPL06128 ~]# vi /etc/fstab
*** alteramos a última linha indicando o /install no lugar do /data
/dev/vg_data/lv_data /install xfs defaults 0 0
```

```
[root@GNCASHPL06128 ~]# mount -a
[root@GNCASHPL06128 ~]# df -h
```

Filesystem	Size	Used	Avail	Use%	Mounted on
devtmpfs	16G	0	16G	0%	/dev
tmpfs	16G	4.0K	16G	1%	/dev/shm
tmpfs	16G	28M	16G	1%	/run
tmpfs	16G	0	16G	0%	/sys/fs/cgroup
/dev/sda2	21G	5.1G	16G	25%	/
tmpfs	3.2G	0	3.2G	0%	/run/user/1237252925
/dev/mapper/vg_data-lv_data	200G	33M	200G	1%	/install

2- adição dos demais pontos de montagem.

Primeiro logamos no VCenter para adicionar 2 discos:

[External Image](#)

Depois de realizada a operação no VCenter, sem necessitar de restart na VM, os discos já estão listados no fdisk:

```
[root@GNCASHPL06128 ~]# fdisk -l
Disk /dev/sda: 25.8 GB, 25769803776 bytes, 50331648 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk label type: dos
Disk identifier: 0x000d5223
```

Device	Boot	Start	End	Blocks	Id	System
/dev/sda1		2048	7813119	3905536	82	Linux swap / Solaris
/dev/sda2	*	7813120	50331647	21259264	83	Linux

```
Disk /dev/sdb: 214.7 GB, 214748364800 bytes, 419430400 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk label type: dos
Disk identifier: 0x0003ec76
```

Device	Boot	Start	End	Blocks	Id	System
/dev/sdb1		2048	419430399	209714176	83	Linux

```
Disk /dev/mapper/vg_data-lv_data: 214.7 GB, 214744170496 bytes, 419422208 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
```

```
Disk /dev/sdc: 32.2 GB, 32212254720 bytes, 62914560 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
```

```
Disk /dev/sdd: 32.2 GB, 32212254720 bytes, 62914560 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
```

Formatação dos discos:

```
[root@GNCASHPL06128 ~]# fdisk /dev/sdc
Welcome to fdisk (util-linux 2.23.2).
```

```
Changes will remain in memory only, until you decide to write them.
Be careful before using the write command.
```

```
Device does not contain a recognized partition table
Building a new DOS disklabel with disk identifier 0xe0f682cd.
```

```
Command (m for help): n
```

```
Partition type:
```

```
  p primary (0 primary, 0 extended, 4 free)
  e extended
```

```
Select (default p): p
```

```
Partition number (1-4, default 1): 1
```

```
First sector (2048-62914559, default 2048):
```

```
Using default value 2048
```

```
Last sector, +sectors or +size{K,M,G} (2048-62914559, default 62914559):
```

```
Using default value 62914559
```

```
Partition 1 of type Linux and of size 30 GiB is set
```

```
Command (m for help): w
```

```
The partition table has been altered!
```

```
Calling ioctl() to re-read partition table.
```

```
Syncing disks.
```

```
[root@GNCASHPL06128 ~]# fdisk /dev/sdd
```

```
Welcome to fdisk (util-linux 2.23.2).
```

```
Changes will remain in memory only, until you decide to write them.
Be careful before using the write command.
```

```
Device does not contain a recognized partition table
Building a new DOS disklabel with disk identifier 0x0b71477a.
```

```
Command (m for help): n
```

```
Partition type:
```

```
  p primary (0 primary, 0 extended, 4 free)
  e extended
```

```
Select (default p): p
```

```
Partition number (1-4, default 1): 1
```

```
First sector (2048-62914559, default 2048):
```

```
Using default value 2048
```

```
Last sector, +sectors or +size{K,M,G} (2048-62914559, default 62914559):
```

```
Using default value 62914559
```

```
Partition 1 of type Linux and of size 30 GiB is set
```

```
Command (m for help): w
```

```
The partition table has been altered!
```

```
Calling ioctl() to re-read partition table.
```

```
Syncing disks.
```

Formatando em xfs

Formatando em xfs

```
1. [root@GNCASHPL06128 ~]# mkfs.xfs /dev/sdc1
2. meta-data=/dev/sdc1          isize=512    agcount=4, agsize=1966016 blks
3.                =               sectsz=512   attr=2, projid32bit=1
4.                =               crc=1        finobt=0, sparse=0
5. data                =               bsize=4096 blocks=7864064, imaxpct=25
6.                =               sunit=0      swidth=0 blks
7. naming              =version 2          bsize=4096   ascii-ci=0 ftype=1
8. log                 =internal log        bsize=4096   blocks=3839, version=2
9.                =               sectsz=512   sunit=0 blks, lazy-count=1
10. realtime            =none              extsz=4096   blocks=0, rtextents=0
11. [root@GNCASHPL06128 ~]# mkfs.xfs /dev/sdd1
12. meta-data=/dev/sdd1          isize=512    agcount=4, agsize=1966016 blks
13.                =               sectsz=512   attr=2, projid32bit=1
14.                =               crc=1        finobt=0, sparse=0
15. data                =               bsize=4096 blocks=7864064, imaxpct=25
16.                =               sunit=0      swidth=0 blks
17. naming              =version 2          bsize=4096   ascii-ci=0 ftype=1
18. log                 =internal log        bsize=4096   blocks=3839, version=2
19.                =               sectsz=512   sunit=0 blks, lazy-count=1
20. realtime            =none              extsz=4096   blocks=0, rtextents=0
```

Criação dos diretórios

```
[root@GNCASHPL06128 ~]# mkdir -p /sapmnt/PPO
[root@GNCASHPL06128 ~]# mkdir -p /usr/sap
[root@GNCASHPL06128 ~]# chmod 775 /sapmnt/PPO
[root@GNCASHPL06128 ~]# chmod 775 /usr/sap
```

Mount das partições:

```
[root@GNCASHPL06128 ~]# mount /dev/sdc1 /sapmnt/PPO
[root@GNCASHPL06128 ~]# mount /dev/sdd1 /usr/sap
```

Listagem dos filesystems:

```
1. [root@GNCASHPL06128 ~]# df -h
2. Filesystem                Size      Used Avail Use% Mounted on
3. devtmpfs                   16G         0    16G   0% /dev
4. tmpfs                      16G       4.0K    16G   1% /dev/shm
5. tmpfs                      16G       28M    16G   1% /run
6. tmpfs                      16G         0    16G   0% /sys/fs/cgroup
7. /dev/sda2                  21G       5.1G    16G  25% /
8. tmpfs                      3.2G         0    3.2G   0% /run/user/1237252925
9. /dev/mapper/vg_data-lv_data 200G       33M   200G   1% /install
10. /dev/sdc1                  30G       33M    30G   1% /sapmnt/PPO
11. /dev/sdd1                  30G       33M    30G   1% /usr/sap
```

Fixação no /etc/fstab para reboot:

```
1. [root@GNCASHPL06128 ~]# cat /etc/fstab
2.
3. #
4. # /etc/fstab
5. # Created by anaconda on Wed Dec 21 09:31:39 2016
6. #
7. # Accessible filesystems, by reference, are maintained under '/dev/disk'
8. # See man pages fstab(5), findfs(8), mount(8) and/or blkid(8) for more info
9. #
10. UUID=98988495-77c4-4285-blea-86cdd8b46efb /                xfs defaults 0 0
11. UUID=c9aaa7d9-f9a9-4618-9e33-b0612ealac72 swap             swap defaults 0 0
12. /dev/vg_data/lv_data /install          xfs defaults 0 0
13. /dev/sdc1 /sapmnt/PPO    xfs defaults 0 0
14. /dev/sdd1 /usr/sap      xfs defaults 0 0
```