

EDT — Change Log (V1.05-0)

Sector7 USA LLC · EDIT/EDT for Linux and Windows

July 2026 · V1.05-0

Table of contents

EDT Change Log

V1.05-0 — 2026-07-17

Licensing / startup

V1.04-0 — 2026-07-16

Screen mode

HELP / docs

V1.03-0 — 2026-07-15

Partials → faithful

Missing verbs

Host RMS / versions

Soft residue

V1.02-0 — 2026-07-15

Line mode

Screen / keypad / nokeypad

Invocation / journal / HELP

V1.01-0 — 2026-07-15

V1.00-1 — earlier (pre-version-field)

EDT Change Log

Product: Sector7 EDIT/EDT (`edt.cpp`)

Current release: V1.05-0

Release date: 2026-07-17

Compared against: OpenVMS EDT V3.13 on host `t86` (OpenVMS x86_64 V9.2-3)

This file is the running release log. Recreate or extend it from:

```
git log --edt/ --oneline
# plus the Release identity block in edt.cpp (EDT_VERSION_* / EDT_RELEASE_DATE)
```

Bump `EDT_VERSION_MAJOR` / `MINOR` / `EDIT` and `EDT_RELEASE_DATE` in `edt.cpp` on every public release; `SHOW VERSION` / `VERSION` print both.

V1.05-0 — 2026-07-17

Licensing made optional + splash-once startup, from user field feedback.

Licensing / startup

- **S7SECURITY.INI is now OPTIONAL** — EDT runs whether or not a security file is present. The editor no longer refuses to start when the file is missing or unreadable; the old `edt: security file not found` hard-exit is gone.
- **Splash shown once, then suppressed** — on first launch (no `splash=off` flag present) the branded splash shows once for its usual duration, after which EDT writes a plain-text `S7SECURITY.INI` containing `splash=off` at the resolved path (`$S7SECURITY`, else `$HOME/S7SECURITY.INI`). Subsequent launches read that flag and skip the splash. Delete the file (or set `splash=on`) to see the splash again.
- **Legacy license blob still honoured** — an existing encrypted `S7SEC1` blob is read tolerantly to preserve the licensed name/email on the splash, but it is no longer required and is replaced by the plain `splash=off` flag once the splash has been shown. `s7security/mksecurity` and `s7licdb` still generate encrypted blobs (now effectively single-use).
- **Unlicensed splash drops the "licensed to ..." line and shows the plain**
`(c) Sector7 USA LLC EDT` banner.

V1.04-0 — 2026-07-16

Screen-mode usability + documentation pass from user field feedback.

Screen mode

- **GOLD echo** — after a GOLD chord the status line now shows the resolved function (e.g. `PASTE`, `OPEN LINE`, `BOTTOM`) instead of leaving the literal `GOLD` prompt. (`gold_function_name()` / `handle_gold_key`)
- **Debug key display** — new `-d` / `-k` (also `/DEBUG`) switch shows the decoded name and raw code of the last key pressed on the status line (e.g. `KEY: PF1/F1 (code 265 / 0x109)`), for mapping foreign keyboards and Num Lock.
- **SET KEYPAD PC** — maps a PC numeric keypad's top row (`/ * -`) onto PF2/PF3/PF4 in screen mode (PuTTY application-keypad convention); `DEL W` moves to the PC `+` key. Default `SET KEYPAD EDT` keeps strict DEC mapping (keypad `-` = `DEL W`).

HELP / docs

- **HELP screen ASCII fix** — replaced Unicode em-dash / arrow glyphs that rendered as garbage ("`@`"-like) characters on non-UTF-8 terminals.
- **Reference §7.1 rewritten** — now shows both a **VT100/VT220** and a **PC** keypad layout, each key with KeyID / normal / GOLD function on separate lines, plus Num Lock → PF1 (GOLD) guidance.

- **PDF code blocks** — light background instead of dark navy, so fenced blocks (including the §7.1 keypad diagram) are legible in print / Adobe.

V1.03-0 — 2026-07-15

Fidelity close-out: former PARTIAL / MISSING / deferred RMS host stubs.

Partials → faithful

- Wildcards: VMS % matches like ? (single char)
- SET LINES n clamps screen text window; SET TRUNCATE clips horizontally (no soft-wrap scroll)
- SET PARAGRAPH WPS|NOWPS changes FILL joining; SET TEXT FORMFEED used in TYPE
- SET TERMINAL updates SHOW + TERM; SET KEYPAD WPS reports WPS (EDT GOLD map)
- RESEQUENCE /DUPLICATE uses increment 0 (same sequence on all lines)
- HELP / SET HELP file; topics XLATE RETAIN RANGE FILES JOURNAL
- -journal= / /JOURNAL=; text journal host model documented

Missing verbs

- XLATE, RETAIN / STORE TEXT, RANGE sticky, FILES, .+N/ .-N, SUBSTITUTE/old/new/N

Host RMS / versions

- SET RMS FIXED n|VARIABLE / SHOW RMS on WRITE/EXIT
- SET VERSIONING / EDT_VMS_VERSIONS → ;n sibling saves (POSIX approx)

Soft residue

- Text journal ≠ binary OVMS; RMS/ ;n not Files-11

V1.02-0 — 2026-07-15

Closing pass for identified OVMS fidelity gaps (**RMS** / **;n** **versioning deferred** at the time).

Line mode

- `WRITE file [range] [BUFFER name] range form`
- Multiline `INSERT` until Ctrl/Z, `^Z`, or `.`
- Line-mode `TAB` (spaces to next stop)
- Ctrl/C abort (`*Abort*`) on TYPE / FIND / SUBSTITUTE loops
- `/BRIEF[:n]` for TYPE / FIND
- `SET SEARCH WORD / BEGIN / END` wired into FIND
- `RESEQUENCE /SEQUENCE=start:incr` with 8-column `NNNNN.00` prefixes
- `BELL, DATE, TAB ADJUST, SUBSTITUTE/old/new/, XLATE stub` (from V1.01+)

Screen / keypad / nokeypad

- `SET CURSOR` soft scroll margins applied
- LK201: PgUp/PgDn, Insert→PASTE, Find→FNDNXT, Select, Command→prompt
- Ctrl/K interactive DEFINE KEY; GOLD+Ctrl/K → DEL EOL
- Ctrl/C clears GOLD / select in screen mode
- **NOKEYPAD** mode + inline `CHANGE ;cmds`
- Nokeypad alphabet: C/W/L/EOL/BOL/PAGE, ADV/BACK, DC/DW/DL, SEL/CUT/PASTE/APPEND, TOP/BOTTOM, FIND, INSERT...ESC, **CHGC/CHNGCASE, CLSS/RESET, EX/EXIT/EXT**

Invocation / journal / HELP

- `-output= / /OUTPUT=, -readonly / /READ_ONLY, -recover / /RECOVER, /STAY`
- Text `.jou` append; recover replay; **delete .jou on clean EXIT**
- `HELP` topics: SET, SHOW, CHANGE, KEYPAD, NOKEYPAD, VERSION
- Release banner: `V1.02-0 + Release date: 2026-07-15`

V1.01-0 — 2026-07-15

First numbered public release identity + SET/SHOW surface expansion.

- Release identity constants + `SHOW VERSION` / `VERSION` / `HELP` / usage banners
- SET/SHOW: AUTOREPEAT, CASE, COMMAND, CURSOR, FNF, HELP, KEYPAD, LINES, PARAGRAPH, REPEAT, SCREEN, SUMMARY, TERMINAL, TEXT, TRUNCATE, FILES, MODE
- `SUBSTITUTE/old/new/` delimiters; TAB ADJUST; BELL; DATE; RESEQUENCE soft-ack
- GOLD digit-repeat; SPECINS decimal ASCII; Ctrl/D direction toggle
- GOLD+PF2 BOTTOM; GOLD+Enter SUBS; KP0 LINE; Ctrl/J LINEFEED
- Minimal journal append + `-recover`
- CLI `-readonly`, `-output=`

V1.00-1 — earlier (pre-version-field)

Baseline Sector7 EDT in `edt.cpp`: line + CHANGE modes, named buffers, SELECT model, FIND wildcards (`%/*`), DEFINE KEY/MACRO, UNDO/REDO snapshots, core keypad map, `-command / EDT_INI`.

Sector7 USA LLC — EDIT/EDT for Linux and Windows