# 1 Simple Applications of macroscopic thermodynamics

### 1.1 General relationship of thermodynamics

Fundamental thermodynamic relation for a quasi-static process:

$$dS = \frac{dQ}{T}$$

where

$$dQ = dE + dW = dE + pdV$$

The only external parameter of change is V

$$\implies dE = TdS - pdV$$

This specifies certain relationship between T, S, p, V i.e. S & V are independent variables

$$E = E(S, V)$$

So we have a pure mathematical relationship

$$dE = \left(\frac{\partial E}{\partial S}\right)_{V} dS + \left(\frac{\partial E}{\partial V}\right)_{S} dV$$

where

$$\begin{cases} T = \left(\frac{\partial E}{\partial S}\right)_V \\ -p = \left(\frac{\partial E}{\partial V}\right)_S \end{cases}$$

which we already know! Because dE is an exact differential

$$\left(\frac{\partial T}{\partial V}\right)_S = -\left(\frac{\partial p}{\partial S}\right)_V$$

this is known as the first Maxwell relation (wiki).

### How about S, P?

From our favorite starting point

$$dE = TdS - pdV$$

we need to change  $dV \to dp$  so from chain rule

$$d(pV) = pdV + Vdp \implies pdV = d(pV) - Vdp$$

so

$$dE = TdS - d(pV) + Vdp$$

or

$$d(E + pV) = TdS + Vdp$$

lets call this new parameter H = E + pV the **enthalpy** i.e.

$$H = H(S, p)$$

So

$$\begin{cases} T = \left(\frac{\partial H}{\partial S}\right)_p \\ V = \left(\frac{\partial H}{\partial p}\right)_S \end{cases}$$

where dH is an exact differential

$$\left(\frac{\partial T}{\partial p}\right)_S = \left(\frac{\partial V}{\partial S}\right)_p$$

or the second Maxwell relation!

**Worksheet** We can derive the Helmholtz free energy F = F(T, V) by starting with

$$d(TS) = TdS + SdT \implies TdS = d(TS) - SdT$$

so

$$\begin{split} dE &= d(TS) - SdT - pdV \\ d(E - TS) &= -SdT - pdV \end{split}$$

1. Thus the Hemholtz free energy  $F \equiv E - TS$  so

$$\begin{split} dF &= dE - (TdS + SdT) \\ &= TdS - pdV - Tds - SdT \\ &= -SdT - pdV \end{split}$$

2. So F = F(T, V) the we know that

$$\begin{cases} -S = \left(\frac{\partial F}{\partial T}\right)_V \\ -p = \left(\frac{\partial F}{\partial V}\right)_T \end{cases}$$

and dF is an exact differential

$$\left(\frac{\partial S}{\partial V}\right)_T = \left(\frac{\partial p}{\partial T}\right)_V$$

Finally for independent parameters T, p:

$$dE = TdS - pdV$$

we need to change  $dV \to dp$  so from chain rule

$$d(pV) = pdV + Vdp \implies pdV = d(pV) - Vdp$$

so also using TdS = d(TS) - SdT

$$\begin{split} dE &= (d(TS) - SdT) - (d(pV) - Vdp) \\ d(E - TS + pV) &= -SdT + VdP \end{split}$$

where G = E - TS + pV is the Gibbs free energy G = G(T, p)

$$\begin{cases} -S = \left(\frac{\partial G}{\partial T}\right)_p \\ V = \left(\frac{\partial G}{\partial p}\right)_T \end{cases}$$

and dG is an exact differential

$$\left(\frac{\partial V}{\partial T}\right)_{p} = -\left(\frac{\partial S}{\partial p}\right)_{T}$$

Summary of Maxwell relations

$$\begin{split} \left(\frac{\partial T}{\partial V}\right)_S &= -\left(\frac{\partial p}{\partial S}\right)_V \\ \left(\frac{\partial T}{\partial p}\right)_S &= \left(\frac{\partial V}{\partial S}\right)_p \\ \left(\frac{\partial S}{\partial V}\right)_T &= \left(\frac{\partial p}{\partial T}\right)_V \\ \left(\frac{\partial V}{\partial T}\right)_p &= -\left(\frac{\partial S}{\partial p}\right)_T \end{split}$$

or in box form Where the components are horizontal (TS) and vert (pV) give us the relations. e.g. someothing

$$\begin{array}{c|c} E & F \\ \hline H & G \end{array}$$

Review of Maxwell relations the DoS and external parameters of the system

$$(T,S)$$
 and  $(p,V)$ 

are not independent, but related through

$$dE = Tds - pdV$$

From this we can get the Maxwell relations

$$\begin{split} \left(\frac{\partial T}{\partial V}\right)_S &= -\left(\frac{\partial p}{\partial S}\right)_V \\ \left(\frac{\partial T}{\partial p}\right)_S &= \left(\frac{\partial V}{\partial S}\right)_p \\ \left(\frac{\partial S}{\partial V}\right)_T &= \left(\frac{\partial p}{\partial T}\right)_V \\ \left(\frac{\partial V}{\partial T}\right)_T &= -\left(\frac{\partial S}{\partial p}\right)_T \end{split}$$

which can be derived from the Thermodynamic functions

$$E = E(S, V)$$

$$H = H(S, p) = E + pV$$

$$F = F(T, V) = E - TS$$

$$G = G(T, p) = E - TS + pV$$

#### 1.2 Specific Heats

• Molar specific heat at constant volume dV = 0

$$C_V = \frac{1}{n} \left( \frac{dQ}{dT} \right)_V \quad dE = dQ = nC_v dT$$

• Molar specific heat for constant pressure dp = 0

$$C_p = \frac{1}{n} \left( \frac{dQ}{dT} \right)_p = C_V + \frac{1}{n} p \left( \frac{dV}{dT} \right)_p$$

When comparing the two specific heats we can infer that  $C_p > C_V$  because the heat dQ has to both increase the internal energy and do mechanical work to expand the volume:

$$dQ = dE + pdV = nC_V dT + pdV$$

• For an ideal gas

$$pV = nRT$$

$$pdV = nRdT$$

$$\implies \left(\frac{dV}{dT}\right) = \frac{nR}{p}$$

thus

$$C_p = C_V + R$$

where we define

$$\gamma = \frac{C_p}{C_v} = 1 + \frac{R}{C_V}$$

For the idea gas molecule the energy is given by

$$E(T) = \frac{3}{2}nRT$$

where there is 3 degrees of freedom thus

$$C_V = \frac{1}{n} \frac{dE}{dT} = \frac{3}{2} R$$
 
$$C_p = C_V + R = \frac{5}{2} R$$

For a diatomimc molecule there are 2 extra degrees of freedom for rotaion so

$$\gamma = \frac{C_p}{C_V} = \frac{5}{3}$$

### 1.3 Adiabatic expansion or compression

Some definitions:

• "Isothermal": T is constant  $\implies pV = \text{Constant}$ .

• "Adiabatic": dQ = 0

$$\implies 0 = dE + pdV$$
$$= nC_V dT + pdV$$

So from the ideal gas law pV = nRT we can get

$$VdP + pdV = nRdT$$

and substituting dT into the adiabatic expression

$$dQ = 0 = V\frac{C_V}{R}dP + \frac{C_VP}{R}dV + pdV$$

which can be rewritten as

$$0 = (C_V + R)pdV + C_V V dP = C_p pdV + C_v V dp$$

or dividing by  $C_V PV$  we ge

$$\gamma \frac{dV}{V} + \frac{dP}{P} = 0$$

Integration then gives

$$\gamma \ln V + \ln P = \text{Constant} \implies \ln(PV^{\gamma}) = \text{Constant}$$

or

$$PV^{\gamma} = \text{Constant}$$

#### Worksheet

• Pumping a bike tire, a liter or air at 1 atm is compressed *adiabatically* to 7 atm. (Air is mostly diatomic gas)

- For diatomic gas

$$E(T) = \frac{5}{2}nRT$$

So the specific heats are

$$C_V = \frac{1}{n} \frac{dE}{dT} = \frac{5}{2} R C_p = C_V + R = \frac{7}{2} R$$

which gives us

$$\gamma = \frac{C_p}{C_V} = \frac{7}{5}$$

- The final volume after compression is

$$p_i V_i^{\gamma} = p_f V_f^{\gamma}$$

or

$$(1 \text{ atm})(1 \text{ L})^{7/5} = (7 \text{ atm})V_f^{7/5} \implies V_f = 0.25 \text{ L}$$

– Work done compressing air: using  $p_i V_i^{\gamma} = 1 \implies p = \frac{1}{V^{\gamma}}$ 

$$W = \int_{V_i}^{V_f} p dV = \int_{V_i}^{V_f} \frac{1}{V^{\gamma}} dV$$
$$= \frac{1}{1 - \gamma} \left( V_f^{1 - \gamma} - V_i^{1 - \gamma} \right)$$

- If initial temp is 300 K, the final temp is

$$P_{i}V_{i} = nRT_{i} \quad P_{f}V_{f} = nRT_{f}$$

$$\implies \frac{P_{f}V_{f}}{P_{i}V_{i}} = \frac{T_{f}}{T_{i}}$$

• If the compression is isothermal (pumping very slowly) how does the answers change?

#### General case:

$$C_V = \left(\frac{dQ}{dT}\right)_V = T\left(\frac{\partial S}{\partial T}\right)_V$$
$$C_p = \left(\frac{dQ}{dT}\right)_p = T\left(\frac{\partial S}{\partial T}\right)_p$$

#### 1.4 Entropy

Consider S = S(T, P)

$$dQ = TdS = T \left[ \left( \frac{\partial s}{\partial T} \right)_P dT + \left( \frac{\partial S}{\partial P} \right)_T dP \right]$$
$$= C_P dT + T \left( \frac{\partial S}{\partial P} \right)_T dP$$

#### 1.5 Specifc heats again

General relation between  $C_v$  and  $C_p$  for non-ideal gas  $(C_p - C_v = R)$ ,

$$C_V = \left(\frac{dQ}{dT}\right)_V = T\left(\frac{\partial S}{\partial T}\right)_V$$
$$C_P = \left(\frac{dQ}{dT}\right)_P = T\left(\frac{\partial S}{\partial T}\right)_P$$

where

$$\begin{split} dQ &= T dS = T \left[ \left( \frac{\partial S}{\partial T} \right)_P dT + \left( \frac{\partial S}{\partial P} \right)_T dP \right] \\ &= C_P dT + T \left( \frac{\partial S}{\partial P} \right)_T dP \end{split}$$

The pressure P(T, V) with temp and volume dependence has a differential

$$dP = \left(\frac{\partial P}{\partial T}\right)_{V} dT + \left(\frac{\partial P}{\partial V}\right)_{T} dV$$

and since  $C_V$  acknowledges fixed volume dV = 0 we get

$$C_V = \left(\frac{dQ}{dT}\right)_V = C_p + T\left(\frac{\partial S}{\partial p}\right)_T \left(\frac{\partial P}{\partial T}\right)_V$$

where we can replace the entropy term wit the Maxwell relation

$$\left(\frac{\partial S}{\partial P}\right)_T = - \left(\frac{\partial V}{\partial T}\right)_P$$

We define the "volume coefficient of expansion"

$$\alpha \equiv \frac{1}{V} \left( \frac{\partial V}{\partial T} \right)_P$$

so

$$\left(\frac{\partial S}{\partial P}\right)_T = -\alpha V$$

The second term is not well defined since fixing volume while increasing pressure is hard to due (e.g. filling a water bottle with more and more water). Now using the volume dependence V(P,T) i.e.

$$dV = \left(\frac{\partial V}{\partial T}\right)_P dT + \left(\frac{\partial V}{\partial P}\right)_T dP = 0$$

and moving thing around we get

$$\left(\frac{dP}{dT}\right)_{V} = -\frac{\left(\frac{\partial V}{\partial T}\right)_{P}}{\left(\frac{\partial V}{\partial P}\right)_{T}}$$

where we define another term

$$\kappa = -\frac{1}{V} \left( \frac{\partial V}{\partial P} \right)_T$$

AKA the "isothermal compressibility" thus

$$C_P - C_V = VT \frac{\alpha^2}{\kappa}$$

One check we can do is use the Ideal gas law to calculate  $\alpha$  and  $\kappa$  then see if the above equation gives us the relation  $C_P - C_V = R$ 

## 1.6 Entropy and Internala energy

S(T, V) doing the same thing

$$\begin{split} dS &= \left(\frac{\partial S}{\partial T}\right)_{V} dT + \left(\frac{\partial S}{\partial V}\right)_{T} dV \\ &= \frac{C_{V}}{T} dT + \left(\frac{\partial P}{\partial T}\right)_{N} dV \end{split}$$

etc

## 1.7 Free expansion of a gas

For the general case

$$dE = 0$$
$$E = E(T, V)$$




Figure 1.1: Free expansion of a gas

Van de Waals Gas

$$\left(P + \frac{a}{v^2}\right)(v - b) = RT \quad E = E(T, V)$$
$$v = \frac{V}{n}$$

#### 1.8 Heat Engine

What is a heat engine? Heat  $\rightarrow$  Work.

Heat Reservoir





Figure 1.2: (top) reverse "easy" process converting work to heat. (botton) Heat Engine converting heat from a reservoir into work.

- For a heat engine: whatever mechanisms needed to retune to the same original condition; go through a cycle; otherwise, engine cannot continuously operate.
- Ideally perfect engine: q = w or 100% efficiency

A perfect engine *violates* the 2nd law of thermodynamics  $\Delta S \geq 0$ .

- entropy change for engine and external device  $\Delta S = 0$
- entropy change for hea reservoir  $\Delta S = -q/T$  thus

$$\Delta S_{\rm tot} = -\frac{q}{T} < 0$$

Building a heat engine: Using two heat reservoirs




Figure 1.3: Heat engine using two heat reservoirs

Where we make  $q_1 > q_2$  so that heat flows from  $T_1 \to T_2$  so that

$$W = q_1 - q_2 \implies q_2 = q_1 - W$$

so the total entropy change is

$$\Delta S_{\text{tot}} = -\frac{q_1}{T_1} - \frac{q_2}{T_2} \ge 0$$

$$= -\frac{q_1}{T_1} + \frac{q_1 - W}{T_2}$$

$$\implies \frac{W}{T_2} \le q_1 \left(\frac{1}{T_1} - \frac{1}{T_2}\right)$$

thus the efficiency of the engine

$$\eta = \frac{W}{q_1} \le T_2 \left(\frac{1}{T_2} - \frac{1}{T_1}\right)$$

$$= 1 - \frac{T_2}{T_1}$$

#### Carnot Engine




Figure 1.4: 4 stages of Carnot Engine

- $a \to b$ : adiabatic (no heat exchange) bringing colder  $T_2 \to T_1$
- $b \to c$ : isothermal (constant temp) adding heat  $q_1$  from hot reservoir
- $c \to d$ : adiabatic (no heat exchange) cooling down  $T_1 \to T_2$  as work is done through expansion
- $d \to a$ : isothermal (constant temp) releasing heat  $q_2$  to cold reservoir

Worksheet Carnot Engine using an ideal gas:

The work done is

$$W = \int_{a}^{b} PdV + \int_{b}^{c} PdV + \int_{c}^{d} PdV + \int_{d}^{a} PdV$$

•  $b \to c$ : Using the ideal gas law PV = nRT we get

$$W = \int P dV = \int_{V_*}^{V_c} \frac{nRT_1}{V} dV = nRT_1 \ln \frac{V_c}{V_b}$$

and since  $\Delta E = 0$  we know that

$$q_1 = W = nRT_1 \ln \frac{V_c}{V_b}$$

•  $d \to a$ : Same as above

$$q_2 = nRT_2 \ln \frac{V_a}{V_d}$$

so

$$W = q_1 - q_2$$

where the work done should be the total heat of the system as we go from  $a \to b \to c \to d \to a$ , i.e.

$$\Delta E = 0 \implies W = \Delta Q$$

The efficiency of the Carnot engine is by definition

$$\eta = \frac{W}{q_1} = \frac{q_1 - q_2}{q_1} = 1 - \frac{q_2}{q_1} = 1 - \frac{T_2}{T_1} \frac{\ln(V_d/V_a)}{\ln(V_c/V_b)}$$

#### Argument:

$$\frac{V_d}{V_a} = \frac{V_c}{V_b}$$

From the adiabatic process

$$PV^{\gamma} = \text{Constant}$$

so

$$\begin{aligned} P_{a}V_{a}^{\gamma} &= P_{b}V_{b}^{\gamma} \\ P_{d}V_{d}^{\gamma} &= P_{c}V_{c}^{\gamma} \\ \Longrightarrow \frac{P_{a}V_{a}^{\gamma}}{P_{d}V_{d}^{\gamma}} &= \frac{P_{b}V_{b}^{\gamma}}{P_{c}V_{c}^{\gamma}} \end{aligned}$$

And from the Isothermal process

$$PV = \text{Constant} \implies \frac{P_a V_a}{P_b V_b} = \frac{P_d V_d}{P_c V_c}$$

From the former equation we can rewrite it as

$$\frac{P_a V_a V_a^{\gamma-1}}{P_d V_d V_d^{\gamma-1}} = \frac{P_b V_b V_b^{\gamma-1}}{P_c V_c V_c^{\gamma-1}}$$

which cancels out some terms

$$\frac{V_a^{\gamma-1}}{V_d^{\gamma-1}} = \frac{V_b^{\gamma-1}}{V_c^{\gamma-1}} \implies \frac{V_d}{V_a} = \frac{V_c}{V_b}$$

## 1.9 Refrigerators

[insert figure of 2 fridges] From the Thermo Laws

• 1st law:

$$W + q_2 + q_1$$

• 2nd law:

$$\Delta S = \frac{q_1}{T_1} + \frac{-q_2}{T_2} \ge 0$$

or

$$\frac{q_1}{q_2} \ge \frac{T_1}{T_2}$$

We define the "coefficient of performance"

$$CoP \equiv \frac{q_2}{W} = \frac{q_2}{q_1 - q_2} = \frac{1}{\frac{q_1}{q_2} - 1} \le \frac{1}{\frac{T_1}{T_2} - 1} = \frac{T_2}{T_1 - T_2}$$

Case:

• Room temp:  $T_1 = 300K$ 

• Freezer:  $T_2 = 255K$ 

so the CoP is roughly

$$\frac{255}{45} \approx 5.67$$

since less work is required to move heat rather than converting into heat, the number is greater than one COP > 1.

$$\begin{array}{c|cccc} & -TS \rightarrow & \\ \hline +pV \downarrow & E & F \\ & H & G \end{array}$$

**Recap:** Classical thermodynamics only focuses on macroscopic parameters and their measures. Key Points:

- dE = dQ + dW from 1st law.
- dE = TdS PdV, and from 2nd law dS = dQ/T
- Relationship between (T, S) and (P, V) where F is the Hemholtz, G is Gibbs, and H is enthalpy.