



☰ MariaDB

Home MariaDB Platform **Server** MaxScale Analytics Galera Cluster Cor

SECURITY > SECURING MARIADB > ENCRYPTION >
DATA-IN-TRANSIT ENCRYPTION

Ask

Requiring TLS on MariaDB Server

Explains how to enforce encrypted connections globally by enabling the `require_secure_transport` system variable, which rejects any connection attempt not using TLS or a local socket.

Overview

[MariaDB Server](#) and MariaDB Community Server support data-in-transit encryption, which secures data transmitted over the network. The server and the clients encrypt data using the Transport Layer Security (TLS) protocol, which is a newer version of the Secure Socket Layer (SSL) protocol.

TLS must be manually enabled on the server.

Enabling TLS

1. Acquire an X509 certificate and a private key for the server.
If it is a test or development server, then self-signed certificates and keys might be sufficient.
2. Determine which [system variables](#) and [options](#) you need to configure.
Mandatory system variables and options for TLS include:

System Variable/Option	Description
<u>require_secure_transport</u>	When this option is enabled, connections attempted using insecure transport will be rejected. Secure transports are SSL/TLS, Unix sockets, or named pipes.
<u>ssl_cert</u>	X509 cert in PEM format
<u>ssl_key</u>	X509 key in PEM format
<u>ssl_ca</u>	JCA file in PEM format

Useful system variables and options for TLS include:

System Variable/Option	Description
<u>ssl_capath</u>	CA directory
<u>ssl_cipher</u>	SSL cipher to use
<u>ssl_crl</u>	CRL file in PEM format
<u>ssl_crlpath</u>	CRL directory
<u>tls_version</u>	TLS protocol version for secure connections.

3. Choose a configuration file in which to configure your system variables and options.

It is not recommended to make custom changes to one of the bundled configuration files. Instead, it is recommended to create a custom configuration file in one of the included directories. Configuration files in included directories are read in alphabetical order. If you want your custom configuration file to override the bundled configuration files, then it is a good idea to prefix the custom configuration file's name with a string that will be sorted last, such as z-.

- On RHEL, CentOS, Rocky Linux, and SLES, a good custom configuration file would be: /etc/my.cnf.d/z-custom-my.cnf
- On Debian and Ubuntu, a good custom configuration file would be: /etc/mysql/mariadb.conf.d/z-custom-my.cnf

4. Set your system variables and options in the configuration file.

They need to be set in a group that will be read by [MariaDB Server](#), such as [mariadb] or [server].

For example:

```
[mariadb]
...
ssl_cert = /certs/server-cert.pem
ssl_key = /certs/server-key.pem
ssl_ca = /certs/ca-cert.pem
```

5. Restart the server.

```
$ sudo systemctl restart mariadb
```

6. Connect to the server using [MariaDB Client](#):

```
$ sudo mariadb
```

7. Confirm that TLS is enabled by confirming that the have_ssl system variable is YES with the SHOW GLOBAL VARIABLES statement:

```
SHOW GLOBAL VARIABLES LIKE 'have_ssl';
```

Variable_name	Value
have_ssl	YES

This page is: Copyright © 2025 MariaDB. All rights reserved.

Previous
[Enabling TLS on MariaDB Server](#)

Next
[Replication with Secure Connections](#)

Last updated 28 days ago

Was this helpful?



Products	Support	Resources	Company
Enterprise Platform	Customer Login	MariaDB Blog	About MariaDB
Community Server	Technical Support	Webinars	Newsroom
Download MariaDB	Remote DBA	Customer Stories	Leadership
Pricing	Professional Services	MariaDB Events	MariaDB Careers
		Documentation	Legal
		Developer Hub	Privacy Policy

© 2026 MariaDB. All rights reserved.