## Setup and Run Oozie Examples

To get familiar with Oozie, set up and try the examples.

- 1. Complete the following steps to set up the examples and copy them to the cluster:
  - a. Extract the oozie examples archive oozie-examples.tar.gz:

```
cd /opt/mapr/oozie/oozie-<version>
tar xvfz ./oozie-examples.tar.gz -C /opt/mapr/oozie/oozie-<version>/
```

b. Copy the examples to MapR-FS. Run the following command as a user that has permissions to write to the specified MapR-FS directory:

```
hadoop fs -put examples maprfs:///user/<user name>/examples
```

c. Copy the input data to MapR-FS. Run the following command as a user that has permissions to write to the specified MapR-FS directory:

```
hadoop fs -put examples/input-data maprfs:///user/<user_name>/input-data
```

d. Change permissions on the examples to make them accessible to all users. Run the following command as the root user, using sudo, or as the owner of the specified directory:

```
hadoop fs -chmod -R 777 maprfs:///user/<user_name>/examples
```

- 2. Complete the following steps to run the examples:
  - a. Choose an example and run it with the <code>oozie job</code> command. You can use the following commands to run the following examples. The <code><oozie\_port\_number></code> (../AdvancedInstallation/InstallOozie.html#InstallOozie\_\_step\_djg\_dp4\_qbb) depends on whether your cluster is secure.
    - MapReduce

/opt/mapr/oozie/oozie-<version>/bin/oozie job -oozie="http://localhost:<oozie\_port\_number>/oozie" -config /opt/mapr/oozie/oozi
e-<version>/examples/apps/map-reduce/job.properties -run

■ Spark

/opt/mapr/oozie/oozie-<version>/bin/oozie job -oozie="http://localhost:<oozie\_port\_number>/oozie" -config /opt/mapr/oozie/oozi
e-<version>/examples/apps/spark/job.properties -run

■ Hiveserver2

/opt/mapr/oozie/oozie-<version>/bin/oozie job -oozie="http://localhost:<oozie\_port\_number>/oozie" -config /opt/mapr/oozie/oozi
e-<version>/examples/apps/hive2/job.properties -run

**Note:** To run the packaged Hive examples, make /tmp on MapR-FS world-writable. Set /tmp to 777. Example:

```
hadoop fs -chmod -R 777 /tmp \,
```

If /tmp does not exist, create /tmp and then set it to 777.