

How to delete corrupted EPG




Make sure you are in us-east-1 region


Open your network inspector and look at the request response, copy the EPG id



Go to Amazon Event Bridge -> Schedules -> Search for the EPG id



Select the schedule and click the Delete button




Now go to DynamoDBn select explore items -> cms-prod table -> Query then as PK (Partition key) value provide the following:

ASSET#EPG#{EPG_ID}


In our example:

ASSET#EPG#b2d60e36f8e7dbd


Then click run



Select all items then click Delete items




Now we will remove the EPG relationship with the channel
Change the PK (Partition key) value with the channel id:
ASSET#CHANNEL#{CHANNEL_ID}
In our case:
ASSET#CHANNEL#cbf378eace354d37
Then click “Run”



Now look for the entry with the channel id as PK value and the EPG id as SK value.
For instance in our case:
PK = **ASSET#CHANNEL#cbf378eace354d37**
SK = **ASSET#EPG#b2d60e36f8e7dbd**


Select and delete the entry using the Action dropdown button




Look for the channel entity now

PK = **ASSET#CHANNEL#cbf378eace354d37**
SK = **ASSET#CHANNEL#cbf378eace354d37**

Open it and look for the epg attribute:



Remove the value **(just the value, do not delete the attribute)**



Then save and you should be able to access you channel again. From there you can start a new EPG ingestion