= Wind shear =

Wind shear , sometimes referred to as windshear or wind gradient , is a difference in wind speed and / or direction over a relatively short distance in the atmosphere . Atmospheric wind shear is normally described as either vertical or horizontal wind shear . Vertical wind shear is a change in wind speed or direction with change in altitude . Horizontal wind shear is a change in wind speed with change in lateral position for a given altitude .

Wind shear is a microscale meteorological phenomenon occurring over a very small distance, but it can be associated with mesoscale or synoptic scale weather features such as squall lines and cold fronts. It is commonly observed near microbursts and downbursts caused by thunderstorms, fronts, areas of locally higher low @-@ level winds referred to as low level jets, near mountains, radiation inversions that occur due to clear skies and calm winds, buildings, wind turbines, and sailboats. Wind shear has a significant effect during take @-@ off and landing of aircraft due to its effects on control of the aircraft, and it has been a sole or contributing cause of many aircraft accidents.

Wind shear is sometimes experienced by pedestrians at ground level when walking across a plaza towards a tower block and suddenly encountering a strong wind stream that is flowing around the base of the tower. This phenomenon is a concern for architects.

Sound movement through the atmosphere is affected by wind shear , which can bend the wave front , causing sounds to be heard where they normally would not , or vice versa . Strong vertical wind shear within the troposphere also inhibits tropical cyclone development , but helps to organize individual thunderstorms into longer life cycles which can then produce severe weather . The thermal wind concept explains how differences in wind speed at different heights are dependent on horizontal temperature differences , and explains the existence of the jet stream .

= = Definition = =

Wind shear refers to the variation of wind over either horizontal or vertical distances . Airplane pilots generally regard significant wind shear to be a horizontal change in airspeed of 30 knots ($15~m\/s$) for light aircraft , and near 45 knots ($22~m\/s$) for airliners at flight altitude . Vertical speed changes greater than 4 @ .@ 9 knots (2 @ .@ 5 m / s) also qualify as significant wind shear for aircraft . Low level wind shear can affect aircraft airspeed during take off and landing in disastrous ways , and airliner pilots are trained to avoid all microburst wind shear (headwind loss in excess of 30 knots) . The rationale for this additional caution includes : (1) microburst intensity can double in a minute or less , (2) the winds can shift to excessive cross wind , (3) 40 @ -@ 50 knots is the threshold for survivability at some stages of low @ -@ altitude operations , and (4) several of the historical wind shear accidents involved 35 @ -@ 45 knot microbursts . Wind shear is also a key factor in the creation of severe thunderstorms . The additional hazard of turbulence is often associated with wind shear .

= = Where and when it is strongly observed = =

Weather situations where shear is observed include:

Weather fronts . Significant shear is observed when the temperature difference across the front is 5 $^{\circ}$ C (9 $^{\circ}$ F) or more , and the front moves at 30 knots or faster . Because fronts are three @-@ dimensional phenomena , frontal shear can be observed at any altitude between surface and tropopause , and therefore be seen both horizontally and vertically . Vertical wind shear above warm fronts is more of an aviation concern than near and behind cold fronts due to their greater duration . Upper @-@ level jet streams . Associated with upper level jet streams is a phenomenon known as clear air turbulence (CAT) , caused by vertical and horizontal wind shear connected to the wind gradient at the edge of the jet streams . The CAT is strongest on the anticyclonic shear side of the jet , usually next to or just below the axis of the jet .

Low @-@ level jet streams. When a nocturnal low @-@ level jet forms overnight above the Earth

's surface ahead of a cold front, significant low level vertical wind shear can develop near the lower portion of the low level jet. This is also known as nonconvective wind shear since it is not due to nearby thunderstorms.

Mountains. When winds blow over a mountain, vertical shear is observed on the lee side. If the flow is strong enough, turbulent eddies known as "rotors" associated with lee waves may form, which are dangerous to ascending and descending aircraft.

Inversions . When on a clear and calm night , a radiation inversion is formed near the ground , the friction does not affect wind above the top of the inversion layer . The change in wind can be 90 degrees in direction and 40 kt in speed . Even a nocturnal (overnight) low level jet can sometimes be observed . It tends to be strongest towards sunrise . Density differences cause additional problems to aviation .

Downbursts . When an outflow boundary forms due to a shallow layer of rain @-@ cooled air spreading out near ground level from the parent thunderstorm , both speed and directional wind shear can result at the leading edge of the three dimensional boundary . The stronger the outflow boundary is , the stronger the resultant vertical wind shear will become .

= = Horizontal component = =

= = = Weather fronts = = =

Weather fronts are boundaries between two masses of air of different densities , or different temperature and moisture properties , which normally are convergence zones in the wind field and are the principal cause of significant weather . Within surface weather analyses , they are depicted using various colored lines and symbols . The air masses usually differ in temperature and may also differ in humidity . Wind shear in the horizontal occurs near these boundaries . Cold fronts feature narrow bands of thunderstorms and severe weather , and may be preceded by squall lines and dry lines . Cold fronts are sharper surface boundaries with more significant horizontal wind shear than warm fronts . When a front becomes stationary , it can degenerate into a line which separates regions of differing wind speed , known as a shear line , though the wind direction across the front normally remains constant . In the tropics , tropical waves move from east to west across the Atlantic and eastern Pacific basins . Directional and speed shear can occur across the axis of stronger tropical waves , as northerly winds precede the wave axis and southeast winds are seen behind the wave axis . Horizontal wind shear can also occur along local land breeze and sea breeze boundaries .

= = = Near coastlines = = =

The magnitude of winds offshore are nearly double the wind speed observed onshore . This is attributed to the differences in friction between land masses and offshore waters . Sometimes , there are even directional differences , particularly if local sea breezes change the wind on shore during daylight hours .

= = Vertical component = =

= = = Thermal wind = = =

Thermal wind is a meteorological term not referring to an actual wind, but a difference in the geostrophic wind between two pressure levels <formula> and <formula>, with <formula>; in essence, wind shear. It is only present in an atmosphere with horizontal changes in temperature (or in an ocean with horizontal gradients of density), i.e. baroclinicity. In a barotropic atmosphere, where temperature is uniform, the geostrophic wind is independent of height. The name stems

from the fact that this wind flows around areas of low (and high) temperature in the same manner as the geostrophic wind flows around areas of low (and high) pressure .

The thermal wind equation is

<formula>,

where the <formula> are geopotential height fields with <formula> , <formula> is the Coriolis parameter , and <formula> is the upward @-@ pointing unit vector in the vertical direction . The thermal wind equation does not determine the wind in the tropics . Since <formula> is small or zero , such as near the equator , the equation reduces to stating that <formula> is small .

This equation basically describes the existence of the jet stream, a westerly current of air with maximum wind speeds close to the tropopause which is (even though other factors are also important) the result of the temperature contrast between equator and pole.

```
= = = Effects on tropical cyclones = = =
```

Tropical cyclones are basically heat engines that are fueled by the temperature gradient between the warm tropical ocean surface and the colder upper atmosphere. Tropical cyclone development requires relatively low values of vertical wind shear so that their warm core can remain above their surface circulation center, thereby promoting strengthening. Vertical wind shear tears up the "machinery" of the heat engine causing it to break down. Strongly sheared tropical cyclones weaken as the upper circulation is blown away from the low level center.

The vertical wind shear in a tropical cyclone 's environment is very important . When the wind shear is weak , the storms that are part of the cyclone grow vertically , and the latent heat from condensation is released into the air directly above the storm , aiding in development . When there is stronger wind shear , this means that the storms become more slanted and the latent heat release is dispersed over a much larger area

```
= = = Effects on thunderstorms and severe weather = = =
```

Severe thunderstorms , which can spawn tornadoes and hailstorms , require wind shear to organize the storm in such a way as to maintain the thunderstorm for a longer period of time . This occurs as the storm 's inflow becomes separated from its rain @-@ cooled outflow . An increasing nocturnal , or overnight , low level jet can increase the severe weather potential by increasing the vertical wind shear through the troposphere . Thunderstorms in an atmosphere with virtually no vertical wind shear weaken as soon as they send out an outflow boundary in all directions , which then quickly cuts off its inflow of relatively warm , moist air and kills the thunderstorm .

```
= = = Planetary boundary layer = = =
```

The atmospheric effect of surface friction with winds aloft force surface winds to slow and back counterclockwise near the surface of the Earth blowing inward across isobars (lines of equal pressure) , when compared to the winds in frictionless flow well above the Earth 's surface . This layer where friction slows and changes the wind is known as the planetary boundary layer , sometimes the Ekman layer , and it is thickest during the day and thinnest at night . Daytime heating thickens the boundary layer as winds at the surface become increasingly mixed with winds aloft due to insolation , or solar heating . Radiative cooling overnight further enhances wind decoupling between the winds at the surface and the winds above the boundary layer by calming the surface wind which increases wind shear . These wind changes force wind shear between the boundary layer and the wind aloft , and is most emphasized at night .

In gliding, wind gradients just above the surface affect the takeoff and landing phases of flight of a glider. Wind gradient can have a noticeable effect on ground launches, also known as winch launches or wire launches. If the wind gradient is significant or sudden, or both, and the pilot maintains the same pitch attitude, the indicated airspeed will increase, possibly exceeding the maximum ground launch tow speed. The pilot must adjust the airspeed to deal with the effect of the gradient.

When landing, wind shear is also a hazard, particularly when the winds are strong. As the glider descends through the wind gradient on final approach to landing, airspeed decreases while sink rate increases, and there is insufficient time to accelerate prior to ground contact. The pilot must anticipate the wind gradient and use a higher approach speed to compensate for it.

Wind shear is also a hazard for aircraft making steep turns near the ground . It is a particular problem for gliders which have a relatively long wingspan , which exposes them to a greater wind speed difference for a given bank angle . The different airspeed experienced by each wing tip can result in an aerodynamic stall on one wing , causing a loss of control accident .

```
= = = = Parachuting = = = =
```

Wind shear or wind gradients are a threat to parachutists, particularly to BASE jumping and wingsuit flying. Skydivers have been pushed off of their course by sudden shifts in wind direction and speed, and have collided with bridges, cliffsides, trees, other skydivers, the ground, and other obstacles. Skydivers routinely make adjustments to the position of their open canopies to compensate for changes in direction while making landings to prevent accidents such as canopy collisions and canopy inversion.

Soaring related to wind shear , also called dynamic soaring , is a technique used by soaring birds like albatrosses , who can maintain flight without wing flapping . If the wind shear is of sufficient magnitude , a bird can climb into the wind gradient , trading ground speed for height , while maintaining airspeed . By then turning downwind , and diving through the wind gradient , they can also gain energy . It has also been used by glider pilots on rare occasions .

Wind shear can also create wave . This occurs when an atmospheric inversion separates two layers with a marked difference in wind direction . If the wind encounters distortions in the inversion layer caused by thermals coming up from below , it will create significant shear waves that can be used for soaring .

```
= = = = = Impact on passenger aircraft = = =
```

Strong outflow from thunderstorms causes rapid changes in the three @-@ dimensional wind velocity just above ground level . Initially , this outflow causes a headwind that increases airspeed , which normally causes a pilot to reduce engine power if they are unaware of the wind shear . As the aircraft passes into the region of the downdraft , the localized headwind diminishes , reducing the aircraft 's airspeed and increasing its sink rate . Then , when the aircraft passes through the other side of the downdraft , the headwind becomes a tailwind , reducing lift generated by the wings , and leaving the aircraft in a low @-@ power , low @-@ speed descent . This can lead to an accident if the aircraft is too low to effect a recovery before ground contact .

As the result of the accidents in the 1970s and 1980s, most notably following the 1985 crash of Delta Air Lines Flight 191, in 1988 the U.S. Federal Aviation Administration mandated that all commercial aircraft have on @-@ board wind shear detection systems by 1993. Between 1964 and 1985, wind shear directly caused or contributed to 26 major civil transport aircraft accidents in the U.S. that led to 620 deaths and 200 injuries. Since 1995, the number of major civil aircraft accidents caused by wind shear has dropped to approximately one every ten years, due to the

mandated on @-@ board detection as well as the addition of Doppler weather radar units on the ground (NEXRAD) . The installation of high @-@ resolution Terminal Doppler Weather Radar stations at many U.S. airports that are commonly affected by wind shear has further aided the ability of pilots and ground controllers to avoid wind shear conditions .

$$=$$
 $=$ $=$ $=$ Sailing $=$ $=$ $=$

Wind shear affects sailboats in motion by presenting a different wind speed and direction at different heights along the mast . The effect of low level wind shear can be factored into the selection of sail twist in the sail design , but this can be difficult to predict since wind shear may vary widely in different weather conditions . Sailors may also adjust the trim of the sail to account for low level wind shear , for example using a boom vang .

```
= = = = Sound propagation = = =
```

Wind shear can have a pronounced effect upon sound propagation in the lower atmosphere , where waves can be "bent" by refraction phenomenon. The audibility of sounds from distant sources , such as thunder or gunshots , is very dependent on the amount of shear . The result of these differing sound levels is key in noise pollution considerations , for example from roadway noise and aircraft noise , and must be considered in the design of noise barriers . This phenomenon was first applied to the field of noise pollution study in the 1960s , contributing to the design of urban highways as well as noise barriers .

The speed of sound varies with temperature . Since temperature and sound velocity normally decrease with increasing altitude , sound is refracted upward , away from listeners on the ground , creating an acoustic shadow at some distance from the source . In the 1862 , during the American Civil War Battle of luka , an acoustic shadow , believed to have been enhanced by a northeast wind , kept two divisions of Union soldiers out of the battle , because they could not hear the sounds of battle only six miles downwind .

```
= = = = Effects on architecture = = = =
```

Wind engineering is a field of engineering devoted to the analysis of wind effects on the natural and built environment. It includes strong winds which may cause discomfort as well as extreme winds such as tornadoes, hurricanes and storms which may cause widespread destruction. Wind engineering draws upon meteorology, aerodynamics and a number of specialist engineering disciplines. The tools used include climate models, atmospheric boundary layer wind tunnels and numerical models. It involves, among other topics, how wind impacting buildings must be accounted for in engineering.

Wind turbines are affected by wind shear . Vertical wind @-@ speed profiles result in different wind speeds at the blades nearest to the ground level compared to those at the top of blade travel , and this in turn affects the turbine operation . This low level wind shear can create a large bending moment in the shaft of a two bladed turbine when the blades are vertical . The reduced wind shear over water means shorter and less expensive wind turbine towers can be used in shallow seas .