A high @-@ pressure area, high or anticyclone is a region where the atmospheric pressure at the surface of the planet is greater than its surrounding environment.

Winds within high @-@ pressure areas flow outward from the higher pressure areas near their centers towards the lower pressure areas further from their centers. Gravity adds to the forces causing this general movement, because the higher pressure compresses the column of air near the center of the area into greater density? and so greater weight compared to lower pressure, lower density, and lower weight of the air outside the center.

However, because the planet is rotating underneath the atmosphere, and frictional forces arise as the planetary surface drags some atmosphere with it, the air flow from center to periphery is not direct, but is twisted due to the Coriolis effect, or the merely apparent force that arise when the observer is in a rotating frame of reference. Viewed from above this twist in wind direction is in the same direction as the rotation of the planet.

The strongest high @-@ pressure areas are associated with cold air masses which push away out of polar regions during the winter when there is less sun to warm neighboring regions. These Highs change character and weaken once they move further over relatively warmer water bodies.

Somewhat weaker but more common are high @-@ pressure areas caused by atmospheric subsidence, that is, areas where large masses of cooler drier air descend from an elevation of 8 to 15 km after the lower temperatures have precipitated out the lighter water vapor. ( H2O is about half of the molecular weight of the other two main constituents of the atmosphere? Oxygen, O2, and Nitrogen, N2.)

Many of the features of Highs may be understood in context of middle- or meso @-@ scale and relatively enduring dynamics of a planet 's atmospheric circulation . For example , massive atmospheric subsidences occur as part of the descending branches of Ferrel cells and Hadley cells . Hadley cells help form the subtropical ridge , steer tropical waves and tropical cyclones across the ocean and is strongest during the summer . The subtropical ridge also helps form most of the world 's deserts .

On English @-@ language weather maps, high @-@ pressure centers are identified by the letter H. Weather maps in other languages may use different letters or symbols.

= = Wind circulation in the northern and southern hemispheres = =

The direction of wind flow around an atmospheric high @-@ pressure area and a low @-@ pressure area, as seen from above, depends on the hemisphere.

The scientific terms in English used to describe the weather systems generated by highs and lows were introduced in the mid @-@ 1800s, mostly by the British. The scientific theories which explain the general phenomena originated about two centuries earlier.

The term Cyclone was coined by Henry Piddington of the British East India Company to describe an especially destructive storm in Mauritius, during February 1845. A cyclone forms around a low @-@ pressure area. Anticyclone, the term for the kind of weather around a high @-@ pressure area, was coined in 1877 by Francis Galton to indicate an area whose winds revolved in the opposite direction of a cyclone. In British English, the opposite direction of clockwise is referred to as anticlockwise, making the label anticyclones a logical extension.

A simple rule of thumb is that for high @-@ pressure areas , where generally air flows from the center outward , the coriolis force given by the earth 's rotation to the air circulation is in the opposite direction of earth 's apparent rotation if viewed from above the hemisphere 's pole . So , both the earth and winds around a low @-@ pressure area rotate counter @-@ clockwise in the northern hemisphere , and clockwise in the southern . The opposite to these two cases occurs in the case of a high . These results derive from the Coriolis effect ; that article explains in detail the physics , and provides an animation of a model to aid understanding .

High @-@ pressure systems form due to downward motion through the troposphere, the atmospheric layer where weather occurs. Preferred areas within a synoptic flow pattern in higher levels of the troposphere are beneath the western side of troughs.

On weather maps, these areas show converging winds (isotachs), also known as confluence, or converging height lines near or above the level of non @-@ divergence, which is near the 500 hPa pressure surface about midway up through the troposphere, and about half the atmospheric pressure at the surface.

High @-@ pressure systems are alternatively referred to as anticyclones . On English @-@ language weather maps , high @-@ pressure centers are identified by the letter H in English , within the isobar with the highest pressure value . On constant pressure upper level charts , it is located within the highest height line contour .

## = = Typical conditions = =

Highs are frequently associated with light winds at the surface and subsidence through the lower portion of the troposphere . In general , subsidence will dry out an air mass by adiabatic , or compressional , heating . Thus , high pressure typically brings clear skies . During the day , since no clouds are present to reflect sunlight , there is more incoming shortwave solar radiation and temperatures rise . At night , the absence of clouds means that outgoing longwave radiation ( i.e. heat energy from the surface ) is not absorbed , giving cooler diurnal low temperatures in all seasons . When surface winds become light , the subsidence produced directly under a high @-@ pressure system can lead to a buildup of particulates in urban areas under the ridge , leading to widespread haze . If the low level relative humidity rises towards 100 percent overnight , fog can form .

Strong , vertically shallow high @-@ pressure systems moving from higher latitudes to lower latitudes in the northern hemisphere are associated with continental arctic air masses . Once arctic air moves over an unfrozen ocean , the air mass modifies greatly over the warmer water and takes on the character of a maritime air mass , which reduces the strength of the high @-@ pressure system . When extremely cold air moves over relatively warm oceans , polar lows can develop . However , warm and moist ( or maritime tropical ) air masses that move poleward from tropical sources are slower to modify than arctic air masses .

## = = In climatology = =

In terms of climatology , high pressure forms at the horse latitudes , or torrid zone , between the latitudes of 20 and 40 degrees from the equator , as a result of air that has been uplifted at the equator . As the hot air rises it cools , losing moisture ; it is then transported poleward where it descends , creating the high @-@ pressure area . This is part of the Hadley cell circulation and is known as the subtropical ridge or subtropical high , and is strongest in the summer . The subtropical ridge is a warm core high @-@ pressure system , meaning it strengthens with height . Many of the world 's deserts are caused by these climatological high @-@ pressure systems .

Some climatological high @-@ pressure areas acquire regionally based names . The land @-@ based Siberian High often remains quasi @-@ stationary for more than a month during the most frigid time of the year , making it unique in that regard . It is also a bit larger and more persistent than its counterpart in North America . Surface winds accelerating down valleys down the western Pacific ocean coastline , causing the winter monsoon . Arctic high @-@ pressure systems such as the Siberian High are cold core , meaning that they weaken with height . The influence of the Azores High , also known as the Bermuda High , brings fair weather over much of the North Atlantic Ocean and mid to late summer heat waves in western Europe . Along its southerly periphery , the clockwise circulation often impels easterly waves , and tropical cyclones that develop from them , across the ocean towards landmasses in the western portion of ocean basins during the hurricane season . The highest barometric pressure ever recorded on Earth was 1 @,@ 085 @.@ 7 hectopascals (32

@.@ 06 inHg) measured in Tonsontsengel, Mongolia on 19 December 2001.

## = = Connection to wind = =

Wind flows from areas of high pressure to areas of low pressure . This is due to density differences between the two air masses . Since stronger high @-@ pressure systems contain cooler or drier air , the air mass is more dense and flows towards areas that are warm or moist , which are in the vicinity of low pressure areas in advance of their associated cold fronts . The stronger the pressure difference , or pressure gradient , between a high @-@ pressure system and a low @-@ pressure system , the stronger the wind . The coriolis force caused by the Earth 's rotation is what gives winds within high @-@ pressure systems their clockwise circulation in the northern hemisphere ( as the wind moves outward and is deflected right from the center of high pressure ) and counterclockwise circulation in the southern hemisphere ( as the wind moves outward and is deflected left from the center of high pressure ) . Friction with land slows down the wind flowing out of high @-@ pressure systems and causes wind to flow more outward than would be the case in the absence of friction . This is known as a geostrophic wind .