CBS
V500R006C70

# Charging Data Record Reference

Issue 01

Date 2019-10-17

HUAWEI TECHNOLOGIES CO., LTD.

**Copyright © Huawei Technologies Co., Ltd. 2019. All rights reserved.**

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of Huawei Technologies Co., Ltd.

**Trademarks and Permissions**

HUAWEI and other Huawei trademarks are trademarks of Huawei Technologies Co., Ltd.

All other trademarks and trade names mentioned in this document are the property of their respective holders.

**Notice**

The purchased products, services and features are stipulated by the contract made between Huawei and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, guarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

Huawei Technologies Co., Ltd.

Address: Huawei Industrial Base
Bantian, Longgang
Shenzhen 518129
People's Republic of China

Website: http://www.huawei.com

Email: support@huawei.com

# About This Document

## Purpose

This document describes details about charging data records (CDRs).

This document provides guides to understand the basic concepts and terminology related to CDRs.

## Intended Audience

This document is intended for:

- Installation and commissioning engineers
- Technical support engineers
- Service administrators

## Symbol Conventions

The symbols that may be found in this document are defined as follows.

| Symbol | Description |
|---|---|
| DANGER | Indicates an imminently hazardous situation which, if not avoided, will result in death or serious injury. |
| WARNING | Indicates a potentially hazardous situation which, if not avoided, could result in death or serious injury. |
| CAUTION | Indicates a potentially hazardous situation which, if not avoided, may result in minor or moderate injury. |
| NOTICE | Indicates a potentially hazardous situation which, if not avoided, could result in equipment damage, data loss, performance deterioration, or unanticipated results.<br>NOTICE is used to address practices not related to personal injury. |

 Copyright © Huawei Technologies Co., Ltd. 

| Symbol | Description |
| --- | --- |
| NOTE | Calls attention to important information, best practices and tips.<br>NOTE is used to address information not related to personal injury, equipment damage, and environment deterioration. |

# Change History

Changes between document issues are cumulative. The latest document issue contains all the changes made in earlier issues.

## Issue 01 (2019-10–17)

This issue is used for first office application (FOA).

 Copyright © Huawei Technologies Co., Ltd. 

# Contents

**About This Document** ..... ii

**1 Basic Concepts** ..... 1

**2 Input CDRs for Offline Rating** ..... 3

2.1 w_abr CDR ..... 3

2.2 w_smo CDR ..... 12

2.3 GPRS CDR ..... 20

2.4 TAPIN_VOICE CDR ..... 32

2.5 TAPIN_SMS CDR ..... 46

2.6 TAPIN_GPRS CDR ..... 59

**3 CDR Files Generated in the OCG** ..... 74

3.1 Basic Information About OCG CDR Files ..... 74

3.1.1 CDR Storage Directories in OCG ..... 74

3.1.2 Process of Generating offline CDRs in the OCG ..... 75

3.1.3 File Name Format of OCG-Generated CDRs ..... 75

3.1.4 Requirements on OCG-Generated CDR Files ..... 77

3.1.5 Configuring the Function of Automatically Deleting CDRs by the OCG ..... 77

3.2 OCG-Generated CDR Files ..... 78

3.2.1 w_abr CDR ..... 78

3.2.2 w_smo CDR ..... 89

**4 Charging Output CDRs** ..... 101

4.1 Basic Information About Charging Output CDRs ..... 101

4.1.1 Charging Output CDR Storage Directories ..... 101

4.1.2 Process of Generating Charging Output CDRs ..... 102

4.1.3 Content Format of a Charging Output CDR File ..... 103

4.1.4 File Name Format of Charging Output CDRs ..... 103

4.1.5 Charging Output CDR Types ..... 104

4.2 Charging Output CDR Files ..... 106

4.2.1 Common Fields in a Charging Output CDR File ..... 106

4.2.2 Extended Charging Service Information ..... 173

4.2.2.1 Extended Charging Service Information in a Voice CDR ..... 173

4.2.2.2 Extended Charging Service Information in an SMS CDR ..... 187

4.2.2.3 Extended Charging Service Information in an MMS CDR ..... 198
4.2.2.4 Extended Charging Service Information in a GPRS CDR ..... 208
4.2.2.5 Extended Charging Service Information in a Recurring Charging CDR ..... 217
4.2.2.6 Extended Charging Service Information in a Management Flow CDR ..... 223
4.2.2.7 Extended Charging Service Information in the Content-based Charging Process ..... 227
4.2.2.8 Extended Charging Service Information in a Resource Clearance CDR ..... 233
4.2.2.9 Extended Charging Service Information in a First Time Activation CDR ..... 235
4.3 Prepaid Transaction CDR Files ..... 238
4.3.1 Recharge CDR ..... 238
4.3.2 Transfer CDR ..... 293
4.3.3 Adjustment CDR ..... 338
4.3.4 Switch Primary Offering CDR ..... 386
4.3.5 Loan CDR ..... 389
4.4 Daily Dump Files ..... 410
4.4.1 Loan Daily Dump ..... 410

 Copyright © Huawei Technologies Co., Ltd. 

# 1 Basic Concepts

This topic describes the basic concepts related to CDRs.

## CDR

A CDR collects and records information about a charging event in a specific format. The information includes the call start time, call duration, and transmitted data amount. The CDR can be provided for the CBS to perform charging and settlement or for a subscriber as a service usage record.

If the CBS does not specify the charged party, it generates a CDR respectively for both the calling and called parties of the charging event. If the call duration reaches the CDR splitting threshold or there are multiple charged parties, the CBS generates multiple CDRs for the charging event.

CDRs are not generated for postpaid balance operations, including payment, transfer, and adjustment. If a site requires CDRs for postpaid balance operations, you can export the CDRs from the AR.

## Complex Field

A complex field consists of inextensible simple fields and complex sub-fields. For example, if the **USAGE** complex field in CBP-generated CDRs consists of the **USAGE_MEASURE_ID**, **ACTUAL_USAGE**, **RATE_USAGE**, and **SERVICE_UNIT_TYPE** simple fields, the format of **USAGE** is {**USAGE_MEASURE_ID**,**ACTUAL_USAGE**,**RATE_USAGE**,**SERVICE_UNIT_TYPE**}.

## Time

In this document, time-related CDR fields are recorded based on the UTC time unless otherwise stated.

## Currency Unit

For fee-related CDR fields, the CBS converts the fee to the minimum currency unit and multiplies the result by an integer that represents the currency precision. To query the currency precision, choose **Unified System Management** > **Organization and Employee** > **Business Entity** and click the **Currency** tab of the corresponding BE. For example, if the

 Copyright © Huawei Technologies Co., Ltd. 

currency precision is set to **1**, the CBS converts 1 euro to **1000** (1 x 100 x 10) before saving the amount to a CDR.

## Reserved Field

When checking CDRs, you do not need to pay attention to fields that are reserved.

 Copyright © Huawei Technologies Co., Ltd. 

# 2 Input CDRs for Offline Rating

## About This Chapter

This topic describes the formats of CDR files that are sent from third-party systems, normalized by the Mediation, and then transferred to CBP for offline rating.

2.1 w_abr CDR

This topic describes the format of offline voice CDR files sent from a third-party system (for example, MSC) and normalized by the Mediation.

2.2 w_smo CDR

This topic describes the format of offline SMS CDR files sent from a third-party system (for example, SMSC or MSC) and normalized by the Mediation.

2.3 GPRS CDR

This topic describes the format of offline data service CDR files sent from a third-party system (for example, GGSN) and normalized by the Mediation.

2.4 TAPIN_VOICE CDR

This topic describes the format of offline roam-out voice CDR files sent from a third-party system and normalized by the Mediation.

2.5 TAPIN_SMS CDR

This topic describes the format of offline roam-out SMS CDR files sent from a third-party system and normalized by the Mediation.

2.6 TAPIN_GPRS CDR

This topic describes the format of offline roam-out data CDR files sent from a third-party system and normalized by the Mediation.

## 2.1 w_abr CDR

This topic describes the format of offline voice CDR files sent from a third-party system (for example, MSC) and normalized by the Mediation.

 Copyright © Huawei Technologies Co., Ltd. 

## CDR File Name Format

w_abr_YYYYMMDD_Seqno.unl

Example: w_abr_20071012_0001.unl

## CDR File Format

Table 2-1 describes the fields in the w_abr CDR.

**Table 2-1** Fields in the w_abr CDR file

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 1 | ServiceKey | NUMBER[10] | Service key. This field identifies a traditional intelligent network service and has a fixed value of **91** for the CBS call service.<br>This field cannot be left empty. |
| 2 | SubCosID | NUMBER[10] | ID of the primary offering subscribed by the subscriber.<br>This field can be left empty. |
| 3 | Calling-Party-Address | VARCHAR2[20] | Calling number.<br>The number formats are as follows:<br>• Country code + MSISDN<br>• Country code + Area code + PSTN<br>This field cannot be left empty in most cases.<br>This field can be left empty only in the scenario where the process of charging the called party is irrelevant to the calling party in the MT process. In this scenario, the calling number is not recorded in CDRs. |
| 4 | Called-Party-Address | VARCHAR2[20] | Called number.<br>The number formats are as follows:<br>• MSISDN<br>• National prefix + MSISDN<br>• National prefix + Area code + PSTN<br>• International prefix + Country code + MSISDN<br>• International prefix + Country code + Area code + PSTN<br>This field can contain the prefix or infix of specific services.<br>This field cannot be left empty. |
| 5 | Calling-Party-NP | VARCHAR2[16] | NP prefix of the calling number.<br>This field can be left empty.<br>This field is reserved. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 6 | Called-Party-NP | VARCHAR2[16] | NP prefix of the called number.<br>This field is reserved.<br>This field can be left empty. |
| 7 | SSP-Time | VARCHAR2[14] | Timestamp reported by the SSP, which is in the time zone of the corresponding SSP.<br>Format: YYYYMMDDhhmmss<br>This field cannot be left empty. |
| 8 | MF-Indicator | NUMBER[10] | Call forwarding flag. The options are as follows:<br>• **0**: not forwarded<br>• **1**: forwarded<br>This field cannot be left empty. |
| 9 | Real-Called-Number | VARCHAR2[20] | Actual called number.<br>The number formats are as follows:<br>• Country code + MSISDN<br>• Country code + Area code + PSTN<br>This field cannot be left empty. |
| 10 | Connect-Called-Number | VARCHAR2[20] | Called number that is connected. The value can be in any format that can be recognized by the MSC. Generally, the CBS directly records the value in CDRs.<br>This field cannot be left empty. |
| 11 | Charge-Flow-Type | NUMBER[10] | Charging process type. The options are as follows:<br>• **0**: MO<br>• **1**: MT<br>• **3**: MF<br>This field cannot be left empty. |
| 12 | Calling-Partys-Category | NUMBER[10] | Calling party category. For a call initiated by an operator, this field also specifies the service language.<br>The value is obtained from the CAP_InitialDP.CallingPartysCategory parameter that is reported.<br>For example, value **00001001** indicates that the calling party is a national operator.<br>This field can be left empty. |
| 13 | Calling-Vlr-Number | VARCHAR2[10] | VLR number of the area where the calling party visits.<br>The VLR number is reported in an IDP message. If no value is reported, this field is left empty.<br>In the MO process, if the CBS uses this field to |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | analyze the visited area, this field cannot be left empty. If the CBS does not use this field to analyze the visited area, this field can be left empty.<br>In the MT process, if the visited area does not need to be analyzed for the calling party, this field can be left empty.<br>Format: Country code + NDC + LSP |
| 14 | Calling-CellID | VARCHAR 2[36] | Cell ID of the calling party.<br>If the CBS does not need to analyze the visited area based on the cell ID, this field can be left empty.<br>The format is Three-digit MCC + Two-digit MNC + Five-digit LAC + Five-digit cell ID, for example, **460002230320412**. |
| 15 | Called-Vlr-Number | VARCHAR 2[10] | VLR number of the area where the called party visits.<br>In the MO process, if the CBS uses this field to analyze the visited area, this field cannot be left empty. If the CBS does not use this field to analyze the visited area, this field can be left empty.<br>In the MT process, if the CBS uses this field to analyze the visited area, this field cannot be left empty. If the CBS does not use this field to analyze the visited area, this field can be left empty. |
| 16 | Called-CellID | VARCHAR 2[36] | Cell ID of the called party.<br>The format is Three-digit MCC + Two-digit MNC + Five-digit LAC + Five-digit cell ID, for example, **460002230320412**.<br>This field can be left empty. |
| 17 | Original-Called-Party-Id | VARCHAR 2[20] | Original called number.<br>• In the MO process, this field is left empty.<br>• In the MF process, this field records the original called number reported in an IDP message.<br>The value can be in any format that can be recognized by the MSC. Generally, the CBS directly records the value in CDRs.<br>This field can be left empty. |
| 18 | Additional-Calling-Party-Number | VARCHAR 2[20] | Additional calling number.<br>This field specifies the original calling number in the MF process and is generally left empty in other processes. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | The original calling number reported by the MSC is recorded and can be in any format. The CBS does not authenticate or process the value.<br>This field can be left empty. |
| 19 | Bearer-Capability | VARCHAR2[10] | Bearer capability for connecting calls.<br>Bearer capability connection type or transmission medium requirement on subscribers, which is reported in an IDP message.<br>If video call, fax, and data services exist, this field specifies these special services.<br>This field can be left empty. An empty value indicates a common call. |
| 20 | EventType-BCSM | NUMBER[10] | Event report.<br>This field specifies the request report event type.<br>This field can be left empty.<br>This field is reserved. |
| 21 | Redirecting-Party-Id | VARCHAR2[20] | Redirected-to number, which is implemented through the number conversion function.<br>This field indicates the redirected-to number in the MT process.<br>The number formats are as follows:<br>• International prefix + Country code + MSISDN<br>• International prefix + Country code + Area code + PSTN<br>This field can be left empty in offline CDRs. If this field is transferred, the CBS does not authenticate the value but directly records it to output CDRs. |
| 22 | Redirection-Information | VARCHAR2[36] | Redirection information.<br>The value is the same as that of **Redirectingnumber** in IDP messages. The CBS does not authenticate the value.<br>This field can be left empty. |
| 23 | Redirection-Reason | NUMBER[10] | Redirection reason, which is reported from the network side.<br>For the GSM network, the options are as follows:<br>• **0**: no call forwarding<br>• **1**: user busy<br>• **2**: no reply<br>• **3**: call forwarding unconditional<br>• **4**: others |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **6**: mobile subscriber not reachable<br>This field cannot be left empty.<br>The default value is 0. |
| 24 | UE-IMSI | VARCHAR 2[20] | IMSI of a subscriber.<br>This field can be left empty. |
| 25 | CallReferenceNumber | VARCHAR 2[128] | Call reference number.<br>• On the CDMA network, this field records the **BillID** value.<br>• On the GSM network, this field records the **CallReferenceNumber** value reported in an IDP message.<br>• For a SIP call, this field records the **Call-ID** value reported in a SIP message.<br>If an external system does not report the call reference number, the OCG generates one in the format YYYYMMDDhhmmss + Three-digit OCG ID + Four-digit automaton number.<br>**NOTE**<br>If the automaton number contains less than four digits, prefix the number with 0. If the automaton number contains more than four digits, obtain the last four digits.<br>This field can be left empty. |
| 26 | MSC-Address | VARCHAR 2[20] | MSC address.<br>If the CBS uses this field to analyze the visited area for the charged party, this field cannot be left empty. If the CBS does not use this field to analyze the visited area for the charged party, this field can be left empty.<br>Format: Country code + NDC + LSP |
| 27 | Time-Zone | NUMBER[10] | Time zone where the calling party locates.<br>This field can be left empty. If this field is left empty, the time zone in the MSC of the subscriber's visited area is the same as that of the home server. |
| 28 | CallBeginTime | VARCHAR 2[14] | Call start time.<br>Format: YYYYMMDDhhmmss<br>This field cannot be left empty. |
| 29 | CallDuration | NUMBER[10] | Call duration used for charging, in seconds.<br>This field cannot be left empty. |
| 30 | SuccessACDuration | NUMBER[10] | Duration for which fees are deducted successfully, in seconds.<br>This field cannot be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 31 | FailACDuration | NUMBER[10] | Duration for which fees fail to be deducted, in seconds.<br>This field cannot be left empty. |
| 32 | VPMNCallFlag | NUMBER[10] | Corporate call flag.<br>The default value is **-1**.<br>This field can be left empty.<br>This field is reserved. |
| 33 | CBEResultCode | NUMBER[10] | Error code sent from the CBP.<br>This field can be left empty.<br>This field is reserved. |
| 34 | DDS-Discount | NUMBER[10] | Dynamic discount.<br>This field is valid only when the dynamic discount feature is enabled and the MSC determines the dynamic discount. The default value is **0**. |
| 35 | DiameterSessionID | VARCHAR2[128] | Diameter session ID.<br>This field specifies the session ID for OCG-generated CDRs and is used for CDR audit.<br>This field can be left empty. |
| 36 | NPPrefix | VARCHAR2[10] | NP prefix of the called number.<br>This field can be left empty.<br>This field is reserved. |
| 37 | CalledHomeNetWork | VARCHAR2[10] | Home network code of the called party.<br>This field can be left empty. |
| 38 | CallingPartyLRN | VARCHAR2[20] | This field is reserved.<br>This field can be left empty. |
| 39 | CalledPartyLRN | VARCHAR2[20] | This field is reserved.<br>This field can be left empty. |
| 40 | OpposeTenantID | NUMBER[10] | Home tenant ID of the called party.<br>This field can be left empty.<br>This field is reserved. |
| 41 | Service-Free-Indicator | NUMBER[10] | Free call flag. The options are as follows:<br>• **0**: normal call<br>• **1**: free call<br>• **2**: directly connected call<br>This field cannot be left empty. |
| 42 | NumFormatOfC | NUMBER[1 | Calling number type. The options are as follows: |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | alling | 0] | • **0**: unknown<br>• **1**: national number<br>• **2**: international number<br>This field can be left empty. |
| 43 | NumFormatOfCalled | NUMBER[10] | Called number type. The options are as follows:<br>• **0**: unknown<br>• **1**: national number<br>• **2**: international number<br>This field can be left empty. |
| 44 | NumFormatOfRoute | NUMBER[10] | Routing number type. The options are as follows:<br>• **0**: unknown<br>• **1**: national number<br>• **2**: international number<br>This field can be left empty. |
| 45 | NumFormatOfOVLR | NUMBER[10] | VLR number type corresponding to the visited area of the calling party. The options are as follows:<br>• **0**: unknown<br>• **1**: national number<br>• **2**: international number<br>This field can be left empty. |
| 46 | NumFormatOfTVLR | NUMBER[10] | VLR number type corresponding to the visited area of the called party. The options are as follows:<br>• **0**: unknown<br>• **1**: national number<br>• **2**: international number<br>This field can be left empty. |
| 47 | NumFormatOfOCalled | NUMBER[10] | VLR number type corresponding to the visited area of the original called party. The options are as follows:<br>• **0**: unknown<br>• **1**: national number<br>• **2**: international number<br>This field can be left empty. |
| 48 | CalledPartyBCDNu | VARCHAR2[32] | Original called number reported in an IDP message.<br>The original called number reported in IDP messages by the MSC is recorded and can be in any format. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | This field can be left empty. |
| 49 | OriginalRedirectPartyId | VARCHAR2[32] | Original number reported in an IDP message in the MF process. The original number reported in IDP messages is recorded and can be in any format.<br>This field is left empty in other processes.<br>This field can be left empty. |
| 50 | Service-Code-Type | NUMBER[10] | Service code type. The options are as follows:<br>• **0**: bearer service code<br>• **1**: telecommunications service code<br>This field can be left empty. |
| 51 | Service-Code | NUMBER[10] | Service code.<br>This field can be left empty.<br>This field is reserved. |
| 52 | OFFLINEFILENAME | VARCHAR2[64] | Name of the original offline CDR file.<br>This field specifies the original offline CDR file name generated by the MSC. This field is left empty for offline CDRs generated by the OCG. |
| 53 | OFFLINEFILELineNo | NUMBER[10] | Line number of the original offline CDR.<br>When the value of the field is 0 or null, this field is invalid.<br>This field can be left empty. |
| 54 | TenantID | NUMBER[10] | Home BE ID of the charged party.<br>This field can be left empty. |
| 55 | Brand | NUMBER[10] | Brand of the charged party.<br>This field can be left empty. |
| 56 | CallType | NUMBER[10] | Call type. The options are as follows:<br>• **1**: international toll call<br>• **2**: toll call between charging areas<br>• **3**: toll call within a charging area<br>• **4**: local call<br>• **5**: call within the group<br>• **6**: emergency number<br>• **7**: international roaming and calling the home country number<br>• **8**: international roaming and calling the visited country number<br>• **9**: international roaming and calling the other country number<br>This field can be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 57 | OnNetFlag | VARCHAR 2[1] | Analyzed call type according to the network. The options are as follows:<br>• **0**: inter-network<br>• **1**: intra-network<br>This field can be left empty. |
| 58 | Reserved. | VARCHAR 2[20] | This field is left empty. |
| 59 | Reserved. | VARCHAR 2[255] | This field is left empty. |
| 60 | Reserved. | VARCHAR 2[255] | This field is left empty. |
| 61 | Reserved. | VARCHAR 2[12] | This field is left empty. |

# 2.2 w_smo CDR

This topic describes the format of offline SMS CDR files sent from a third-party system (for example, SMSC or MSC) and normalized by the Mediation.

## CDR File Name Format

w_smo_YYYYMMDD_Seqno.unl

Example: w_smo_20071012_0001.unl

## CDR File Format

Table 2-2 describes the fields in the w_smo CDR.

**Table 2-2** Fields in the w_smo CDR file

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 1 | SmsType | VARCHAR 2[1] | SMS message type. The options are as follows:<br>• **1**: SMPP+ or MAP3 SMS message<br>• **3**: CAP2 or CAP3 SMS message<br>• **4**: Nokia-Siemens CAMEL1 SMS message<br>This field can be left empty. |
| 2 | MessageType | VARCHAR 2[1] | Message type. The options are as follows:<br>• **1**: fee deduction request<br>• **2**: confirmation message<br>This field can be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 3 | SMSCAddress | VARCHAR2[8] | SMSC address.<br>This field can be left empty. |
| 4 | SMID | VARCHAR2[64] | SMS message ID.<br>The value is a unique SMS message ID generated by the SMSC. The CBS uses this message ID to deduct or refund fees.<br>This field can be left empty. |
| 5 | SMLength | NUMBER[10] | Length of the SMS message content.<br>This field is valid to sites that charge for SMS messages based on the SMS message length. If the SMS message length is not used as a charging factor, this field can be left empty or set to **0**. |
| 6 | MoMSCAddr | VARCHAR2[32] | MSC address of the roaming area of the SMS message sender.<br>Format: Country code + NDC + LSP<br>This field cannot be left empty. |
| 7 | MtMSCAddr | VARCHAR2[32] | MSC address of the roaming area of the SMS message recipient.<br>Format: Country code + NDC + LSP<br>This field can be left empty if the charging function is not involved in the MT process or this field is not used as a charging factor. |
| 8 | SourceAddr | VARCHAR2[32] | Number of the SMS message sender.<br>The number formats are as follows:<br>• Country code + MSISDN<br>• International prefix of the home country in the CBS + Country code + MSISDN<br>This field cannot be left empty. |
| 9 | DestAddr | VARCHAR2[32] | Number of the SMS message recipient.<br>The number formats are as follows:<br>• Country code + MSISDN<br>• International prefix of the home country in the CBS + Country code + MSISDN<br>• NP RN prefix + Country code + MSISDN<br>• Special number<br>This field cannot be left empty. |
| 10 | FeeAddr | VARCHAR2[32] | Charged number.<br>The number formats are as follows:<br>• Country code + MSISDN<br>• International prefix of the home country in |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | the CBS + Country code + MSISDN<br>This field can be left empty. |
| 11 | FeeFlag | NUMBER[10] | Fee deduction flag. The options are as follows:<br>• **1**: Charge the sender.<br>• **2**: Charge the recipient.<br>This field cannot be left empty. |
| 12 | FeeType | NUMBER[10] | Charging type. The options are as follows:<br>• **0**: default charging type (Common point-to-point SMS messages are charged based on the charge rate configured on the CBS. In other situations, SMS messages are charged based on the charge rate transferred from the SMSC.)<br>• **1**: charging by piece (The SP charges SMS messages based on the message pieces.)<br>• **2**: charging by month (fee deduction)<br>• **3**: charging by month (check)<br>• **4**: charging by the number of SMS messages without exceeding the upper limit<br>• **5**: charging by month with a limited number of SMS messages (fee deduction)<br>• **6**: charging by month with a limited number of SMS messages (check)<br>This field can be left empty. |
| 13 | FeeItdMsgNum | NUMBER[10] | Total number of SMS messages in a monthly package. This field is currently not supported.<br>This field can be left empty.<br>This field is reserved. |
| 14 | FeeSingle | NUMBER[10] | Tariff of a single SMS message when the messages are charged by piece.<br>This field can be left empty.<br>This field is reserved. |
| 15 | FeeFixed | NUMBER[10] | Charge rate of a single SMS message when the limited number of messages are charged by month.<br>The excess SMS messages are charged based on the charge rate specified by **FeeSingle**. The **FeeFixed** field is used only when SMS messages are charged by month.<br>This field can be left empty.<br>This field is reserved. |
| 16 | MessagePID | NUMBER[1 | SMS message PID. |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | 0] | This field can be left empty.<br>This field is reserved. |
| 17 | StatusReportRequest | NUMBER[10] | Indicates whether a message status report is required. The options are as follows:<br>• **0**: no<br>• **1**: yes<br>This field can be left empty. The default value is **0**. |
| 18 | OriginalNetType | NUMBER[10] | Source network type. The options are as follows:<br>• **0**: GSM<br>• **1**: CDMA<br>• **2**: TDMA<br>• **3**: SMPP<br>This field can be left empty. The default value is **0**. The system considers that the value is **0** if this field is left empty. |
| 19 | SMSReceiveTime | VARCHAR2[14] | Time when an SMS message is received.<br>When receiving a refund message, the CBS performs rating and refund based on the time.<br>This field is applicable only to fee deduction requests and is left empty for confirmation messages. |
| 20 | CallingService | VARCHAR2[32] | Identifier of an MO service, which is an array with a fixed length of 16 bytes.<br>Each byte specifies a service. The value **0** indicates that the corresponding service is not used. The value **1** indicates that the corresponding service is used in the current message.<br>The service types are as follows:<br>• **Calling_Service[0]**: SMS signature service<br>• **Calling_Service[1]**: MO SMS enhanced receipt service<br>• **Calling_Service[2]**: power-on notification service<br>This field can be left empty. |
| 21 | CalledService | VARCHAR2[32] | Identifier of an MT service, which is an array with a fixed length of 16 bytes.<br>Each byte specifies a service. The value **0** indicates that the corresponding service is not used. The value **1** indicates that the corresponding service is used in the current message. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | The service types are as follows:<br>• **Called_Service[0]**: SMS forwarding service<br>• **Called_Service[1]**: automatic reply service<br>This field can be left empty. |
| 22 | OriginalMsgID | VARCHAR2[32] | ID of the original SMS message that is associated with the current message.<br>The value is recorded in refund messages.<br>This field can be left empty. |
| 23 | SMDSendResult | NUMBER[10] | SMS message sending result. This field is set based on the corresponding value in the SMPP+ message. Value **0** indicates that an SMS message is sent successfully. The other values indicate that the SMS message fails to be sent.<br>This field cannot be left empty. |
| 24 | MsgID | VARCHAR2[32] | SMS message ID generated by the gateway.<br>This field is applicable only to inter-network and Monternet SMS messages, but left empty for intra-network SMS messages.<br>This field can be left empty.<br>This field is reserved. |
| 25 | GWID | VARCHAR2[32] | ID of the gateway that sends an SMS message.<br>This field is applicable only to inter-network and Monternet SMS messages, but left empty for intra-network SMS messages.<br>This field can be left empty.<br>This field is reserved. |
| 26 | MsgSeq | VARCHAR2[32] | SMS message ID generated by the SMSC.<br>This field is applicable only to inter-network and Monternet SMS messages, but left empty for intra-network SMS messages.<br>This field can be left empty.<br>This field is reserved. |
| 27 | SPID | VARCHAR2[32] | SP ID.<br>This field is applicable only to inter-network and Monternet SMS messages, but left empty for intra-network SMS messages.<br>This field can be left empty.<br>This field is reserved. |
| 28 | ServiceCode | VARCHAR2[32] | Service type code.<br>This field is applicable only to inter-network and Monternet SMS messages, but left empty for intra-network SMS messages. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | This field can be left empty.<br>This field is reserved. |
| 29 | SourceGWID | VARCHAR2[32] | ID of the source gateway that forwards an SMS message.<br>This field is applicable only to inter-network and Monternet SMS messages, but left empty for intra-network SMS messages.<br>This field can be left empty.<br>This field is reserved. |
| 30 | PriorityFlag | NUMBER[10] | Priority of an SMS message.<br>This field is applicable only to inter-network and Monternet SMS messages, but left empty for intra-network SMS messages.<br>This field can be left empty.<br>This field is reserved. |
| 31 | ChargingRate | NUMBER[10] | Charge rate.<br>This field is applicable only to inter-network and Monternet SMS messages, but left empty for intra-network SMS messages.<br>This field can be left empty.<br>This field is reserved. |
| 32 | ChargingType | NUMBER[10] | Charge rate type.<br>This field is applicable only to inter-network and Monternet SMS messages, but left empty for intra-network SMS messages.<br>The options are as follows:<br>• **0**: not charged, applicable only to the SP channel fee reduction scenario<br>• **1**: free<br>• **2**: charging by piece<br>• **3**: charging by month<br>• **4**: charging within an upper limit<br>For inter-network SMS messages, this field is set to **2**.<br>This field can be left empty.<br>This field is reserved. |
| 33 | CDRType | NUMBER[10] | CDR type.<br>This field is applicable only to inter-network and Monternet SMS messages, but left empty for intra-network SMS messages.<br>For Monternet SMS messages, the options are as follows: |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **1**: upstream<br>• **2**: downstream<br>• **3**: monthly SMS service control<br>For inter-network SMS messages, the options are as follows:<br>• **11**: MO CDR generated for SMS messages sent to China Unicom<br>• **12**: MT CDR generated for SMS messages sent to China Unicom<br>For inter-network SMS messages, this field is set to **11**.<br>This field can be left empty.<br>This field is reserved. |
| 34 | Discount | NUMBER[10] | Percentage-based discount.<br>The value **100** indicates that no discount is provided.<br>This field is applicable only to inter-network and Monternet SMS messages, but left empty for intra-network SMS messages.<br>This field can be left empty.<br>This field is reserved. |
| 35 | GiftResult | NUMBER[10] | This field is reserved.<br>Generally, this field can be left empty. |
| 36 | Subscription-Id-Data | VARCHAR2[32] | Charged number.<br>For E.164 numbers, the number formats are as follows:<br>• International prefix + Country code + MSISDN<br>• Country code + MSISDN<br>The value is in the calling number in the MO process and called number in the MT process.<br>This field cannot be left empty. |
| 37 | DiameterSessionID | VARCHAR2[128] | Diameter session ID.<br>This field specifies the session ID that external systems send to the CBS through DCC messages and is used for audit.<br>This field can be left empty. |
| 38 | NPPrefix | VARCHAR2[32] | NP or RN prefix of the recipient.<br>This field can be left empty.<br>This field is reserved. |
| 39 | CalledHomeNet | VARCHAR | This field can be left empty. |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | Work | 2[32] | This field is reserved. |
| 40 | OpposeTenantID | NUMBER[10] | Home tenant ID of the peer party.<br>This field can be left empty.<br>This field is reserved. |
| 41 | DCS | NUMBER[10] | Encoding mode of an SMS message that is sent. The options are as follows:<br>• **-1**: not distinguished<br>• **0**: 7-bit (English)<br>• **8**: UCS-2 (Farsi/Other)<br>• **4**: binary<br>This field can be left empty. The system considers that the value is **0** if this field is left empty. |
| 42 | NumFormatOfCalling | NUMBER[10] | Number type of the sender. The options are as follows:<br>• **0**: unknown<br>• **1**: national number<br>• **2**: international number<br>The default value is **0**. |
| 43 | NumFormatOfCalled | NUMBER[10] | Number type of the recipient. The options are as follows:<br>• **0**: unknown<br>• **1**: national number<br>• **2**: international number<br>The default value is **0**. |
| 44 | NumFormatOfOMSC | NUMBER[10] | Type of the sender number processed by the MSC of the roaming area. The options are as follows:<br>• **0**: unknown<br>• **1**: national number<br>• **2**: international number<br>The default value is **0**. |
| 45 | NumFormatOfTMSC | NUMBER[10] | Type of the recipient number processed by the MSC of the roaming area. The options are as follows:<br>• **0**: unknown<br>• **1**: national number<br>• **2**: international number<br>The default value is **0**. |
| 46 | CalledPartyBC | VARCHAR | Original recipient number reported in an IDP |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | DNu | 2[32] | message.<br>The value is reported by the MSC and can be in any format.<br>This field cannot be left empty. |
| 47 | OFFLINEFILE NAME | VARCHAR 2[64] | Name of the original offline CDR file.<br>The value is the name of the original offline CDR file collected by the MSC or SMSC and is used as the input for subscriber audit.<br>This field can be left empty. |
| 48 | OFFLINEFILE LineNo | NUMBER[10] | Line number of the original offline CDR.<br>The value is the line number of the original offline CDR collected by the MSC or SMSC and is used as the input for subscriber audit.<br>This field can be left empty. |
| 49 | TenantID | NUMBER[10] | Home BE ID of the charged party.<br>This field can be left empty.<br>This field is reserved. |
| 50 | Brand | NUMBER[10] | Brand of the charged party.<br>This field can be left empty.<br>This field is reserved. |
| 51 | CallType | NUMBER[10] | SMS message type. The options are as follows:<br>• **1**: national SMS message<br>• **2**: international toll SMS message<br>• **3**: international roaming SMS message<br>This field can be left empty. |
| 52 | OnNetFlag | VARCHAR 2[1] | Analyzed SMS message type according to the network. The options are as follows:<br>• **0**: inter-network<br>• **1**: intra-network<br>This field can be left empty. |
| 53 | reserve | VARCHAR 2[12] | This field is reserved.<br>This field can be left empty. |

# 2.3 GPRS CDR

This topic describes the format of offline data service CDR files sent from a third-party system (for example, GGSN) and normalized by the Mediation.

 Copyright © Huawei Technologies Co., Ltd. 

## CDR File Name Format

GPRS_YYYYMMDD_Seqno.unl

Example: GPRS_20091012_0001.unl

## CDR File Format

Table 2-3 describes the fields in the GPRS CDR.

**Table 2-3** Fields in the GPRS CDR file

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 1 | Session-Id | VARCHAR2[128] | Diameter session ID. The format is as follows:<br><DiameterIdentity>;<high 32 bits>;<low 32 bits>[;<optional value>]<br>• <DiameterIdentity>: The value is the same as that in the **Origin-Host** AVP.<br>• <high 32 bits>: The current system time is recorded.<br>• <low 32 bits>: The value increases cyclically. The initial value is **0**. When the system restarts, the value is set to **0**.<br>• <optional value>: This field is reserved.<br>Separate each two fields with a semicolon (;).<br>Example: OCG001.huawei.com;1876543210;523<br>This field can be left empty. |
| 2 | Origin-Host | VARCHAR2[64] | Host that sends the Diameter message.<br>This field can be left empty. |
| 3 | Origin-Realm | VARCHAR2[32] | Domain of the host that sends the Diameter message.<br>This field can be left empty. |
| 4 | Destination-Host | VARCHAR2[64] | Destination host, namely, the CBS.<br>This field can be left empty. |
| 5 | Destination-Realm | VARCHAR2[32] | Domain of the destination host, namely, domain of the CBS.<br>This field can be left empty. |
| 6 | Auth-Application-Id | NUMBER[10] | Unique ID of the application used for re-authentication and re-authorization. The options are as follows:<br>• **0**: Diameter common message |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **1**: NASREQ [NASREQ]<br>• **2**: Mobile-IP<br>• **3**: Diameter Base Accounting [DIAMMIP]<br>• **4**: DCCA<br>• **0xffffffff**: Relay<br>The default value is **0**. |
| 7 | Service-Context-Id | VARCHAR2[64] | Unique ID of a Diameter service.<br>Example: in@huawei.com<br>Currently, the values include **in@huawei.com**, **manage@huawei.com**, and **mdsp@huawei.com**.<br>This field can be left empty. |
| 8 | CC-Request-Type | NUMBER[10] | Request type. The options are as follows:<br>• **1**: initial request<br>• **2**: update request<br>• **3**: terminate request<br>• **4**: event request<br>The default value is **3**. |
| 9 | CC-Request-Number | NUMBER[10] | Request sequence number.<br>This field uniquely identifies a request in a Diameter session where multiple requests are initiated. The default value is **1**. |
| 10 | CC-Subsession-Id | VARCHAR2[64] | ID of a subsession.<br>This field can be left empty. |
| 11 | User-Name | VARCHAR2[128] | Subscriber name in the NAI format.<br>This field can be left empty. |
| 12 | Origin-State-Id | NUMBER[10] | Status ID of the host that sends a Diameter message.<br>This field can be left empty. |
| 13 | Event-Timestamp | VARCHAR2[16] | Time when an event occurs.<br>Format: YYYYMMDDHHMMSS<br>This field cannot be left empty. |
| 14 | Subscription-Id-Type | NUMBER[10] | Subscriber type. The options are as follows:<br>• **0**: E.164<br>• **1**: IMSI<br>• **2**: SIP URI |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **3**: NAI<br>• **4**: private<br>This field cannot be left empty. |
| 15 | Subscription-Id-Data | VARCHAR2[128] | Subscriber ID.<br>For E.164 numbers, the number formats are as follows:<br>• MSISDN<br>• International prefix + Country code + MSISDN<br>This field cannot be left empty. |
| 16 | Service-Identifier1 | NUMBER[10] | Service identifier.<br>The combination of **Service-Context-ID** and **Service-Identifier** can uniquely identify the service corresponding to a request.<br>This field can be left empty. |
| 17 | Termination-Cause | NUMBER[10] | Cause for the termination of a Diameter client session. The options are as follows:<br>• **1**: DIAMETER_LOGOUT (A subscriber ends the session.)<br>• **2**: DIAMETER_SERVICE_NOT_PROVIDED (The session is terminated before a subscriber receives an authorization response.)<br>• **3**: DIAMETER_BAD_ANSWER (The authorization response received by the Diameter client is not successfully processed.)<br>• **4**: DIAMETER_ADMINISTRATIVE (A subscriber is not granted the access authority or the connection is disconnected due to a management problem, for example, the Abort-Session-Request message is received.)<br>• **5**: DIAMETER_LINK_BROKEN (The communication with a subscriber is interrupted unexpectedly.)<br>• **6**: DIAMETER_AUTH_EXPIRED (A subscriber's access ends because the validity period of the authorized session ends.)<br>• **7**: DIAMETER_USER_MOVED (A subscriber is receiving the service of another Diameter client.) |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **8**: DIAMETER_SESSION_TIMEOUT (The Diameter session times out.)<br>This field can be left empty. |
| 18 | Route-Record | VARCHAR2[64] | Routing record, which can be entered only by the Diameter proxy.<br>A relay or proxy must add this field to all messages forwarded by the relay or the proxy.<br>This field can be left empty. |
| 19 | Requested-Action | NUMBER[10] | If **CC-Request-Type** in a CCR message is set to **4**, this field specifies the requested action. The options are as follows:<br>• **0**: direct debiting<br>• **1**: refund<br>• **2**: balance check<br>• **3**: price query<br>This field can be left empty. |
| 20 | CC-Time1 | NUMBER[10] | Requested, allocated, or used duration, in seconds.<br>This field can be left empty. |
| 21 | Value-Digits1 | NUMBER[20] | Value, which is used together with the **Exponent1** field. For example, to represent 0.05, set this field to **5** and **Exponent1** to **-2**.<br>This field can be left empty. |
| 22 | Exponent1 | NUMBER[10] | Exponent, which is used together with the **Value-Digits1** field.<br>This field can be left empty. |
| 23 | Currency-Code1 | NUMBER[10] | Currency code that is defined in ISO4217.<br>This field can be left empty. If this field is left empty, the default currency code of the main fund account book is used. |
| 24 | CC-Total-Octets1 | NUMBER[20] | Requested, allocated, or used traffic, in bytes.<br>This field can be left empty. |
| 25 | CC-Input-Octets1 | NUMBER[20] | Number of requested, authorized, or used bytes received from a subscriber.<br>This field can be left empty. |
| 26 | CC-Output-Octe | NUMBER[20] | Number of requested, authorized, or used |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | ts1 | | bytes sent to a subscriber.<br>This field can be left empty. |
| 27 | CC-Service-Specific-Units1 | NUMBER[10] | Number of special service units.<br>The special service is specified by **Service-Identifier** or **Rating-Group** in the **Multiple-Services-Credit-Control** AVP.<br>This field can be left empty. |
| 28 | Reporting-Reason1 | NUMBER[10] | Reason for reporting the usage of one or more types of quota. This field is extended based on the 3GPP specification. The options are as follows:<br>• **0**: THRESHOLD (The quota usage is reported in the **Used-Service-Units** AVP because the threshold is reached.)<br>• **1**: QHT (The quota usage is reported in the **Multiple-Services-Credit-Control** AVP because the QHT specified in the previous CCA message is reached. For example, the quota is not used during a specified period.)<br>• **2**: FINAL (The quota usage is reported in the **Multiple-Services-Credit-Control** AVP because a common access ends in the PS service or a subscriber ends the session in the IN service.)<br>• **3**: QUOTA_EXHAUSTED (The quota usage is reported in the **Used-Service-Units** AVP because the quota is used up.)<br>• **4**: VALIDITY_TIME (The quota usage is reported in the **Multiple-Services-Credit-Control** AVP because the life cycle of the authorized credit ends. The life cycle of the authorized credit is specified by the **Validity-Time**.)<br>• **5**: OTHER_QUOTA_TYPE (The quota is reported the **Used-Service-Units** AVP because other quotas meet the conditions for triggering the report in the case of multiple quotas.)<br>• **6**: RATING_CONDITION_CHANGE (The quota usage is reported in the |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | **Multiple-Services-Credit-Control** AVP because the rating conditions are changed. The changed rating conditions are specified by the corresponding **Trigger-Type**.)<br>• **7**: FORCED_REAUTHORISATION (The quota usage is reported in the **Multiple-Services-Credit-Control** AVP because the server initiates a re-authorization request, for example, when the server receives an RAR request.)<br>Values **1**, **2**, **4**, **6**, and **7** apply to all quota types and used in the **Multiple-Services-Credit-Control** AVP. The other values apply to a specified quota type and are used only in **Used-Service-Units**.<br>If this field is set to **6**, the event that causes the re-authorization request must be specified by the **Trigger-Type** AVP.<br>This field can be left empty. |
| 29 | Tariff-Change-Usage1 | NUMBER[10] | Indicates whether to charge the service usage using the tariff before or after tariff switch or both tariffs before and after tariff switch.<br>If this field is omitted, the charge rate is unchanged.<br>This field can be left empty. |
| 30 | CC-Time2 | NUMBER[10] | Requested, allocated, or used duration, in seconds.<br>This field can be left empty. |
| 31 | Value-Digits2 | NUMBER[20] | Value, which is used together with the **Exponent2** field. For example, to represent 0.05, set this field to **5** and **Exponent2** to **-2**.<br>This field can be left empty. |
| 32 | Exponent2 | NUMBER[10] | Exponent, which is used together with the **Value-Digits2** field.<br>This field can be left empty. |
| 33 | Currency-Code2 | NUMBER[10] | Currency code that is defined in ISO4217.<br>This field can be left empty. |
| 34 | CC-Total-Octets2 | NUMBER[20] | Requested, allocated, or used traffic, in bytes. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | This field can be left empty. |
| 35 | CC-Input-Octets2 | NUMBER[20] | Number of requested, authorized, or used bytes received from a subscriber.<br>This field can be left empty. |
| 36 | CC-Output-Octets2 | NUMBER[20] | Number of requested, authorized, or used bytes sent to a subscriber.<br>This field can be left empty. |
| 37 | CC-Service-Specific-Units2 | NUMBER[10] | Number of special service units.<br>The special service is specified by **Service-Identifier** or **Rating-Group** in the **Multiple-Services-Credit-Control** AVP.<br>This field can be left empty. |
| 38 | Multiple-Services-Indicator | NUMBER[10] | Multi-service flag.<br>This field can be left empty. |
| 39 | Reporting-Reason2 | NUMBER[10] | Reason for reporting the usage of one or more types of quota. This field is extended based on the 3GPP specification.<br>This field can be left empty. |
| 40 | Trigger-Type | NUMBER[10] | Single re-authorization event type. This field is extended based on the 3GPP specification.<br>This field can be left empty. |
| 41 | CC-Time3 | NUMBER[10] | Requested, allocated, or used duration, in seconds.<br>This field can be left empty. |
| 42 | Value-Digits3 | NUMBER[20] | Value, which is used together with the **Exponent3** field. For example, to represent 0.05, set this field to **5** and **Exponent3** to **-2**.<br>This field can be left empty. |
| 43 | Exponent 3 | NUMBER[10] | Exponent, which is used together with the **Value-Digits3** field.<br>This field can be left empty. |
| 44 | Currency-Code3 | NUMBER[10] | Currency code that is defined in ISO4217.<br>This field can be left empty. |
| 45 | CC-Total-Octets3 | NUMBER[20] | Requested, allocated, or used traffic, in bytes.<br>This field can be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 46 | CC-Input-Octets3 | NUMBER[20] | Number of requested, authorized, or used bytes received from a subscriber.<br>This field can be left empty. |
| 47 | CC-Output-Octets3 | NUMBER[20] | Number of requested, authorized, or used bytes sent to a subscriber.<br>This field can be left empty. |
| 48 | CC-Service-Specific-Units3 | NUMBER[10] | Number of special service units.<br>The special service is specified by **Service-Identifier** or **Rating-Group** in the **Multiple-Services-Credit-Control** AVP.<br>This field can be left empty. |
| 49 | Reporting-Reason3 | NUMBER[10] | Reason for reporting the usage of one or more types of quota. This field is extended based on the 3GPP specification.<br>This field can be left empty. |
| 50 | Tariff-Change-Usage2 | NUMBER[10] | Indicates whether to charge the service usage using the tariff before or after tariff switch or both tariffs before and after tariff switch.<br>If this field is omitted, the charge rate is unchanged.<br>This field can be left empty. |
| 51 | CC-Time4 | NUMBER[10] | Requested, allocated, or used duration, in seconds.<br>This field can be left empty. |
| 52 | Value-Digits4 | NUMBER[20] | Value, which is used together with the **Exponent4** field. For example, to represent 0.05, set this field to **5** and **Exponent4** to **-2**.<br>This field can be left empty. |
| 53 | Exponent4 | NUMBER[10] | Exponent, which is used together with the **Value-Digits4** field.<br>This field can be left empty. |
| 54 | Currency-Code4 | NUMBER[10] | Currency code that is defined in ISO4217.<br>This field can be left empty. |
| 55 | CC-Total-Octets4 | NUMBER[20] | Requested, allocated, or used traffic, in bytes.<br>This field can be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 56 | CC-Input-Octets4 | NUMBER[20] | Number of requested, authorized, or used bytes received from a subscriber.<br>This field can be left empty. |
| 57 | CC-Output-Octets4 | NUMBER[20] | Number of requested, authorized, or used bytes sent to a subscriber.<br>This field can be left empty. |
| 58 | CC-Service-Specific-Units4 | NUMBER[10] | Number of special service units.<br>The special service is specified by **Service-Identifier** or **Rating-Group** in the **Multiple-Services-Credit-Control** AVP.<br>This field can be left empty. |
| 59 | Service-Identifier2 | NUMBER[10] | Service identifier.<br>This field can be left empty. |
| 60 | Rating-Group | NUMBER[10] | Rating group ID. All the services of the same rating type belong to the same rating group.<br>This field can be left empty for sites that do not differentiate rating groups. |
| 61 | CC-Correlation-Id | VARCHAR2[128] | Information used to associate credit control requests generated by different components involved in a service.<br>For example, this field must be set when **Service-Context-Id** is assigned on the transmission or service layer.<br>This field can be left empty. |
| 62 | Validity-Time | NUMBER[10] | Session timeout interval reported by an external NE.<br>The CBS determines the session timeout interval based on this field value and the internal configuration.<br>This field can be left empty. |
| 63 | 3GPP-Charging-Id1 | VARCHAR2[64] | Charging ID.<br>This field can be left empty. |
| 64 | 3GPP-PDP-Type | VARCHAR2[64] | PDP context type.<br>This field can be left empty. |
| 65 | PDP-Address | VARCHAR2[64] | PDP context address.<br>This field can be left empty. |
| 66 | QOS | VARCHAR2[64] | Service quality.<br>This field can be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 67 | SGSN-Address | VARCHAR2[64] | SGSN address.<br>This field can be left empty. |
| 68 | GGSN-Address | VARCHAR2[64] | GGSN address.<br>This field can be left empty. |
| 69 | CG-Address | VARCHAR2[64] | CG address.<br>This field can be left empty. |
| 70 | 3GPP-IMSI-MCC-MNC | VARCHAR2[64] | MCC and MNC extracted from the IMSI.<br>This field can be left empty. |
| 71 | 3GPP-GGSN-MCC-MNC | VARCHAR2[64] | MCC and MNC of the network to which the GGSN belongs.<br>This field can be left empty. |
| 72 | 3GPP-NSAPI | VARCHAR2[64] | Network service access point identifier (NSAPI).<br>This field can be left empty. |
| 73 | Called-Station-Id | VARCHAR2[64] | APN address.<br>If charging is implemented based on the APN address, this field cannot be left empty. |
| 74 | 3GPP-Session-Stop-Indicator | VARCHAR2[64] | Session termination flag.<br>This field can be left empty. |
| 75 | 3GPP-Selection-Mode | VARCHAR2[64] | Selection mode.<br>This field can be left empty. |
| 76 | 3GPP-Charging-Characteristics | VARCHAR2[64] | Charging attribute.<br>This field can be left empty. |
| 77 | 3GPP-SGSN-MCC-MNC | VARCHAR2[64] | MCC and MNC of the calling party.<br>If the CBS uses this field to analyze the roaming area, this field cannot be left empty. If the CBS does not use this field to analyze the roaming area, this field can be left empty. |
| 78 | 3GPP-MS-Time Zone | VARCHAR2[64] | Time zone where a subscriber locates.<br>This field can be left empty. |
| 79 | 3GPP-CAMEL-Charging-Info | VARCHAR2[64] | CAMEL-based charging information.<br>This field can be left empty. |
| 80 | Charging-Rule-Base-Name | VARCHAR2[64] | Charging rule name.<br>This field can be left empty. |
| 81 | 3GPP-User-Location-Info | VARCHAR2[64] | Roam-in area information.<br>If the CBS uses this field to analyze the |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | roaming area, this field cannot be left empty. If the CBS does not use this field to analyze the roaming area, this field can be left empty. |
| 82 | 3GPP-RAT-Type | VARCHAR2[64] | Parameter transferred from the wireless network.<br>This field can be left empty. |
| 83 | 3GPP-Charging-Id2 | VARCHAR2[64] | Charging ID.<br>This field can be left empty. |
| 84 | PS-Free-Format-Data | VARCHAR2[64] | Data of the PS format.<br>This field can be left empty. |
| 85 | PS-Append-Free-Format-Data | NUMBER[10] | Additional data of the PS format.<br>This field can be left empty. |
| 86 | PDP-Context-Type | NUMBER[10] | PDP context type.<br>This field can be left empty. |
| 87 | SP-Id | VARCHAR2[28] | SP ID.<br>This field can be left empty. |
| 88 | Service-Id | VARCHAR2[28] | Service ID.<br>This field can be left empty. |
| 89 | Service-Type | NUMBER[10] | Service type.<br>This field can be left empty. |
| 90 | Content-Id | VARCHAR2[28] | Content ID.<br>This field can be left empty. |
| 91 | BearerType | NUMBER[10] | Message bearer type.<br>This field can be left empty. |
| 92 | StartTime | VARCHAR2[14] | Charging start time.<br>This field can be left empty. |
| 93 | StopTime | VARCHAR2[14] | Charging end time.<br>This field can be left empty. |
| 94 | BearerProtocolType | NUMBER[10] | Message protocol.<br>This field can be left empty. |
| 95 | ChargingID | VARCHAR2[28] | ID of the charged party.<br>This field can be left empty. |
| 96 | ServiceLevel | NUMBER[10] | Service level.<br>This field can be left empty. |
| 97 | Transaction-Id | VARCHAR2[28 | Transaction ID. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | ] | This field can be left empty. |
| 98 | TotalVolume | NUMBER[20] | Total traffic used in a session, in bytes<br>This field cannot be left empty. |
| 99 | TotalDuration | NUMBER[10] | Total duration used in a session, in seconds.<br>This field cannot be left empty. |
| 100 | UnchargedVolume | NUMBER[20] | Traffic used in the period from the last time when a session is updated successfully to the end of the session. If the CBP is disconnected when the session starts, value of this field is the same as that of **TotalVolume**.<br>This field cannot be left empty. |
| 101 | UnchargedDuration | NUMBER[10] | Duration used in the period from the last time when a session is updated successfully to the end of the session, in seconds.<br>If the CBP is disconnected when the session starts, value of this field is the same as that of **TotalDuration**.<br>This field cannot be left empty. |
| 102 | LastUpdateTime | VARCHAR2[14] | Last time when a session is updated successfully.<br>This field can be left empty. |
| 103 | OFFLINEFILENAME | VARCHAR2[64] | Name of the original offline CDR file.<br>This field is used to audit original CDRs. If original CDRs do not need to be audited, this field can be left empty. |
| 104 | OFFLINEFILELineNo | NUMBER[10] | Line number of the original offline CDR.<br>This field is used to audit original CDRs. If original CDRs do not need to be audited, this field can be left empty. |
| 105 | Tariff Class | VARCHAR2[12] | This field contains the tariff class according to your originated main charging zone.<br>This field can be left empty. |

# 2.4 TAPIN_VOICE CDR

This topic describes the format of offline roam-out voice CDR files sent from a third-party system and normalized by the Mediation.

 Copyright © Huawei Technologies Co., Ltd. 

## CDR File Name Format

TAPIN_VOICE_YYYYMMDD_SEQUENCE.unl

Example: TAPIN_VOICE_20130204_0001.unl

## CDR File Format

Table 2-4 describes the fields in the TAPIN_VOICE CDR.

**Table 2-4** Fields in the TAPIN_VOICE CDR

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 1 | CDR_type | VARCHAR 2[2] | CDR type. The options are as follows:<br>• **00**: MO<br>• **01**: MT<br>• **02**: MF<br>This field cannot be left empty. |
| 2 | Fraud_Monitor_ Indicator | VARCHAR 2[2] | ID of a charged subscriber who is monitored due to the possibility of fraud.<br>This field can be left empty. |
| 3 | IDType | NUMBER[1 0] | Terminal ID type.<br>**0**: international mobile subscriber identity (IMSI)<br>This field has a fixed value of **0**.<br>This field cannot be left empty. |
| 4 | MSISDN | VARCHAR 2[30] | Number of the charged party.<br>The number formats are as follows:<br>• MSISDN<br>• International prefix + Country code + MSISDN |
| 5 | IMSI | VARCHAR 2[15] | IMSI of the charged party.<br>This field cannot be left empty. |
| 6 | IMEI | VARCHAR 2[15] | International mobile equipment identity (IMEI) or electronic serial number (ESN) of the charged party.<br>This field can be left empty. |
| 7 | Network_Type | VARCHAR 2[2] | Network type of the charged party number.<br>This field can be left empty. |
| 8 | START_TIME | VARCHAR 2[14] | Charging start time.<br>Format: YYYYMMDDHHMMSS<br>This field cannot be left empty. |
| 9 | DURATION | NUMBER[1 0] | Call duration, in seconds.<br>This field cannot be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 10 | END_TIME | VARCHAR 2[14] | Charging end time. This field is left empty.<br>An external system needs to convert the value to the subscriber's home time zone. |
| 11 | END_CAUSE | VARCHAR 2[4] | Cause for call interruption.<br>This field can be left empty. |
| 12 | Recording_Entity_Type | VARCHAR 2[2] | Entity type. The options are as follows:<br>• **1**: mobile switching center (MSC)<br>• **2**: short message service center (SMSC)<br>• **3**: gateway GPRS support node (GGSN)<br>• **4**: serving GPRS support node (SGSN)<br>• **5**: gateway mobile location center (GMLC)<br>This field can be left empty. |
| 13 | LAC | VARCHAR 2[8] | Area code of a mobile device that processes calls.<br>This field can be left empty. |
| 14 | CELL_ID | VARCHAR 2[8] | ID of a cell or base station.<br>This field can be left empty. |
| 15 | charged_Item1 | VARCHAR 2[2] | Type of the first charging item group in the charging information list. The options are as follows:<br>• **A**: call attempt<br>• **C**: content-based charging<br>• **D**: duration-based charging<br>• **E**: event-based charging<br>• **F**: one-off charging<br>• **I**: cross-network charging<br>• **N**: no charging<br>• **V**: charging by upstream traffic<br>• **W**: charging by downstream traffic<br>• **X**: charging by total traffic<br>This field cannot be left empty. |
| 16 | Called_Country_Code | VARCHAR 2[10] | Country code of the called party.<br>This field can be left empty. |
| 17 | Call_Type_Level1 | VARCHAR 2[2] | Level-1 call type. The options are as follows:<br>• **1**: national<br>• **2**: international<br>This field can be left empty. |
| 18 | Call_Type_Level2 | VARCHAR 2[2] | Level-2 call type. The options are as follows: |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **0**: unknown<br>• **1**: mobile<br>• **2**: fixed-line network<br>• **3**: irrelevant to location<br>• **4**: premium rate<br>This field can be left empty. |
| 19 | Call_Type_Level3 | VARCHAR2[2] | Level-3 call type. The items in this category are sub-items of the level-2 category.<br>Value **1** is restricted for local calls and shall not be used for any other category within the virtual private mobile network (VPMN)'s Internet of Things (IOT).<br>All other values are as defined within the VPMN's IOT.<br>This field can be left empty. |
| 20 | charge_Type11 | VARCHAR2[4] | Charge code of the first charging item in the first charging item group. The options are as follows:<br>• **00**: total fee that can be invoiced<br>• **01**: total call fee<br>• **02**: reserved<br>• **03**: toll call fee<br>• **04**: directory assistance service<br>• **05**: directory assistance after a call<br>• **06-13**: reserved<br>• **14**: voice mailbox deposits<br>• **15**: voice mailbox compensation<br>• **16-20**: reserved<br>• **21**: additional fee of the VPMN<br>• **69-99**: reserved<br>• **100**: total fee generated during the charging detail rating period<br>• **101**: total call fee generated during the charging detail rating period<br>• **102**: toll call fee generated during the charging detail rating period<br>The service usage fee for a charged party is calculated based on the values of **charGE1***X* (such as **charGE11**, **charGE12**, and **charGE13**), **charGE2***X* (such as **charGE21**, **charGE22**, and **charGE23**), and **charge_Type**. The calculation methods are as follows:<br>• If none of the values of **charge_Type1***X* and **charge_Type2***X* is **00**, the calculation |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | formula is as follows:<br>Total fee = **charGE11** + **charGE12** + **charGE13** + **charGE21** + **charGE22** + **charGE23**<br>• If one of the values of **charge_Type1***X* and **charge_Type2***X* is **00**, for example, when the value of **charge_Type12** is **00**, the calculation formula is as follows:<br>Total fee = **charGE12** + **charGE21** + **charGE22** + **charGE23**<br>• If multiple values of **charge_Type1***X* and **charge_Type2***X* are **00**, the total fee is the sum of the **charGE** values corresponding to the first **charge_Type1***X* and **charge_Type2***X* whose values are **00**. For example, when the value of **charge_Type11** is **00**, **charge_Type12** is **04**, **charge_Type13** is **00**, **charge_Type21** is **05**, **charge_Type22** is **00**, and **charge_Type23** is **00**, the calculation formula is as follows: Total fee = **charGE11** + **charGE22**.<br>This field can be left empty. |
| 21 | charGE11 | NUMBER[20] | Charged amount of the first charging item in the first charging item group.<br>This field can be left empty. |
| 22 | charge_Units11 | NUMBER[10] | Unit of the first charging item in the first charging item group.<br>This field can be left empty. |
| 23 | charge_Type12 | VARCHAR2[4] | Charge code of the second charging item in the first charging item group. The options are as follows:<br>• **00**: total fee that can be invoiced<br>• **01**: total call fee<br>• **02**: reserved<br>• **03**: toll call fee<br>• **04**: directory assistance service<br>• **05**: directory assistance after a call<br>• **06-13**: reserved<br>• **14**: voice mailbox deposits<br>• **15**: voice mailbox compensation<br>• **16-20**: reserved<br>• **21**: additional fee of the VPMN<br>• **69-99**: reserved<br>• **100**: total fee generated during the charging |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | detail rating period<br>• **101**: total call fee generated during the charging detail rating period<br>• **102**: toll call fee generated during the charging detail rating period<br>This field can be left empty. |
| 24 | charGE12 | NUMBER[20] | Charged amount of the second charging item in the first charging item group.<br>This field can be left empty. |
| 25 | charge_Units12 | NUMBER[10] | Unit of the second charging item in the first charging item group.<br>This field can be left empty. |
| 26 | charge_Type13 | VARCHAR2[4] | Charge code of the third charging item in the first charging item group. The options are as follows:<br>• **00**: total fee that can be invoiced<br>• **01**: total call fee<br>• **02**: reserved<br>• **03**: toll call fee<br>• **04**: directory assistance service<br>• **05**: directory assistance after a call<br>• **06-13**: reserved<br>• **14**: voice mailbox deposits<br>• **15**: voice mailbox compensation<br>• **16-20**: reserved<br>• **21**: additional fee of the VPMN<br>• **69-99**: reserved<br>• **100**: total fee generated during the charging detail rating period<br>• **101**: total call fee generated during the charging detail rating period<br>• **102**: toll call fee generated during the charging detail rating period<br>This field can be left empty. |
| 27 | charGE13 | NUMBER[20] | Charged amount of the third charging item in the first charging item group.<br>This field can be left empty. |
| 28 | charge_Units13 | NUMBER[10] | Unit of the third charging item in the first charging item group.<br>This field can be left empty. |
| 29 | charged_Item2 | VARCHAR | Type of the second charging item group in the |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | 2[2] | charging information list. The options are as follows:<br>• **A**: call attempt<br>• **C**: content-based charging<br>• **D**: duration-based charging<br>• **E**: event-based charging<br>• **F**: one-off charging<br>• **I**: cross-network charging<br>• **N**: no charging<br>• **V**: charging by upstream traffic<br>• **W**: charging by downstream traffic<br>• **X**: charging by total traffic<br>This field can be left empty. |
| 30 | charge_Type21 | VARCHAR 2[4] | Charge code of the first charging item in the second charging item group. The options are as follows:<br>• **00**: total fee that can be invoiced<br>• **01**: total call fee<br>• **02**: reserved<br>• **03**: toll call fee<br>• **04**: directory assistance service<br>• **05**: directory assistance after a call<br>• **06-13**: reserved<br>• **14**: voice mailbox deposits<br>• **15**: voice mailbox compensation<br>• **16-20**: reserved<br>• **21**: additional fee of the VPMN<br>• **69-99**: reserved<br>• **100**: total fee generated during the charging detail rating period<br>• **101**: total call fee generated during the charging detail rating period<br>• **102**: toll call fee generated during the charging detail rating period<br>This field can be left empty. |
| 31 | charGE21 | NUMBER[20] | Charged amount of the first charging item in the second charging item group.<br>This field can be left empty. |
| 32 | charged_Units21 | NUMBER[10] | Unit of the first charging item in the second charging item group.<br>This field can be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 33 | charge_Type22 | VARCHAR2[4] | Charge code of the second charging item in the second charging item group. The options are as follows:<br>• **00**: total fee that can be invoiced<br>• **01**: total call fee<br>• **02**: reserved<br>• **03**: toll call fee<br>• **04**: directory assistance service<br>• **05**: directory assistance after a call<br>• **06-13**: reserved<br>• **14**: voice mailbox deposits<br>• **15**: voice mailbox compensation<br>• **16-20**: reserved<br>• **21**: additional fee of the VPMN<br>• **69-99**: reserved<br>• **100**: total fee generated during the charging detail rating period<br>• **101**: total call fee generated during the charging detail rating period<br>• **102**: toll call fee generated during the charging detail rating period<br>This field can be left empty. |
| 34 | charGE22 | NUMBER[20] | Charged amount of the second charging item in the second charging item group.<br>This field can be left empty. |
| 35 | charged_Units22 | NUMBER[10] | Unit of the second charging item in the second charging item group.<br>This field can be left empty. |
| 36 | charge_Type23 | VARCHAR2[4] | Charge code of the third charging item in the second charging item group. The options are as follows:<br>• **00**: total fee that can be invoiced<br>• **01**: total call fee<br>• **02**: reserved<br>• **03**: toll call fee<br>• **04**: directory assistance service<br>• **05**: directory assistance after a call<br>• **06-13**: reserved<br>• **14**: voice mailbox deposits<br>• **15**: voice mailbox compensation<br>• **16-20**: reserved |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **21**: additional fee of the VPMN<br>• **69-99**: reserved<br>• **100**: total fee generated during the charging detail rating period<br>• **101**: total call fee generated during the charging detail rating period<br>• **102**: toll call fee generated during the charging detail rating period<br>This field can be left empty. |
| 37 | charGE23 | NUMBER[20] | Charged amount of the third charging item in the second charging item group.<br>This field can be left empty. |
| 38 | charged_Units23 | NUMBER[10] | Unit of the third charging item in the second charging item group.<br>This field can be left empty. |
| 39 | Day_Category | VARCHAR2[4] | Preferential day type. The options are as follows:<br>• **N**: workday<br>• **I**: national independence day<br>• **P**: public holiday<br>• **R**: weekend<br>This field can be left empty. |
| 40 | Category_Subtype | VARCHAR2[4] | Subtype associated with **Day Category**.<br>This field is defined by the carrier corresponding to the visited area of a roaming subscriber.<br>This field can be left empty. |
| 41 | Time_Band | VARCHAR2[4] | Charging time segment associated with **Charge Detail** and **Charge Detail Timestamp**. This field is defined by the carrier corresponding to the visited area of a roaming subscriber. If **Charge Detail Timestamp** is not provided, this field indicates the time segment corresponding to **Charging Timestamp** associated with **Charging Information**.<br>The carrier corresponding to the visited area can set **Time_Band_Subtype** to further specify the charging time segment.<br>This field can be left empty. |
| 42 | Time_Band_Subtype | VARCHAR2[4] | Charging time segment subtype.<br>This field is defined by the carrier corresponding to the visited area of a roaming subscriber.<br>This field can be left empty. |
| 43 | Multiate_Indica | VARCHAR | Indicates whether the type of the preferential day |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | tor | 2[2] | or preferential time segment changes during charging.<br>A flag indicating that a Charge Detail began during the related Day Category and Time Band and spanned a change of either of those items.<br>This field can be left empty. |
| 44 | Tax_Type | VARCHAR 2[4] | Tax type.<br>Tax type associated with Tax Rate Code and Tax Rate. The options are as follows:<br>• **01**: national tax<br>• **02**: regional tax<br>• **03**: county tax<br>• **04**: local or city tax<br>• **05**: provincial tax.<br>• **06**: dominion tax<br>• **07**: gross receipts tax<br>• **08**: absolute or fixed tax (no tax rate specified)<br>• **09**: public utility tax<br>• **10**: sales and use tax<br>• **11**: excise tax<br>• **12**: communications tax<br>• **13**: value added tax (VAT)<br>• **14**: harmonized sales tax<br>This field can be left empty. |
| 45 | Tax_Rate | NUMBER[10] | Tax rate for a specific tax type and code.<br>According to some national laws and regulations, taxes must be collected based on the tax rate corresponding to the invoice date. If invoice generation is postponed, the tax rate in the invoice may be different from the tax rate that is transferred. However, the occurrence rate of this situation is extremely low.<br>This field is mandatory unless the fixed tax rate is used.<br>The value is precise to five decimal places and ranges from 00.00000 to 99.99999.<br>This field can be left empty. |
| 46 | Tax_Value | NUMBER[20] | Actual tax amount. The value must be equal to or greater than 0 and the number of decimal places is specified by **TAP Decimal Places**. The value is in SDRs.<br>This field can be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 47 | Discount_Type | NUMBER[10] | Discount type. The options are as follows:<br>• **0**: discount rate<br>• **1**: fixed discount value<br>This field can be left empty. |
| 48 | Discount_Rate | NUMBER[10] | Discount rate.<br>This field can be left empty. |
| 49 | Discount_Value | NUMBER[20] | Discount amount.<br>This field can be left empty. |
| 50 | CAMEL_Service_Address | VARCHAR2[8] | IP address of the Customized Applications for Mobile Network Enhanced Logic (CAMEL) server.<br>This field can be left empty. |
| 51 | CAMEL_Service_Level | VARCHAR2[4] | CAMEL service level.<br>This field can be left empty. |
| 52 | CAMEL_Service_Key | VARCHAR2[4] | CAMEL service key value.<br>This field can be left empty. |
| 53 | Default_Call_Handling_Indicator | VARCHAR2[2] | Default call processing ID of the CAMEL.<br>This field can be left empty. |
| 54 | CAMEL_MSC_Address | VARCHAR2[15] | MSC address of the CAMEL.<br>This field can be left empty. |
| 55 | CAMEL_Reference_Num | NUMBER[20] | CAMEL activation flag.<br>This field can be left empty. |
| 56 | CAMEL_Initiated_Indicator | VARCHAR2[2] | Indicates whether the call is a forwarded call initiated by the CAMEL server.<br>This field can be left empty. |
| 57 | CAMEL_Modification | VARCHAR2[2] | Indicates whether a call is initiated when the CAMEL protocol is used.<br>This field can be left empty. |
| 58 | CSE_Info | VARCHAR2[40] | Information downloaded from the CAMEL server.<br>This field can be left empty. |
| 59 | Caller_number | VARCHAR2[30] | Calling number, in the format *Country code* + *MSISDN*.<br>The value consists of digits, asterisks (*), and number signs (#).<br>This field cannot be left empty. |
| 60 | Dialed_Digits | VARCHAR | Dialed number. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | 2[30] | This field cannot be left empty. |
| 61 | Called_number | VARCHAR 2[30] | Called number, in the format *Country code + MSISDN*.<br>The value consists of digits, asterisks (*), and number signs (#).<br>This field cannot be left empty. |
| 62 | third_number | VARCHAR 2[30] | Third-party number, which is valid only in the MF process.<br>This field can be left empty. |
| 63 | Called_Place | VARCHAR 2[10] | Home city of the called party, which is valid only in the CDRs generated in the MO process.<br>This field can be left empty. |
| 64 | Called_Region | VARCHAR 2[10] | Home area of the called party, which is valid only in the CDRs generated in the MO process.<br>This field can be left empty. |
| 65 | MSC | VARCHAR 2[15] | MSC ID.<br>This field can be left empty. |
| 66 | Service_Type | VARCHAR 2[4] | Service type.<br>This field can be left empty. |
| 67 | SERVICE_CODE | VARCHAR 2[4] | Service code.<br>This field can be left empty. |
| 68 | Radio_Channel_Req | NUMBER[10] | Radio channel type requested by the terminal during call connection.<br>This field can be left empty. |
| 69 | Radio_Channel_Used | NUMBER[10] | Allocated radio channel type during call connection.<br>This field can be left empty. |
| 70 | Speech_Version_Req | NUMBER[10] | Preferred voice version that the terminal requests the mobile station to deliver when a call is established.<br>This field can be left empty. |
| 71 | Speech_Version_Used | NUMBER[10] | Voice version delivered by the mobile station during call connection.<br>This field can be left empty. |
| 72 | Transparency_Indicator | VARCHAR 2[2] | Indicates whether used services are transparent.<br>This field can be left empty. |
| 73 | Fixed_Network_User_Rate | VARCHAR 2[2] | Rate on the fixed-line network. The options are as follows:<br>• **1**: 9.6 kbit/s |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **2**: 14.4 kbit/s<br>• **3**: 19.2 kbit/s<br>• **4**: 28.8 kbit/s<br>• **5**: 38.4 kbit/s<br>• **6**: 48 kbit/s<br>• **7**: 56 kbit/s<br>• **8**: 64 kbit/s<br>This field can be left empty. |
| 74 | Air_Interface_User_Rate_Req | VARCHAR 2[2] | Rate at which subscribers request air interfaces.<br>This field can be left empty. |
| 75 | User_Protocol_Indicator | VARCHAR 2[2] | High-end subscriber protocol between the mobile station and network.<br>This field can be left empty. |
| 76 | reserve | VARCHAR 2[1] | This field is reserved.<br>This field can be left empty. |
| 77 | reserve | VARCHAR 2[2] | This field is reserved.<br>This field can be left empty. |
| 78 | reserve | VARCHAR 2[2] | This field is reserved.<br>This field can be left empty. |
| 79 | reserve | VARCHAR 2[2] | This field is reserved.<br>This field can be left empty. |
| 80 | reserve | VARCHAR 2[1] | This field is reserved.<br>This field can be left empty. |
| 81 | reserve | VARCHAR 2[5] | This field is reserved.<br>This field can be left empty. |
| 82 | reserve | VARCHAR 2[10] | This field is reserved.<br>This field can be left empty. |
| 83 | reserve | VARCHAR 2[1] | This field is reserved.<br>This field can be left empty. |
| 84 | reserve | VARCHAR 2[1] | This field is reserved.<br>This field can be left empty. |
| 85 | reserve | VARCHAR 2[24] | This field is reserved.<br>This field can be left empty. |
| 86 | TAPFILENAME | VARCHAR 2[64] | CDR file name, containing the international roaming PMN code that indicates the country code and carrier information. The CDR file name is in the format CD*XXXXXYYYYYSequence* |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | *number*.suffix.<br>• **CD**: CDR file name prefix. The first two digits have a fixed value of **CD**.<br>• *XXXXX*: PMN code of the carrier corresponding to the visited area of a roaming-out subscriber<br>• *YYYYY*: PMN code of the carrier corresponding to the home area of a roaming-out subscriber<br>This field cannot be left empty. |
| 87 | reserve | VARCHAR2[10] | This field is reserved.<br>This field can be left empty. |
| 88 | reserve | VARCHAR2[5] | This field is reserved.<br>This field can be left empty. |
| 89 | ExchangeRate | NUMBER[10] | Exchange rate between the local currency and standard currency.<br>This field can be left empty. |
| 90 | chargeable_unit1 | NUMBER[10] | Rounding unit for the first type of service usage generated during charging.<br>This field can be left empty. |
| 91 | chargeable_unit2 | NUMBER[10] | Rounding unit for the second type of service usage generated during charging.<br>This field can be left empty. |
| 92 | chargeable_unit3 | NUMBER[10] | Rounding unit for the third type of service usage generated during charging.<br>This field can be left empty. |
| 93 | reserve | VARCHAR2[1] | This field is reserved.<br>This field can be left empty. |
| 94 | reserve | VARCHAR2[60] | This field is reserved.<br>This field can be left empty. |
| 95 | CALL_START_TIME_TIMEZONE | NUMBER[10] | Time zone of the visited area. The information is transparently transferred and recorded in CDRs, but it does not affect rating.<br>This field can be left empty. |
| 96 | TAPFILELineNo | NUMBER[10] | Line number of a CDR in a TAPIN CDR file. The file header and tail are not counted as lines.<br>This field cannot be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

# 2.5 TAPIN_SMS CDR

This topic describes the format of offline roam-out SMS CDR files sent from a third-party system and normalized by the Mediation.

## CDR File Name Format

TAPIN_SMS_YYYYMMDD_SEQUENCE.unl

Example: TAPIN_SMS_20130204_0001.unl

## CDR File Format

Table 2-5 describes the fields in the TAPIN_SMS CDR.

**Table 2-5** Fields in the TAPIN_SMS CDR

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 1 | CDR_type | VARCHAR 2[2] | CDR type. The options are as follows:<br>• **10**: SMS message sender<br>• **11**: SMS message recipient<br>This field cannot be left empty. |
| 2 | Fraud_Monitor_ Indicator | VARCHAR 2[2] | ID of a charged subscriber who is monitored due to the possibility of fraud.<br>This field can be left empty. |
| 3 | IDType | NUMBER[1 0] | Terminal ID type.<br>**0**: international mobile subscriber identity (IMSI)<br>This field has a fixed value of **0**.<br>This field cannot be left empty. |
| 4 | MSISDN | VARCHAR 2[30] | Number of the charged party.<br>The number formats are as follows:<br>• MSISDN<br>• International prefix + Country code + MSISDN<br>This field can be left empty. |
| 5 | IMSI | VARCHAR 2[15] | IMSI of the charged party.<br>This field cannot be left empty. |
| 6 | IMEI | VARCHAR 2[15] | International mobile equipment identity (IMEI) or electronic serial number (ESN) of the charged party.<br>This field can be left empty. |
| 7 | Network_Type | VARCHAR 2[2] | Network type.<br>This field can be left empty. |
| 8 | START_TIME | VARCHAR | Charging start time. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | 2[14] | An external system needs to convert the value to the subscriber's home time zone.<br>This field cannot be left empty. |
| 9 | DURATION | NUMBER[10] | Duration for sending an SMS message, in seconds.<br>This field cannot be left empty. |
| 10 | END_TIME | VARCHAR2[14] | Charging end time. This field is left empty.<br>An external system converts the value to the CBS system time zone. |
| 11 | END_CAUSE | VARCHAR2[4] | Cause for SMS message sending interruption.<br>This field can be left empty. |
| 12 | Recording_Entity_Type | VARCHAR2[2] | Entity type. The options are as follows:<br>• **1**: mobile switching center (MSC)<br>• **2**: short message service center (SMSC)<br>• **3**: gateway GPRS support node (GGSN)<br>• **4**: serving GPRS support node (SGSN)<br>• **5**: gateway mobile location center (GMLC)<br>This field can be left empty. |
| 13 | LAC | VARCHAR2[8] | Area code of a mobile device that processes SMS messages.<br>This field can be left empty. |
| 14 | CELL_ID | VARCHAR2[8] | ID of a cell or base station.<br>This field can be left empty. |
| 15 | charged_Item1 | VARCHAR2[2] | Type of the first charging item group in the charging information list. The options are as follows:<br>• **A**: call attempt<br>• **C**: content-based charging<br>• **D**: duration-based charging<br>• **E**: event-based charging<br>• **F**: one-off charging<br>• **I**: cross-network charging<br>• **N**: no charging<br>• **V**: charging by upstream traffic<br>• **W**: charging by downstream traffic<br>• **X**: charging by total traffic<br>This field cannot be left empty. |
| 16 | Called_Country_Code | VARCHAR2[10] | Country code of the recipient.<br>This field can be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 17 | Call_Type_Level1 | VARCHAR2[2] | SMS message level 1. The options are as follows:<br>• **1**: national<br>• **2**: international<br>This field can be left empty. |
| 18 | Call_Type_Level2 | VARCHAR2[2] | SMS message level 2. The options are as follows:<br>• **0**: unknown<br>• **1**: mobile<br>• **2**: fixed-line network<br>• **3**: irrelevant to location<br>• **4**: premium rate<br>This field can be left empty. |
| 19 | Call_Type_Level3 | VARCHAR2[2] | SMS message level 3. The items in this category are sub-items of the level-2 category.<br>Value **1** is restricted for local calls and shall not be used for any other category within the VPMN's IOT.<br>All other values are as defined within the VPMN's IOT.<br>This field can be left empty. |
| 20 | charge_Type11 | VARCHAR2[4] | Charge code of the first charging item in the first charging item group. The options are as follows:<br>• **00**: total fee that can be invoiced<br>• **01**: total call fee<br>• **02**: reserved<br>• **03**: toll call fee<br>• **04**: directory assistance service<br>• **05**: directory assistance after a call<br>• **06-13**: reserved<br>• **14**: voice mailbox deposits<br>• **15**: voice mailbox compensation<br>• **16-20**: reserved<br>• **21**: additional fee of the VPMN<br>• **69-99**: reserved<br>• **100**: total fee generated during the charging detail rating period<br>• **101**: total call fee generated during the charging detail rating period<br>• **102**: toll call fee generated during the charging detail rating period |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | The service usage fee for a charged party is calculated based on the values of **charGE1***X* (such as **charGE11**, **charGE12**, and **charGE13**), **charGE2***X* (such as **charGE21**, **charGE22**, and **charGE23**), and **charge_Type**. The calculation methods are as follows:<br>• If none of the values of **charge_Type1***X* and **charge_Type2***X* is **00**, the calculation formula is as follows:<br>Total fee = **charGE11** + **charGE12** + **charGE13** + **charGE21** + **charGE22** + **charGE23**<br>• If one of the values of **charge_Type1***X* and **charge_Type2***X* is **00**, for example, when the value of **charge_Type12** is **00**, the calculation formula is as follows:<br>Total fee = **charGE12** + **charGE21** + **charGE22** + **charGE23**<br>• If multiple values of **charge_Type1***X* and **charge_Type2***X* are **00**, the total fee is the sum of the **charGE** values corresponding to the first **charge_Type1***X* and **charge_Type2***X* whose values are **00**. For example, when the value of **charge_Type11** is **00**, **charge_Type12** is **04**, **charge_Type13** is **00**, **charge_Type21** is **05**, **charge_Type22** is **00**, and **charge_Type23** is **00**, the calculation formula is as follows: Total fee = **charGE11** + **charGE22**.<br>This field can be left empty. |
| 21 | charGE11 | NUMBER[20] | Charged amount of the first charging item in the first charging item group.<br>This field can be left empty. |
| 22 | charge_Units11 | NUMBER[10] | Unit of the first charging item in the first charging item group.<br>This field can be left empty. |
| 23 | charge_Type12 | VARCHAR2[4] | Charge code of the second charging item in the first charging item group. The options are as follows:<br>• **00**: total fee that can be invoiced<br>• **01**: total call fee<br>• **02**: reserved<br>• **03**: toll call fee<br>• **04**: directory assistance service<br>• **05**: directory assistance after a call<br>• **06-13**: reserved |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **14**: voice mailbox deposits<br>• **15**: voice mailbox compensation<br>• **16-20**: reserved<br>• **21**: additional fee of the VPMN<br>• **69-99**: reserved<br>• **100**: total fee generated during the charging detail rating period<br>• **101**: total call fee generated during the charging detail rating period<br>• **102**: toll call fee generated during the charging detail rating period<br>This field can be left empty. |
| 24 | charGE12 | NUMBER[20] | Charged amount of the second charging item in the first charging item group.<br>This field can be left empty. |
| 25 | charge_Units12 | NUMBER[10] | Unit of the second charging item in the first charging item group.<br>This field can be left empty. |
| 26 | charge_Type13 | VARCHAR2[4] | Charge code of the third charging item in the first charging item group. The options are as follows:<br>• **00**: total fee that can be invoiced<br>• **01**: total call fee<br>• **02**: reserved<br>• **03**: toll call fee<br>• **04**: directory assistance service<br>• **05**: directory assistance after a call<br>• **06-13**: reserved<br>• **14**: voice mailbox deposits<br>• **15**: voice mailbox compensation<br>• **16-20**: reserved<br>• **21**: additional fee of the VPMN<br>• **69-99**: reserved<br>• **100**: total fee generated during the charging detail rating period<br>• **101**: total call fee generated during the charging detail rating period<br>• **102**: toll call fee generated during the charging detail rating period<br>This field can be left empty. |
| 27 | charGE13 | NUMBER[2 | Charged amount of the third charging item in the |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | 0] | first charging item group.<br>This field can be left empty. |
| 28 | charge_Units13 | NUMBER[10] | Unit of the third charging item in the first charging item group.<br>This field can be left empty. |
| 29 | charged_Item2 | VARCHAR2[2] | Type of the second charging item group in the charging information list. The options are as follows:<br>• **A**: call attempt<br>• **C**: content-based charging<br>• **D**: duration-based charging<br>• **E**: event-based charging<br>• **F**: one-off charging<br>• **I**: cross-network charging<br>• **N**: no charging<br>• **V**: charging by upstream traffic<br>• **W**: charging by downstream traffic<br>• **X**: charging by total traffic<br>This field can be left empty. |
| 30 | charge_Type21 | VARCHAR2[4] | Charge code of the first charging item in the second charging item group. The options are as follows:<br>• **00**: total fee that can be invoiced<br>• **01**: total call fee<br>• **02**: reserved<br>• **03**: toll call fee<br>• **04**: directory assistance service<br>• **05**: directory assistance after a call<br>• **06-13**: reserved<br>• **14**: voice mailbox deposits<br>• **15**: voice mailbox compensation<br>• **16-20**: reserved<br>• **21**: additional fee of the VPMN<br>• **69-99**: reserved<br>• **100**: total fee generated during the charging detail rating period<br>• **101**: total call fee generated during the charging detail rating period<br>• **102**: toll call fee generated during the charging detail rating period<br>This field can be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 31 | charGE21 | NUMBER[20] | Charged amount of the first charging item in the second charging item group.<br>This field can be left empty. |
| 32 | charged_Units21 | NUMBER[10] | Unit of the first charging item in the second charging item group.<br>This field can be left empty. |
| 33 | charge_Type22 | VARCHAR2[4] | Charge code of the second charging item in the second charging item group. The options are as follows:<br>• **00**: total fee that can be invoiced<br>• **01**: total call fee<br>• **02**: reserved<br>• **03**: toll call fee<br>• **04**: directory assistance service<br>• **05**: directory assistance after a call<br>• **06-13**: reserved<br>• **14**: voice mailbox deposits<br>• **15**: voice mailbox compensation<br>• **16-20**: reserved<br>• **21**: additional fee of the VPMN<br>• **69-99**: reserved<br>• **100**: total fee generated during the charging detail rating period<br>• **101**: total call fee generated during the charging detail rating period<br>• **102**: toll call fee generated during the charging detail rating period<br>This field can be left empty. |
| 34 | charGE22 | NUMBER[20] | Charged amount of the second charging item in the second charging item group.<br>This field can be left empty. |
| 35 | charged_Units22 | NUMBER[10] | Unit of the second charging item in the second charging item group.<br>This field can be left empty. |
| 36 | charge_Type23 | VARCHAR2[4] | Charge code of the third charging item in the second charging item group. The options are as follows:<br>• **00**: total fee that can be invoiced<br>• **01**: total call fee<br>• **02**: reserved<br>• **03**: toll call fee |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **04**: directory assistance service<br>• **05**: directory assistance after a call<br>• **06-13**: reserved<br>• **14**: voice mailbox deposits<br>• **15**: voice mailbox compensation<br>• **16-20**: reserved<br>• **21**: additional fee of the VPMN<br>• **69-99**: reserved<br>• **100**: total fee generated during the charging detail rating period<br>• **101**: total call fee generated during the charging detail rating period<br>• **102**: toll call fee generated during the charging detail rating period<br>This field can be left empty. |
| 37 | charGE23 | NUMBER[20] | Charged amount of the third charging item in the second charging item group.<br>This field can be left empty. |
| 38 | charged_Units23 | NUMBER[10] | Unit of the third charging item in the second charging item group.<br>This field can be left empty. |
| 39 | Day_Category | VARCHAR2[4] | Preferential day type. The options are as follows:<br>• **N**: workday<br>• **I**: national independence day<br>• **P**: public holiday<br>• **R**: weekend<br>This field can be left empty. |
| 40 | Category_Subtype | VARCHAR2[4] | Subtype associated with **Day Category**.<br>This field is defined by the carrier corresponding to the visited area of a roaming subscriber.<br>This field can be left empty. |
| 41 | Time_Band | VARCHAR2[4] | Charging time segment associated with **Charge Detail** and **Charge Detail Timestamp**. This field is defined by the carrier corresponding to the visited area of a roaming subscriber. If **Charge Detail Timestamp** is not provided, this field indicates the time segment corresponding to **Charging Timestamp** associated with **Charging Information**.<br>The carrier corresponding to the visited area can set **Time_Band_Subtype** to further specify the charging time segment. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | This field can be left empty. |
| 42 | Time_Band_Subtype | VARCHAR2[4] | Charging time segment subtype.<br>This field is defined by the carrier corresponding to the visited area of a roaming subscriber.<br>This field can be left empty. |
| 43 | Multiate_Indicator | VARCHAR2[2] | Indicates whether the type of the preferential day or preferential time segment changes during charging.<br>A flag indicating that a Charge Detail began during the related Day Category and Time Band and spanned a change of either of those items.<br>This field can be left empty. |
| 44 | Tax_Type | VARCHAR2[4] | Tax type.<br>Tax type associated with Tax Rate Code and Tax Rate. The options are as follows:<br>• **01**: national tax<br>• **02**: regional tax<br>• **03**: county tax<br>• **04**: local or city tax<br>• **05**: provincial tax.<br>• **06**: dominion tax<br>• **07**: gross receipts tax<br>• **08**: absolute or fixed tax (no tax rate specified)<br>• **09**: public utility tax<br>• **10**: sales and use tax<br>• **11**: excise tax<br>• **12**: communications tax<br>• **13**: value added tax (VAT)<br>• **14**: harmonized sales tax<br>This field can be left empty. |
| 45 | Tax_Rate | NUMBER[10] | Tax rate for a specific tax type and code.<br>According to some national laws and regulations, taxes must be collected based on the tax rate corresponding to the invoice date. If invoice generation is postponed, the tax rate in the invoice may be different from the tax rate that is transferred. However, the occurrence rate of this situation is extremely low.<br>This field is mandatory unless the fixed tax rate is used.<br>The value is precise to five decimal places and |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | ranges from 00.00000 to 99.99999.<br>This field can be left empty. |
| 46 | Tax_Value | NUMBER[20] | Actual tax amount. The value must be equal to or greater than 0 and the number of decimal places is specified by **TAP Decimal Places**. The value is in SDRs.<br>This field can be left empty. |
| 47 | Discount_Type | NUMBER[10] | Discount type. The options are as follows:<br>• **0**: discount rate<br>• **1**: fixed discount value<br>This field can be left empty. |
| 48 | Discount_Rate | NUMBER[10] | Discount rate.<br>This field can be left empty. |
| 49 | Discount_Value | NUMBER[20] | Discount amount.<br>This field can be left empty. |
| 50 | CAMEL_Service_Address | VARCHAR2[8] | IP address of the Customized Applications for Mobile Network Enhanced Logic (CAMEL) server.<br>This field can be left empty. |
| 51 | CAMEL_Service_Level | VARCHAR2[4] | CAMEL service level.<br>This field can be left empty. |
| 52 | CAMEL_Service_Key | VARCHAR2[4] | CAMEL service key value.<br>This field can be left empty. |
| 53 | Default_Call_Handling_Indicator | VARCHAR2[2] | Default call processing ID of the CAMEL.<br>This field can be left empty. |
| 54 | CAMEL_MSC_Address | VARCHAR2[15] | MSC address of the CAMEL.<br>This field can be left empty. |
| 55 | CAMEL_Reference_Num | NUMBER[20] | CAMEL activation flag.<br>This field can be left empty. |
| 56 | CAMEL_Initiated_Indicator | VARCHAR2[2] | Indicates whether the call is a forwarded call initiated by the CAMEL server.<br>This field can be left empty. |
| 57 | CAMEL_Modification | VARCHAR2[2] | Indicates whether a call is initiated when the CAMEL protocol is used.<br>This field can be left empty. |
| 58 | CSE_Info | VARCHAR2[40] | Information downloaded from the CAMEL server.<br>This field can be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 59 | Caller_number | VARCHAR2[30] | Calling number, in the format *Country code* + *MSISDN*.<br>The value consists of digits, asterisks (*), and number signs (#).<br>This field cannot be left empty. |
| 60 | Dialed_Digits | VARCHAR2[30] | Dialed number.<br>This field cannot be left empty. |
| 61 | Called_number | VARCHAR2[30] | Called number, in the format *Country code* + *MSISDN*.<br>The value consists of digits, asterisks (*), and number signs (#).<br>This field cannot be left empty. |
| 62 | third_number | VARCHAR2[30] | Third-party number, which is valid only in the MF process.<br>This field can be left empty. |
| 63 | Called_Place | VARCHAR2[10] | Home city of the called party, which is valid only in the CDRs generated in the MO process.<br>This field can be left empty. |
| 64 | Called_Region | VARCHAR2[10] | Home area of the called party, which is valid only in the CDRs generated in the MO process.<br>This field can be left empty. |
| 65 | MSC | VARCHAR2[15] | MSC ID.<br>This field can be left empty. |
| 66 | Service_Type | VARCHAR2[4] | Service type.<br>This field can be left empty. |
| 67 | SERVICE_CODE | VARCHAR2[4] | Service code.<br>This field can be left empty. |
| 68 | Radio_Channel_Req | NUMBER[10] | Radio channel type requested by the terminal during call connection.<br>This field can be left empty. |
| 69 | Radio_Channel_Used | NUMBER[10] | Allocated radio channel type during call connection.<br>This field can be left empty. |
| 70 | Speech_Version_Req | NUMBER[10] | Preferred voice version that the terminal requests the mobile station to deliver when a call is established.<br>This field can be left empty. |
| 71 | Speech_Version_Used | NUMBER[10] | Voice version delivered by the mobile station during call connection. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | This field can be left empty. |
| 72 | Transparency_Indicator | VARCHAR2[2] | Indicates whether used services are transparent.<br>This field can be left empty. |
| 73 | Fixed_Network_User_Rate | VARCHAR2[2] | Rate on the fixed-line network. The options are as follows:<br>• **1**: 9.6 kbit/s<br>• **2**: 14.4 kbit/s<br>• **3**: 19.2 kbit/s<br>• **4**: 28.8 kbit/s<br>• **5**: 38.4 kbit/s<br>• **6**: 48 kbit/s<br>• **7**: 56 kbit/s<br>• **8**: 64 kbit/s<br>This field can be left empty. |
| 74 | Air_Interface_User_Rate_Req | VARCHAR2[2] | Rate at which subscribers request air interfaces.<br>This field can be left empty. |
| 75 | User_Protocol_Indicator | VARCHAR2[2] | High-end subscriber protocol between the mobile station and network.<br>This field can be left empty. |
| 76 | reserve | VARCHAR2[1] | This field is reserved.<br>This field can be left empty. |
| 77 | reserve | VARCHAR2[2] | This field is reserved.<br>This field can be left empty. |
| 78 | reserve | VARCHAR2[2] | This field is reserved.<br>This field can be left empty. |
| 79 | reserve | VARCHAR2[2] | This field is reserved.<br>This field can be left empty. |
| 80 | reserve | VARCHAR2[1] | This field is reserved.<br>This field can be left empty. |
| 81 | reserve | VARCHAR2[5] | This field is reserved.<br>This field can be left empty. |
| 82 | reserve | VARCHAR2[10] | This field is reserved.<br>This field can be left empty. |
| 83 | reserve | VARCHAR2[1] | This field is reserved.<br>This field can be left empty. |
| 84 | reserve | VARCHAR2[1] | This field is reserved.<br>This field can be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 85 | reserve | VARCHAR2[24] | This field is reserved.<br>This field can be left empty. |
| 86 | TAPFILENAME | VARCHAR2[64] | CDR file name, containing the international roaming PMN code that indicates the country code and carrier information. The CDR file name is in the format CD*XXXXXYYYYYSequence number*.suffix.<br>• **CD**: CDR file name prefix. The first two digits have a fixed value of **CD**.<br>• *XXXXX*: PMN code of the carrier corresponding to the visited area of a roaming-out subscriber<br>• *YYYYY*: PMN code of the carrier corresponding to the home area of a roaming-out subscriber<br>This field cannot be left empty. |
| 87 | reserve | VARCHAR2[10] | This field is reserved.<br>This field can be left empty. |
| 88 | reserve | VARCHAR2[5] | This field is reserved.<br>This field can be left empty. |
| 89 | ExchangeRate | NUMBER[10] | Exchange rate between the local currency and standard currency.<br>This field can be left empty. |
| 90 | chargeable_unit1 | NUMBER[10] | Rounding unit for the first type of service usage generated during charging.<br>This field can be left empty. |
| 91 | chargeable_unit2 | NUMBER[10] | Rounding unit for the second type of service usage generated during charging.<br>This field can be left empty. |
| 92 | chargeable_unit3 | NUMBER[10] | Rounding unit for the third type of service usage generated during charging.<br>This field can be left empty. |
| 93 | reserve | VARCHAR2[1] | This field is reserved.<br>This field can be left empty. |
| 94 | reserve | VARCHAR2[60] | This field is reserved.<br>This field can be left empty. |
| 95 | CALL_START_TIME_TIMEZONE | NUMBER[10] | Time zone of the visited area. The information is transparently transferred and recorded in CDRs, but it does not affect rating.<br>This field can be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 96 | TAPFILELineNo | NUMBER[10] | Line number of a CDR in a TAPIN CDR file. The file header and tail are not counted as lines.<br>This field cannot be left empty. |

# 2.6 TAPIN_GPRS CDR

This topic describes the format of offline roam-out data CDR files sent from a third-party system and normalized by the Mediation.

## CDR File Name Format

TAPIN_GPRS_YYYYMMDD_SEQUENCE.unl

Example: TAPIN_GPRS_20130204_0001.unl

## CDR File Format

Table 2-6 describes the fields in the TAPIN_GPRS CDR.

**Table 2-6** Fields in the TAPIN_GPRS CDR

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 1 | CDR_type | VARCHAR2[2] | CDR type.<br>**15**: GPRS<br>This field cannot be left empty. |
| 2 | Fraud_Monitor_Indicator | VARCHAR2[2] | ID of a charged subscriber who is monitored due to the possibility of fraud.<br>This field can be left empty. |
| 3 | IDType | NUMBER[10] | Terminal ID type.<br>**0**: international mobile subscriber identity (IMSI)<br>This field has a fixed value of **0**.<br>This field can be left empty. |
| 4 | MSISDN | VARCHAR2[30] | Number of the charged party.<br>The number formats are as follows:<br>• MSISDN<br>• International prefix + Country code + MSISDN<br>This field can be left empty. |
| 5 | IMSI | VARCHAR2[15] | IMSI of the charged party.<br>This field cannot be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 6 | IMEI | VARCHAR2[15] | International mobile equipment identity (IMEI) or electronic serial number (ESN) of the charged party.<br>This field can be left empty. |
| 7 | Network_Type | VARCHAR2[2] | Network type.<br>This field can be left empty. |
| 8 | START_TIME | VARCHAR2[14] | Data service start time.<br>An external system converts the value to the CBS system time zone.<br>This field cannot be left empty. |
| 9 | DURATION | NUMBER[10] | Data service duration, in seconds.<br>This field can be left empty. |
| 10 | END_TIME | VARCHAR2[14] | Data service end time. This field is left empty.<br>An external system converts the value to the home BE time zone in the CBS.<br>This field can be left empty. |
| 11 | END_CAUSE | VARCHAR2[4] | Cause for service termination.<br>This field can be left empty. |
| 12 | Recording_Entity_Type | VARCHAR2[2] | Entity type. The options are as follows:<br>• **1**: mobile switching center (MSC)<br>• **2**: short message service center (SMSC)<br>• **3**: gateway GPRS support node (GGSN)<br>• **4**: serving GPRS support node (SGSN)<br>• **5**: gateway mobile location center (GMLC)<br>This field can be left empty. |
| 13 | LAC | VARCHAR2[8] | Area code of a mobile device that processes the data service.<br>This field can be left empty. |
| 14 | CELL_ID | VARCHAR2[8] | ID of a cell or base station.<br>This field can be left empty. |
| 15 | charged_Item1 | VARCHAR2[2] | Type of the first charging item group in the charging information list. The options are as follows:<br>• **A**: call attempt<br>• **C**: content-based charging<br>• **D**: duration-based charging<br>• **E**: event-based charging<br>• **F**: one-off charging<br>• **I**: cross-network charging |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **N**: no charging<br>• **V**: charging by upstream traffic<br>• **W**: charging by downstream traffic<br>• **X**: charging by total traffic<br>This field cannot be left empty. |
| 16 | Called_Country_Code | VARCHAR2[10] | Country code of the called party.<br>This field can be left empty. |
| 17 | Call_Type_Level1 | VARCHAR2[2] | Level-1 call type. The options are as follows:<br>• **1**: national<br>• **2**: international<br>This field can be left empty. |
| 18 | Call_Type_Level2 | VARCHAR2[2] | Level-2 call type. The options are as follows:<br>• **0**: unknown<br>• **1**: mobile<br>• **2**: fixed-line network<br>• **3**: irrelevant to location<br>• **4**: premium rate<br>This field can be left empty. |
| 19 | Call_Type_Level3 | VARCHAR2[2] | Level-3 call type. The items in this category are sub-items of the level-2 category.<br>• Value **1** is restricted for local calls and shall not be used for any other category within the VPMN's IOT.<br>• All other values are as defined within the VPMN's IOT.<br>This field can be left empty. |
| 20 | charge_Type11 | VARCHAR2[4] | Charge code of the first charging item in the first charging item group. The options are as follows:<br>• **00**: total fee that can be invoiced<br>• **01**: total call fee<br>• **02**: reserved<br>• **03**: toll call fee<br>• **04**: directory assistance service<br>• **05**: directory assistance after a call<br>• **06-13**: reserved<br>• **14**: voice mailbox deposits<br>• **15**: voice mailbox compensation<br>• **16-20**: reserved<br>• **21**: additional fee of the VPMN<br>• **69-99**: reserved |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **100**: total fee generated during the charging detail rating period<br>• **101**: total call fee generated during the charging detail rating period<br>• **102**: toll call fee generated during the charging detail rating period<br>The service usage fee for a charged party is calculated based on the values of **charGE1***X* (such as **charGE11**, **charGE12**, and **charGE13**), **charGE2***X* (such as **charGE21**, **charGE22**, and **charGE23**), and **charge_Type**. Each charging item group (**charge_Type**) corresponds to a charGE value, for example, **charge_Type12** corresponds to **charGE12**. The calculation methods are as follows:<br>• If none of the values of **charge_Type1***X* and **charge_Type2***X* is **00**, the calculation formula is as follows: Total fee = **charGE11** + **charGE12** + **charGE13** + **charGE21** + **charGE22** + **charGE23**.<br>• If one of the values of **charge_Type1***X* and **charge_Type2***X* is **00**, for example, when the value of **charge_Type12** is **00**, the calculation formula is as follows: Total fee = **charGE12** + **charGE21** + **charGE22** + **charGE23**.<br>• If multiple values of **charge_Type1***X* and **charge_Type2***X* are **00**, the total fee is the sum of the **charGE** values corresponding to the first **charge_Type1***X* and **charge_Type2***X* whose values are **00**. For example, when the value of **charge_Type11** is **00**, **charge_Type12** is **04**, **charge_Type13** is **00**, **charge_Type21** is **05**, **charge_Type22** is **00**, and **charge_Type23** is **00**, the calculation formula is as follows: Total fee = **charGE11** + **charGE22**.<br>This field can be left empty. |
| 21 | charGE11 | NUMBER[20] | Charged amount of the first charging item in the first charging item group.<br>This field can be left empty. |
| 22 | charge_Units11 | NUMBER[10] | Unit of the first charging item in the first charging item group.<br>This field can be left empty. |
| 23 | charge_Type12 | VARCHAR2[4] | Charge code of the second charging item in the first charging item group. The options are as follows: |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **00**: total fee that can be invoiced<br>• **01**: total call fee<br>• **02**: reserved<br>• **03**: toll call fee<br>• **04**: directory assistance service<br>• **05**: directory assistance after a call<br>• **06-13**: reserved<br>• **14**: voice mailbox deposits<br>• **15**: voice mailbox compensation<br>• **16-20**: reserved<br>• **21**: additional fee of the VPMN<br>• **69-99**: reserved<br>• **100**: total fee generated during the charging detail rating period<br>• **101**: total call fee generated during the charging detail rating period<br>• **102**: toll call fee generated during the charging detail rating period<br>This field can be left empty. |
| 24 | charGE12 | NUMBER[20] | Charged amount of the second charging item in the first charging item group.<br>This field can be left empty. |
| 25 | charge_Units12 | NUMBER[10] | Unit of the second charging item in the first charging item group.<br>This field can be left empty. |
| 26 | charge_Type13 | VARCHAR2[4] | Charge code of the third charging item in the first charging item group. The options are as follows:<br>• **00**: total fee that can be invoiced<br>• **01**: total call fee<br>• **02**: reserved<br>• **03**: toll call fee<br>• **04**: directory assistance service<br>• **05**: directory assistance after a call<br>• **06-13**: reserved<br>• **14**: voice mailbox deposits<br>• **15**: voice mailbox compensation<br>• **16-20**: reserved<br>• **21**: additional fee of the VPMN<br>• **69-99**: reserved<br>• **100**: total fee generated during the charging detail rating period |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **101**: total call fee generated during the charging detail rating period<br>• **102**: toll call fee generated during the charging detail rating period<br>This field can be left empty. |
| 27 | charGE13 | NUMBER[20] | Charged amount of the third charging item in the first charging item group.<br>This field can be left empty. |
| 28 | charge_Units13 | NUMBER[10] | Unit of the third charging item in the first charging item group.<br>This field can be left empty. |
| 29 | charged_Item2 | VARCHAR2[2] | Type of the second charging item group in the charging information list. The options are as follows:<br>• **A**: call attempt<br>• **C**: content-based charging<br>• **D**: duration-based charging<br>• **E**: event-based charging<br>• **F**: one-off charging<br>• **I**: cross-network charging<br>• **N**: no charging<br>• **V**: charging by upstream traffic<br>• **W**: charging by downstream traffic<br>• **X**: charging by total traffic<br>This field can be left empty. |
| 30 | charge_Type21 | VARCHAR2[4] | Charge code of the first charging item in the second charging item group. The options are as follows:<br>• **00**: total fee that can be invoiced<br>• **01**: total call fee<br>• **02**: reserved<br>• **03**: toll call fee<br>• **04**: directory assistance service<br>• **05**: directory assistance after a call<br>• **06-13**: reserved<br>• **14**: voice mailbox deposits<br>• **15**: voice mailbox compensation<br>• **16-20**: reserved<br>• **21**: additional fee of the VPMN<br>• **69-99**: reserved<br>• **100**: total fee generated during the charging |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | detail rating period<br>• **101**: total call fee generated during the charging detail rating period<br>• **102**: toll call fee generated during the charging detail rating period<br>This field can be left empty. |
| 31 | charGE21 | NUMBER[20] | Charged amount of the first charging item in the second charging item group.<br>This field can be left empty. |
| 32 | charged_Units21 | NUMBER[10] | Unit of the first charging item in the second charging item group.<br>This field can be left empty. |
| 33 | charge_Type22 | VARCHAR2[4] | Charge code of the second charging item in the second charging item group. The options are as follows:<br>• **00**: total fee that can be invoiced<br>• **01**: total call fee<br>• **02**: reserved<br>• **03**: toll call fee<br>• **04**: directory assistance service<br>• **05**: directory assistance after a call<br>• **06-13**: reserved<br>• **14**: voice mailbox deposits<br>• **15**: voice mailbox compensation<br>• **16-20**: reserved<br>• **21**: additional fee of the VPMN<br>• **69-99**: reserved<br>• **100**: total fee generated during the charging detail rating period<br>• **101**: total call fee generated during the charging detail rating period<br>• **102**: toll call fee generated during the charging detail rating period<br>This field can be left empty. |
| 34 | charGE22 | NUMBER[20] | Charged amount of the second charging item in the second charging item group.<br>This field can be left empty. |
| 35 | charged_Units22 | NUMBER[10] | Unit of the second charging item in the second charging item group.<br>This field can be left empty. |
| 36 | charge_Type23 | VARCHAR | Charge code of the third charging item in the |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | 2[4] | second charging item group. The options are as follows:<br>• **00**: total fee that can be invoiced<br>• **01**: total call fee<br>• **02**: reserved<br>• **03**: toll call fee<br>• **04**: directory assistance service<br>• **05**: directory assistance after a call<br>• **06-13**: reserved<br>• **14**: voice mailbox deposits<br>• **15**: voice mailbox compensation<br>• **16-20**: reserved<br>• **21**: additional fee of the VPMN<br>• **69-99**: reserved<br>• **100**: total fee generated during the charging detail rating period<br>• **101**: total call fee generated during the charging detail rating period<br>• **102**: toll call fee generated during the charging detail rating period<br>This field can be left empty. |
| 37 | charGE23 | NUMBER[20] | Charged amount of the third charging item in the second charging item group.<br>This field can be left empty. |
| 38 | charged_Units23 | NUMBER[10] | Unit of the third charging item in the second charging item group.<br>This field can be left empty. |
| 39 | Day_Category | VARCHAR2[4] | Preferential day type. The options are as follows:<br>• **N**: workday<br>• **I**: national independence day<br>• **P**: public holiday<br>• **R**: weekend<br>This field can be left empty. |
| 40 | Category_Subtype | VARCHAR2[4] | Subtype associated with **Day Category**.<br>This field is defined by the carrier corresponding to the visited area of a roaming subscriber.<br>This field can be left empty. |
| 41 | Time_Band | VARCHAR2[4] | Charging time segment associated with **Charge Detail** and **Charge Detail Timestamp**. This field is defined by the carrier corresponding to the visited area of a roaming subscriber. If **Charge** |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | **Detail Timestamp** is not provided, this field indicates the time segment corresponding to **Charging Timestamp** associated with **Charging Information**.<br>The carrier corresponding to the visited area can set **Time_Band_Subtype** to further specify the charging time segment.<br>This field can be left empty. |
| 42 | Time_Band_Subtype | VARCHAR2[4] | Charging time segment subtype.<br>This field is defined by the carrier corresponding to the visited area of a roaming subscriber.<br>This field can be left empty. |
| 43 | Multiate_Indicator | VARCHAR2[2] | Indicates whether the type of the preferential day or preferential time segment changes during charging.<br>A flag indicating that a Charge Detail began during the related Day Category and Time Band and spanned a change of either of those items.<br>This field can be left empty. |
| 44 | Tax_Type | VARCHAR2[4] | Tax type.<br>Tax type associated with Tax Rate Code and Tax Rate. The options are as follows:<br>• **01**: national tax<br>• **02**: regional tax<br>• **03**: county tax<br>• **04**: local or city tax<br>• **05**: provincial tax.<br>• **06**: dominion tax<br>• **07**: gross receipts tax<br>• **08**: absolute or fixed tax (no tax rate specified)<br>• **09**: public utility tax<br>• **10**: sales and use tax<br>• **11**: excise tax<br>• **12**: communications tax<br>• **13**: value added tax (VAT)<br>• **14**: harmonized sales tax<br>This field can be left empty. |
| 45 | Tax_Rate | NUMBER[10] | Tax rate for a specific tax type and code.<br>According to some national laws and regulations, taxes must be collected based on the tax rate corresponding to the invoice date. If invoice generation is postponed, the tax rate in the |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | invoice may be different from the tax rate that is transferred. However, the occurrence rate of this situation is extremely low.<br>This field is mandatory unless the fixed tax rate is used.<br>The value is precise to five decimal places and ranges from 00.00000 to 99.99999.<br>This field can be left empty. |
| 46 | Tax_Value | NUMBER[20] | Actual tax amount. The value must be equal to or greater than 0 and the number of decimal places is specified by TAP Decimal Places. The value is in SDRs.<br>This field can be left empty. |
| 47 | Discount_Type | NUMBER[10] | Discount type. The options are as follows:<br>• **0**: discount rate<br>• **1**: fixed discount value<br>This field can be left empty. |
| 48 | Discount_Rate | NUMBER[10] | Discount rate.<br>This field can be left empty. |
| 49 | Discount_Value | NUMBER[20] | Discount amount.<br>This field can be left empty. |
| 50 | CAMEL_Service_Address | VARCHAR2[8] | Customized Applications for Mobile Network Enhanced Logic (CAMEL) server address.<br>This field can be left empty. |
| 51 | CAMEL_Service_Level | VARCHAR2[4] | CAMEL service level.<br>This field can be left empty. |
| 52 | CAMEL_Service_Key | VARCHAR2[4] | CAMEL service key value.<br>This field can be left empty. |
| 53 | Default_Call_Handling_Indicator | VARCHAR2[2] | Default call processing ID of the CAMEL.<br>This field can be left empty. |
| 54 | CAMEL_MSC_Address | VARCHAR2[15] | MSC address of the CAMEL.<br>This field can be left empty. |
| 55 | CAMEL_Reference_Num | NUMBER[20] | CAMEL activation flag.<br>This field can be left empty. |
| 56 | CAMEL_Initiated_Indicator | VARCHAR2[2] | Indicates whether the call is a forwarded call initiated by the CAMEL server.<br>This field can be left empty. |
| 57 | CAMEL_Modif | VARCHAR | Indicates whether a call is initiated when the |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | ication | 2[2] | CAMEL protocol is used.<br>This field can be left empty. |
| 58 | CSE_Info | VARCHAR 2[40] | Information downloaded from the CAMEL server.<br>This field can be left empty. |
| 59 | SGSN | VARCHAR 2[15] | Address of the serving GPRS support node (SGSN).<br>This field can be left empty. |
| 60 | GGSN | VARCHAR 2[15] | Address of the gateway GPRS support node (GGSN).<br>This field can be left empty. |
| 61 | GPRS_Conn_Type | NUMBER[10] | GPRS connection type.<br>• **0**: Global System for Mobile Communications (GSM)<br>• **1**: Universal Mobile Telecommunications System (UMTS)<br>This field can be left empty. |
| 62 | Ctrl_Node | NUMBER[10] | Control node type. The options are as follows:<br>• **0**: combination of the SGSN and GGSN nodes<br>• **1**: SGSN<br>• **2**: GGSN<br>This field can be left empty. |
| 63 | PDP_Type | NUMBER[10] | Packet Data Protocol (PDP) session type.<br>This field can be left empty. |
| 64 | PDP_Address | VARCHAR 2[20] | PDP address.<br>This field can be left empty. |
| 65 | APNNI | VARCHAR 2[63] | Network ID of an access point.<br>This field can be left empty. |
| 66 | APNOI | VARCHAR 2[37] | Carrier ID of an access point.<br>This field can be left empty. |
| 67 | Partial_Type | VARCHAR 2[1] | ID of a partial CDR.<br>This field can be left empty. |
| 68 | PDP_Start_Time | VARCHAR 2[14] | PDP session start time.<br>This field can be left empty. |
| 69 | Network_Init_PDP | NUMBER[10] | Type of the network created by a PDP session.<br>This field can be left empty. |
| 70 | charging_ID | NUMBER[1 | Charging ID. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | 0] | This field can be left empty. |
| 71 | Data_Volume_Incoming | NUMBER[10] | Received traffic.<br>This field can be left empty. |
| 72 | Data_Volume_Outgoing | NUMBER[10] | Sent traffic.<br>This field can be left empty. |
| 73 | QOS_REQ_Alloc_Reten_Prior | NUMBER[10] | Allocation or retention priority of the wireless access during GPRS connection in the Universal Mobil Telecommunications System (UMTS).<br>This field can be left empty. |
| 74 | QOS_USED_Alloc_Reten_Prior | NUMBER[10] | Indicates whether the allocation or retention priority of the wireless access is used during GPRS connection in the UMTS.<br>This field can be left empty. |
| 75 | QOS_REQ_Guar_Dlink | VARCHAR2[10] | Request bit rate that must be provided by the UMTS bearer service for customers or applications to use in the download service.<br>This field can be left empty. |
| 76 | QOS_USED_Guar_Dlink | VARCHAR2[10] | Actual bit rate that must be provided by the UMTS bearer service for customers or applications to use in the download service.<br>This field can be left empty. |
| 77 | QOS_REQ_Guar_Ulink | VARCHAR2[10] | Request bit rate that must be provided by the UMTS bearer service for customers or applications to use in the upload service.<br>This field can be left empty. |
| 78 | QOS_USED_Guar_Ulink | VARCHAR2[10] | Actual bit rate that must be provided by the UMTS bearer service for customers or applications to use in the upload service.<br>This field can be left empty. |
| 79 | QOS_REQ_Max_Dlink | VARCHAR2[10] | Maximum download request bit rate during GPRS connection in the UMTS.<br>This field can be left empty. |
| 80 | QOS_USED_Max_Dlink | VARCHAR2[10] | Actual maximum download bit rate during GPRS connection in the UMTS.<br>This field can be left empty. |
| 81 | QOS_REQ_Max_Ulink | VARCHAR2[10] | Maximum upload request bit rate during GPRS connection in the UMTS.<br>This field can be left empty. |
| 82 | QOS_USED_Max_Ulink | VARCHAR2[10] | Actual maximum upload bit rate during GPRS connection in the UMTS. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | This field can be left empty. |
| 83 | QOS_REQ_Traff_Class | NUMBER[10] | Request application type during GPRS connection in the UMTS.<br>This field can be left empty. |
| 84 | QOS_USED_Traff_Class | NUMBER[10] | Actual application type during GPRS connection in the UMTS.<br>This field can be left empty. |
| 85 | QOS_REQ_Delay | NUMBER[10] | Request transmission delay during GPRS connection.<br>This field can be left empty. |
| 86 | QOS_USED_Delay | NUMBER[10] | Actual transmission delay during GPRS connection.<br>This field can be left empty. |
| 87 | QOS_REQ_Mean Throughput | NUMBER[10] | Minimum request throughput during GPRS connection.<br>This field can be left empty. |
| 88 | QOS_USED_Mean Throughput | NUMBER[10] | Actual minimum throughput during GPRS connection.<br>This field can be left empty. |
| 89 | QOS_REQ_peak Throughput | NUMBER[10] | Maximum request throughput during GPRS connection.<br>This field can be left empty. |
| 90 | QOS_USED_peak Throughput | NUMBER[10] | Actual maximum throughput during GPRS connection.<br>This field can be left empty. |
| 91 | QOS_REQ_precedence | NUMBER[10] | Request priority during GPRS connection.<br>• **0**: not specified<br>• **1**: high<br>• **2**: medium<br>• **3**: low<br>This field can be left empty. |
| 92 | QOS_USED_precedence | NUMBER[10] | Actual priority during GPRS connection.<br>• **0**: not specified<br>• **1**: high<br>• **2**: medium<br>• **3**: low<br>This field can be left empty. |
| 93 | QOS_REQ_reliability | NUMBER[10] | Request reliability during GPRS connection.<br>This field can be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 94 | QOS_USED_reliability | NUMBER[10] | Actual reliability during GPRS connection.<br>This field can be left empty. |
| 95 | Reserve | VARCHAR2[1] | This field is reserved.<br>This field can be left empty. |
| 96 | Reserve | VARCHAR2[1] | This field is reserved.<br>This field can be left empty. |
| 97 | Reserve | VARCHAR2[24] | This field is reserved.<br>This field can be left empty. |
| 98 | TAPFILENAME | VARCHAR2[64] | CDR file name, containing the international roaming PMN code that indicates the country code and carrier information. The CDR file name is in the format CD*XXXXXYYYYYSequence number*.suffix.<br>• **CD**: CDR file name prefix. The first two digits have a fixed value of **CD**.<br>• XXXXX: PMN code of the carrier corresponding to the visited area of a roaming-out subscriber<br>• YYYYY: PMN code of the carrier corresponding to the home area of a roaming-out subscriber<br>This field cannot be left empty. |
| 99 | reserve | VARCHAR2[10] | This field is reserved.<br>This field can be left empty. |
| 100 | Service_Type | VARCHAR2[5] | Service type.<br>This field can be left empty. |
| 101 | ExchangeRate | NUMBER[10] | Exchange rate between the local currency and standard currency.<br>This field can be left empty. |
| 102 | chargeable_unit1 | NUMBER[10] | Rounding unit for the first type of service usage generated during charging.<br>This field can be left empty. |
| 103 | chargeable_unit2 | NUMBER[10] | Rounding unit for the second type of service usage generated during charging.<br>This field can be left empty. |
| 104 | chargeable_unit3 | NUMBER[10] | Rounding unit for the third type of service usage generated during charging.<br>This field can be left empty. |
| 105 | reserve | VARCHAR2[1] | This field is reserved.<br>This field can be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 106 | CALL_START_TIME_TIMEZONE | NUMBER[10] | Time zone of the visited area. The information is transparently transferred and recorded in CDRs, but it does not affect rating.<br>This field can be left empty. |
| 107 | TAPFILELineNo | NUMBER[10] | Line number of a CDR in a TAPIN CDR file. The file header and tail are not counted as lines.<br>This field cannot be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

# 3 CDR Files Generated in the OCG

## About This Chapter

This topic describes the file storage directories, file name formats, CDR fields, and field sequences of different types of CDRs generated in the OCG.

## 3.1 Basic Information About OCG CDR Files

This topic describes basic information such as the file name formats and file storage directories of CDRs generated in the OCG.

### 3.1.1 CDR Storage Directories in OCG

#### CDR Storage Directories

The CDR files are stored in the following directories:

- Destination directory: **${ENIP_HOME}/record/w_vou/send**

  It is the destination directory for storing CDR files after the CDR files meet the switching conditions.
- Temporary directory: **${ENIP_HOME}/record/w_vou/buffer**

  It is the directory for storing temporary CDR files before the CDR files meet the switching conditions.
- Backup directory: **${ENIP_HOME}/record/w_vou/bak**

  It is the directory for backing up CDRs obtained from the destination directory. CDRs can be used to locate problems.

In the preceding directories, **${ENIP_HOME}** refers to the installation directory of the OCG. The directories are just an example.

**NOTE**

w_vou is the prefix of CDR file name.

 Copyright © Huawei Technologies Co., Ltd. 

### Set the directory for storing CDR files.

To set the directory for storing CDR files, you can perform the following operations: In the service view of the iCnfg, choose **Service Related Configuration** > **CDR Configuration** > **CDR Charging Data Configuration**. In the window that is displayed, set **Directory name**.

### Set the number of CDR events and CDR event interval for triggering CDR file writing

To set the number of CDR events and CDR event interval for triggering CDR file writing, do as follows: In the service view of the iCnfg, choose **Service Related Configuration** > **CDR Configuration** > **CDR Basic Configuration**. In the window that is displayed, set **Number of triggering records for writing cdr file** (indicating the number of records for triggering CDR file writing) and **Interval for triggering writing cdr file (s)** (indicating the CDR event interval for triggering CDR file writing).

## 3.1.2 Process of Generating offline CDRs in the OCG

This topic describes the process of generating offline CDR files in the OCG.

Figure 3-1 shows the OCG offline CDR processing process.

**Figure 3-1** OCG offline CDR processing process




OCG offline CDRs are processed as follows:

1. The Mediation obtains CDRs periodically from the destination directory according to configurations, and then transfers them to the CBP.
2. The CBP generates a CDR after charging.
3. The Mediation preprocesses the CDR files and uploads them to the EDRDB system for CDR sorting, storage, accumulation, and collection.

## 3.1.3 File Name Format of OCG-Generated CDRs

In the Online Mediation service, CDRs generated by the service can be regarded as CDR logs. The OCG CDR file name is in the following format:

{CDR prefix}{xxxxx}.{YYYYMMDD}.{NEID}.{Index number}{CDR file name extension}

Table 3-1 describes fields in a OCG-generated CDR file name.

**Table 3-1** Description of fields in an OCG-generated CDR file name

| Field | Description |
|---|---|
| CDR prefix | Indicates the prefix of a CDR file name and refers to the CDR type.<br>CDRs can be distinguished based on CDR file name prefixes. |
| xxxxx | *xxxxx* indicates five-digit charging node ID.<br>The system prefixes zeros if the node ID is less than five digits.<br>If this field is set to **0**, it can be omitted. |
| YYYYMMDD | Indicates the date when a CDR file is generated. |
| NEID | Indicates the SEE node ID that generates a CDR file.<br>The serial number is a numeric string of five digits. The system prefixes zeros if the node ID is less than five digits.<br>Whether the CDR file name contains the field is configurable. |
| Index number | Indicates the serial number of a CDR file in a day.<br>The serial number is a string of six characters.<br>Value range: 000000 to 999999. |
| CDR file name extension | Indicates the extension of a CDR file name. The extension is **.unl** by default. |

## Example of OCG CDRs file name

- w_abr10101.20180510.01001.000001.unl

  It indicates that the CDR with the serial number 000001, and charging node id 10101 in the Service generated the w_abr CDR file on May 10, 2018.
- w_rec10101.20150315.01001.000018.unl

  It indicates that the CDR with the serial number 000018, SEE node ID 01001, and charging node id 10101 in the Service generated the w_rec CDR file on May 15, 2015.
- w_vou10101.20150724.01001.000034.unl

  It indicates that the CDR with the serial number 000034, and charging node id 10101 in the Service generated the w_vou CDR file on July 24, 2015.

## Related Configuration

- Set the time type in the CDR file name

  To set the time type in the CDR file name, you can perform the following operations: In the service view of the iCnfg, choose **Service Related Configuration** > **CDR Configuration** > **CDR Charging Data Configuration**. In the window that appears, set **Format of time in CDR file name**.
- Set whether CDR file name carries the SEE node ID

  On the iCnfg Service view, select **Generate NodeID in file name** after choosing **Service Related Configuration** > **CDR Configuration** > **CDR Charging Data Configuration**. You can configure whether CDR file name carries the node ID.

 Copyright © Huawei Technologies Co., Ltd. 

## 3.1.4 Requirements on OCG-Generated CDR Files

OCG will generate a new record file, when the size, duration, and record count of current file matches this configuration value.

OCG will generate a new record file, when matching one of these three conditions:

- 1. The file size matches the configuration value of "Max. size of a CDR file".
- 2. The file generation matches the configuration value of "Max. duration of a CDR file".
- 3. The file records count matches the configuration value of "Max. record count of a CDR file".

### Set the Max. size of a CDR file

To set the Max. size of a CDR file, you can perform the following operations: In the service view of the iCnfg, choose **Service Related Configuration** > **CDR Configuration** > **CDR Charging Data Configuration**. In the window that is displayed, set **Max. size of a CDR file**.

### Set the Max. duration of a CDR file

To set the Max. duration of a CDR file, you can perform the following operations: In the service view of the iCnfg, choose **Service Related Configuration** > **CDR Configuration** > **CDR Charging Data Configuration**. In the window that is displayed, set **Max. duration of a CDR file**.

### Set the Max. record count of a CDR file

To set the Max. record count of a CDR file, you can perform the following operations: In the service view of the iCnfg, choose **Service Related Configuration** > **CDR Configuration** > **CDR Charging Data Configuration**. In the window that is displayed, set **Max. record count of a CDR file**.

## 3.1.5 Configuring the Function of Automatically Deleting CDRs by the OCG

If the system does not automatically obtain CDRs, the OCG needs to automatically delete the CDRs to prevent the system memory from being occupied. This topic describes how to configure the function of automatically deleting CDRs by the OCG.

### Procedure

**Step 1** Log in to the iCnfg.

**Step 2** Choose **Service Related Configuration** > **CDR Configuration** > **CDR Basic Configuration** and configure the table.

| Parameter | Setting |
| --- | --- |
| Threshold time when report alarm | Threshold time of non-moved cdr files in **send** directory.<br>Unit: Day.<br>Value range: an integer ranging from 1 to 30.<br>For example: 7. |
| Is auto backup | Indicates whether to back up the CDR file automatic.<br>For example: backup. |
| Threshold time when backup | Threshold time of auto backup of non-moved cdr files in **send** directory.<br>Unit: Day.<br>Value range: an integer ranging from 1 to 30.<br>For example: 3. |

**----End**

# 3.2 OCG-Generated CDR Files

This topic describes the file name format, CDR fields, field sequence, and service scenarios of different types of CDRs generated in the OCG.

**NOTE**

Offline CDRs can be customized in the OCG. To customize an offline CDR, configure information such as the CDR generation component and CDR type under **NGOCG** > **Basic** > **CDR** > **CDR Type Info**, and then configure information such as output CDR fields under **NGOCG** > **Basic** > **CDR** > **CDR Output Field Control**.

Alternatively, you can configure the information in the **ocg_cdrtype** and **ocg_cdroutinfo** tables in the background.

## 3.2.1 w_abr CDR

When an error occurs during the interaction between the Routing and the CBP, w_abr CDR records the information if the system allows a subscriber to go on using the call service. The CBE rates and deducts fees based on the CDR after the CBE recovers.

### Generation Scenario

In the MO, MT, or MF process, the Routing generates a w_abr CDR if the system allows a subscriber to go on using the call service when an error occurs during the interaction between the Routing and the CBP.

### CDR File Name Format

{w_abr}.{YYYYMMDD}.{NEID}.{Index number}.unl

### CDR Instance

Example of a w_abr CDR file name: w_abr.20130515.10002.000001.unl

91|1147732910|00861360000001|00861360000002|||20130620144700|0|00861360000002|008
61360000002|0||0086133|0000000000000000||||||2|||0|460070360000012|20160818100227404
01116050020|86133|8|20160818100227|260|0|260|0|2001|0||||||-1|0|2|2|0|2|0|0|0086136000000
2||1|0||0|101|1|4|1|||||||

## CDR File Format

**Table 3-2** Format of w_abr CDR

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 1 | ServiceKey | Integer | Indicates the service key.<br>The options are as follows:<br>• GSM network: The value of the field is **91**.<br>• CDMA network: The value of the field is **13100**.<br>• SIP network: The value of the field is **103**.<br>• SINAP network: The value of the field is **104**.<br>• INAPCS1+ network: The value of the field is **105**.<br>Not null. |
| 2 | SubCosID | Integer/Char[20] | Indicates the main product of a subscriber.<br>**NOTE**<br>In CBS 5.5, the data type for this field is **Char[20]**. In other CBS versions, the data type for this field is **Integer**.<br>Not null. |
| 3 | CallingPartyNumber | Char[32] | Indicates the calling number.<br>**NOTE**<br>The value of this parameter is the IDP original reported value.<br>Can be null. |
| 4 | CalledPartyNumber | Char[32] | Indicates the called number.<br>**NOTE**<br>The value of this field is an original number reported by the IDP and is not converted.<br>Can be null. |
| 5 | Calling-Party-NP | Char[16] | Indicates the number portability prefix of the calling number. It refers to the routing prefix of the calling number after the calling party transfers from one network to another. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | Can be null. |
| 6 | Called-Party-NP | Char[16] | Indicates the number portability prefix of the called number. It refers to the routing prefix of the called number after the called party transfers from one network to another.<br>Can be null. |
| 7 | SSP-Time | Char[14] | Indicates the time reported by the SSP.<br>Format: YYYYMMDDhhmmss<br>**NOTE**<br>This field value in all versions is GMT time.<br>In SIP and CDMA network, the field can be null.<br>Can be null. |
| 8 | MF-Indicator | Integer | Indicates the indicator of called forwarding.<br>The options are as follows:<br>• 0: Not forward<br>• 1: Forward<br>Not null. |
| 9 | Real-Called-Number | Char[32] | Indicates the real called number.<br>Format:<br>• CC+MSISDN<br>• CC+AREACODE+PSTN<br>• International prefix+CC+MSISDN<br>**NOTE**<br>In CBS5.5, the field can be empty. In other CBS versions, the field can not be empty.<br>Can be null. |
| 10 | Connect-Called-Number | Char[32] | Indicates the called number for connection.<br>For example, when an IP address is preset, the value of **Connect-Called-Number** is in the format *IP prefix* + *called number*.<br>Not null. |
| 11 | Charge-Flow-Typ | Integer | Indicates the charge process type. |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | e | | The options are as follows:<br>• 0: The calling process<br>• 1: The called process<br>• 3: The forwarding process<br>Not null. |
| 12 | Calling-Partys-Category | Char[] | Indicates the category of the calling party.<br>Example: a carrier, a public call office, or a user.<br>The value of the field **Calling-Partys-Category** depends on the value of the variable **CAP_InitialDP_callingPartysCategory**.<br>Can be null. |
| 13 | Calling-Vlr-Number | Char[32] | Indicates the VLR number of the visitor location of the calling party.<br>The field can be null in the called process and forwarding process.<br>In the MO, MF flow, when the site uses **location number** for analysis, this parameter is recorded as **location number**. |
| 14 | CallingCellID | Char[32] | Indicates the cell ID of the calling party.<br>The field can be null in the called process and forwarding process.<br>**NOTE**<br>Choose **NG OCG** > **Basic** > **System Configuration** > **System Control**. Click to display the **Settings** page. Click next to **System Flag** and view the value of **Record Subscribe Location Info**.<br>• If **Record Subscribe Location Info** is set to **Yes**, this field records location information.<br>• If **Record Subscribe Location Info** is set to **No**, this field is recorded as a string of asterisks (*). |
| 15 | Called-Vlr-Number | Char[32] | Indicates the VLR number of the visitor location of the called party.<br>The field can be null in the calling |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | process and forwarding process.<br>Can be null.<br>In the MT flow, when the site uses **location number** for analysis, this parameter is recorded as **location number**. |
| 16 | CalledCellID | Char[32] | Indicates the cell ID of the called party.<br>The field can be null in the calling process and forwarding process.<br>**NOTE**<br>Choose **NG OCG** > **Basic System Configuration** > **System Control**. Click to display the **Settings** page. Click next to **System Flag** and view the value of **Record Subscribe Location Info**.<br>• If **Record Subscribe Location Info** is set to **Yes**, this field records location information.<br>• If **Record Subscribe Location Info** is set to **No**, this field is recorded as a string of asterisks (*). |
| 17 | Original-Called-Party-Id | Char[32] | Indicates the original called number.<br>• In the forwarding process, the MSC reports the original called number.<br>• In the calling process, the MSC does not report the original called number. Therefore, the field is null.<br>Can be null. |
| 18 | Additional-Calling-Party-Number | Char[64] | Indicates the additional calling number.<br>Can be null. |
| 19 | Bearer-Capability | Char[32] | Indicates the bearer capacity of subscriber connection.<br>For example, 8000080006.<br>• If the octet3 (characters 5 and 6) is not 08, the call type is Voice.<br>• If Octect3 is 8 and Octect5 (characters 9 and 10) is 6, the call type is Video. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • The other type is Data.<br>Can be null. |
| 20 | EventType-BCSM | Integer | Indicates the event report.<br>• 2: MO/MF<br>• 12: MT<br>• 101: Initial<br>• 102: Update<br>• 103: Termination<br>• 104: Direct debit<br>Not null. |
| 21 | Redirecting-Party-Id | Char[32] | Indicates the redirection number in the forwarding process. It is the calling number in the forwarding process.<br>• In the forwarding process, the MSC reports the redirection number.<br>• In the calling process, the MSC does not report the redirection number. Therefore, the field is null.<br>Can be null. |
| 22 | Redirection-Information | Char[36] | Indicates the redirection information. It is used in the forwarding process.<br>Can be null. |
| 23 | Redirection-Reason | Integer | Indicates the forwarding reason.<br>The options are as follows:<br>CDMA:<br>• 0: Not forward<br>• 1: Forward unconditionally<br>• 2: Forward on the busy mobile<br>• 3: Forward on no reply<br>• 4: Other<br>• 22: Forward unreachable<br>GSM:<br>• 0: Not forward<br>• 1: Forward on the busy mobile<br>• 2: Forward on no reply<br>• 3: Forward unconditionally<br>• 4: Other |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • 6: Forward unreachable<br>Not null. |
| 24 | UE-IMSI | Char[64] | Indicates the IMSI of the calling party.<br>Can be null. |
| 25 | CallReferenceNumber | Char[128] | Indicates the reference number of a call. It is used to uniquely identify a call.<br>The options are as follows:<br>• For the CDMA network, obtain the value of **BillID** in the ORREQ message for this field.<br>• For the GSM network, obtain the value of **CallReferenceNumber** that is reported in the IDP signaling for this field.<br>• For the NGN and IMS networks, obtain the value of **Call-ID** that is reported in the SIP signaling for this field.<br>• If the system cannot obtain the required information (excluding the preceding conditions), the value of this field is in the format *YYYYMMDDhhmmss* (14 digits) + *NE ID* (6-8 digits) + *hostid* + *container ID* + *Index* (4 digits).<br>**NOTE**<br>If the length of the automation number is less than four digits, prefix 0 to the automation number. If the length of the automation number is more than four digits, obtain the last four digits from the automation number.<br>In the UK VDF voice process, this field records the value of **Chargeable-Event-Id**.<br>Not null. |
| 26 | MSC-Address | Char[32] | Indicates the MSC address.<br>Can be null. |
| 27 | Time-Zone | Integer | Indicates the time zone of the area where a subscriber is. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | Not null. |
| 28 | CallBeginTime | Char[14] | Indicates the time of the calling beginning.<br>Format: YYYYMMDDhhmmss<br>**NOTE**<br>This field value is system local time. |
| 29 | CallDuration | Integer | Indicates the call duration.<br>Unit: second.<br>**NOTE**<br>If the system supports charging by 100 milliseconds, the value of this field is in 100 milliseconds.<br>Not null. |
| 30 | SuccessACDuration | Integer | Indicates the duration of which the fee has been deducted.<br>Unit: second.<br>Not null. |
| 31 | FailACDuration | Integer | Indicates the AC duration during which an error occurs.<br>Unit: second.<br>Not null. |
| 32 | VPMNCallFlag | Integer | Indicates the flag of calls in a community group.<br>Not null. |
| 33 | CBEResultCode | Integer | Indicates that registers the result code return from CBE.<br>The Diameter protocol provides the following types of error codes. The error type is judged based on the first digit of an error code.<br>• 1xxx: Informational<br>• 2xxx: Success<br>• 3xxx: Protocol errors<br>• 4xxx: Transient failure<br>• 5xxx: Permanent failure<br>An error type that cannot be identified, that is, the first digit of an error type is not in the preceding definition, is regarded as a permanent failure.<br>OM gets the resultcode from CBPAdapter.<br>Not Null. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 34 | DDS-Discount | Integer | Indicates the discount value of the MTN zone service. If there is no discount, enter **0**.<br>Not Null. |
| 35 | DiameterSessionID | Char[128] | Format: <DiameterIdentity>;<high 32 bits>;<low 32 bits>[;<optional value>]<br>• <DiameterIdentity>: The value of this field is the same as the value of **Origin-Host**.<br>• <high>: Indicates the current system time.<br>• <low>: The value increases cyclically. The initial value is **0**. When the system is restarted, the value is set to **0**.<br>• <optional value=">: Reserved.<br>Separate each two fields with a semicolon (;).<br>Example: SCP001.huawei.com;1876543210;523<br>Can be null. |
| 36 | NPPrefix | Char[10] | Indicates the NP of called number. It is also called RN prefix.<br>Can be null. |
| 37 | CalledHomeNetWork | Char[10] | Indicates the home area network code of the called party after NP.<br>Can be null. |
| 38 | CallingPartyLRN | Char[20] | Indicates the location routing number (LRN) of the calling party. This field is recorded in the MT process.<br>Can be null. |
| 39 | CalledPartyLRN | Char[20] | Indicates the location routing number (LRN) of the called party. This field is recorded in the MO process.<br>Can be null. |
| 40 | OpposeTenantID | Integer | Indicates the home tenant ID of the peer number.<br>Not Null. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 41 | Service-Free-Indicator | Integer4 | Free service flag.<br>• 0: Normal<br>• 1: Free<br>• 2: DirectConnect<br>Not Null. |
| 42 | NumFormatOfCalling | Integer4 | Calling number type.<br>• 0: Unknown<br>• 1: National<br>• 2: International<br>Not Null. |
| 43 | NumFormatOfCalled | Integer4 | Called number type.<br>• 0: Unknown<br>• 1: National<br>• 2: International<br>Not Null. |
| 44 | NumFormatOfRoute | Integer4 | Route number type.<br>• 0: Unknown<br>• 1: National<br>• 2: International<br>Not Null. |
| 45 | NumFormatOfOVLR | Integer4 | Calling number type of VLR.<br>• 0: Unknown<br>• 1: National<br>• 2: International<br>Not Null. |
| 46 | NumFormatOfTVLR | Integer4 | Called number type of VLR.<br>• 0: Unknown<br>• 1: National<br>• 2: International<br>Not Null. |
| 47 | NumFormatOfOCalled | Integer4 | Original called number type of VLR.<br>• 0: Unknown<br>• 1: National<br>• 2: International<br>Not Null. |
| 48 | CalledPartyBCDNu | Char[32] | Original number from IDP.<br>**NOTE** |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | Can be null while IDP contains this parameter in case of charged party is roaming. |
| 49 | OriginalRedirectPartyId | Char[32] | Original number from IDP for MF, otherwise, put null.<br>Can be null. |
| 50 | Service-Code-Type | Integer4 | Service code type.<br>• 0: BearerService<br>• 1: Teleservice<br>Not Null. |
| 51 | Service-Code | Integer4 | Service code.<br>Not Null. |
| 52 | OFFLINEFILENAME | Char[32] | Reserved.<br>Can be null. |
| 53 | OFFLINEFILELineNo | Integer4 | Reserved.<br>Not Null. |
| 54 | TenantID | Integer4 | Home BE ID of the charged party.<br>Not Null. |
| 55 | Brand | Integer/Char[20] | Brand of the charged party.<br>**NOTE**<br>In CBS 5.5, the data type for this field is **Char[20]**. In other CBS versions, the data type for this field is **Integer**.<br>Not Null. |
| 56 | CallType | Integer4 | Call type. The options are as follows:<br>• 1: international toll call<br>• 2: toll call between charging areas<br>• 3: toll call within a charging area<br>• 4: local call<br>• 7: call made to the home country during international roaming<br>• 8: call made to the roam-in country during international roaming<br>• 9: call made to other countries during international roaming<br>Not Null. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 57 | OnNetFlag | Char[1] | • 0: inter-network<br>• 1: intra-network<br>Not null. |
| 58 | NonChgMainofferId | Char[] | Primary offering ID of the non-charged party.<br>**NOTE**<br>If the primary offering ID fails to be obtained, this field is left empty.<br>Can be null. |
| 59 | Subscription-Id-Data | Char[255] | Charged number. Set this field to the value of **subscriber-id-data** in the group where **subscriber-id-type** is set to **0**.<br>Can be null. |
| 60 | Calling-locationnumber | VARCHAR2[255] | Calling location number.<br>Can be null. |
| 61 | called-locationnumber | VARCHAR2[12] | Called location number.<br>Can be null. |
| 62 | Reserved. | VARCHAR2[12] | This field is left empty. |
| 63 | IMEI | VARCHAR2[15] | IMEI of a phone. The value is reported by an external system. If no value is reported, this parameter can be left empty.<br>This parameter indicates the IMEI of the calling party's device in the MO process, the IMEI of the call forwarding party's device in the MF process, and IMEI of the called party's device in the MT process.<br>**NOTE**<br>This parameter is reported only in the CAMEL4 specification. In the CAP4 definition, CDRs are reported and recorded only in the MO process.<br>Can be null. |

## 3.2.2 w_smo CDR

A w_smo CDR is generated in the following case: In the CBS service, when a subscriber succeeds in sending SMS Messages, but the CBP fails to deduct fees due to system error, the Routing generates a w_smo CDR. The CBE rates and deducts fees based on the CDR after the CBE recovers.

 Copyright © Huawei Technologies Co., Ltd. 

## Generation Scenario

In the Online Mediation service, when a subscriber sends a short message successfully, but the CBP fails to deduct fees due to system errors, the Routing generates a w_smo CDR. The CBP rates and deducts fees based on the CDR after the CBP recovers. The fields contained in the w_smo CDR are the same as the fields contained in the DCC interface between the Routing and the CBP. If some field values cannot be obtained, the fields are set to blank.

## CDR File Name Format

{w_smo}.{YYYYMMDD}.{NEID}.{Index number}.unl

## CDR Instance

Example of a w_smo CDR file name: w_smo.20131225.10002.000002.unl

3|1|27829129|||27829108137||27829804793|27712829118|27829804793|1|0|||||0|0|20160528070126||||0||||||||||||27829804793||||0|0|2|1|0|0|0712829118||0|101|4|4|1|||||||||

## CDR File Format

**Table 3-3** Format of w_smo CDR

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 1 | SmsType | String | Indicates the type of a SMS Message.<br>The options are as follows:<br>• 1: SMPP+, MAP3 SMS Message<br>• 3: CAP3, CAP2, CAP1 SMS Message<br>• 101: Diameter direct debit<br>Can be null. |
| 2 | MessageType | Char[1] | Indicates the message type.<br>The options are as follows:<br>• 1: A fee deduction request message<br>• 2: A confirmation message<br>Can be null. |
| 3 | SMSCAddress | Char[20] | Indicates the SMSC address.<br>Can be null. |
| 4 | SMID | Char[64] | Indicates the short message ID.<br>**NOTE**<br>Currently, the length of an SMS message cannot exceed 24 characters. In the UK VDF DCC-based SMS process, this field records **charge-event-id** and the length can exceed 24 characters.<br>Can be null. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 5 | SMLength | Char[] | Indicates the length of the short message, which is used for charging traffic.<br>Can be null. |
| 6 | MoMSCAddr | Char[20] | Indicates the MSC address of the roaming location of the sender.<br>Can be null.<br>In the SMS interface at Turkey Vodafone, the value maps the value of the **Originating-SCCP-Address** AVP.<br>**NOTE**<br>The field contains the country code but does not contain the international prefix. |
| 7 | MtMSCAddr | Char[20] | Indicates the MSC address of the roaming location of the receiver.<br>Can be null.<br>**NOTE**<br>The field contains the country code but does not contain the international prefix. |
| 8 | SourceAddr | Char[64] | Indicates the sender number. The number is normalized in the OCG and it contains the country code.<br>Not null. |
| 9 | DestAddr | Char[64] | Indicates the receiver number.<br>Not null.<br>The **NG OCG > Basic > BE Control > BE System Control > System Flag > Called Number Format Sent to Rating in CAP3 SMS Flow** field in CBS GUI determines the number format normalized by the OCG. The values of this field are as follows: 0: Country code + MSISDN; 1: International prefix 00 + Country code + MSISDN |
| 10 | FeeAddr | Char[64] | Indicates the charged number. The number is a normalized number containing the country code.<br>Can be null. |
| 11 | FeeFlag | Integer | Indicates the charge flag.<br>The options are as follows:<br>• 0: To charge by using the original method. The value **0** indicates an |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | exception.<br>• 1: To charge the calling number.<br>• 2: To charge the called number.<br>• 3: To charge the charge number.<br>Not null. |
| 12 | FeeType | Integer | Indicates the fee deduction type.<br>The options are as follows:<br>• 0: To charge in the default mode.<br>**NOTE**<br>For the common point-to-point short messages, the fee is configured on the CBS. For other short messages, fees must be charged based on the charging policy sent by the SMSC.<br>• 1: To charge by the number of short messages by the SP.<br>• 2: To charge by months (deducting fees) by the SP.<br>• 3: To charge by months (checking).<br>• 4: To charge by upper limit based on the number of short messages.<br>• 5: To charge the fee of monthly SMS package with the limited number of short messages (deducting fees).<br>• 6: To charge the fee of monthly SMS package with the limited number of short messages (checking).<br>Not null. |
| 13 | FeeItdMsgNum | Integer | Reserved.<br>Not null. The default value is **0**. |
| 14 | FeeSingle | Char[] | Indicates the charge rate of a single short message.<br>Can be null. |
| 15 | FeeFixed | Char[] | Indicates the charge rate of each short message in a monthly SMS package. If the number of short messages exceeds the limited number, the charge rate of the excess short messages is specified by the **FeeSingle** field.<br>Can be null |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 16 | MessagePID | Char[] | Indicates the message PID such as a picture and voice.<br>Can be null. |
| 17 | StatusReportRequest | Integer | Whether a status report is needed after a request message is sent.<br>The options are as follows:<br>• 0: No<br>• 1: Yes<br>Not null. |
| 18 | OriginalNetType | Integer | Indicates the type of the source network.<br>The options are as follows:<br>• 0: GSM<br>• 1: CDMA<br>• 2: TDMA<br>• 3: SMPP<br>Not null. |
| 19 | SMSReceiveTime | Char[14] | Indicates the time when a short message is received. The value is in the format *YYYYMMDDHHMMSS*.<br>**NOTE**<br>• In baseline version, the field value is system local time.<br>• In the UK and SFR versions:<br>For the CAP-based access, the local system time is converted to the UTC time, and this field value is the UTC time (GMT = 0).<br>For the DCC-based access, the **Event-Timestamp** in UTC format in DCC messages is converted to time in the format YYYYMMDDHHMMSS, and this field value is in the format YYYYMMDDHHMMSS.<br>Not null. |
| 20 | CallingService | Char[16] | Indicates the calling service, an array of 16 bytes with each byte representing a type of service.<br>If the value of a byte is **0**, it indicates no service. If the value of a byte is **1**, it indicates that the current message contains the service.<br>The format is as follows: |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • CallingServcie[0]: Short message signature<br>• CallingServcie[1]: Enhanced return notification of MO short message<br>• CallingServcie[2]: Power-on notification<br>Can be null. |
| 21 | CalledService | Char[16] | Indicates the called service, an array of 16 bytes with each byte representing a type of services.<br>If the value of a byte is **0**, it indicates no service. If the value of a byte is **1**, it indicates that the current message contains the service.<br>The options are as follows:<br>• CallingServcie[0]: Short message transfer<br>• CallingServcie[1]: Automatic reply<br>Can be null. |
| 22 | OriginalMsgID | Char[64] | Indicates the ID of the original SMS Message that is associated with the current message.<br>Can be null. |
| 23 | SMDSendResult | Char[] | Whether sending an intra-network short message succeeds or fails and how to dispose.<br>The options are as follows:<br>• 0: Confirm the successful sending of a message<br>• 1: Refund the fee if sending a message fails<br>Not null. |
| 24 | MsgID | Char[20] | Indicates the message ID that the gateway generates.<br>The field **MsgID** is valid to inter-network short messages and Monternet short messages.<br>For intra-network short messages, the value is blank.<br>Can be null. |
| 25 | GWID | Char[10] | Indicates the ID of the gateway that sends the message. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | The field **GWID** is valid to inter-network short messages and Monternet short messages.<br>For intra-network short messages, the value is blank.<br>Can be null. |
| 26 | MsgSeq | Char[10] | Indicates the short message sequence number generated by the SMSC.<br>The field **MsgSeq** is valid to inter-network short messages and Monternet short messages.<br>For intra-network short messages, the value is blank.<br>Can be null. |
| 27 | SPID | Char[10] | Indicates the ID of service provider.<br>The field **SPID** is valid to inter-network short messages and Monternet short messages.<br>For intra-network short messages, the value is blank.<br>Can be null. |
| 28 | ServiceCode | Char[10] | Indicates the code of the service type.<br>The field **ServiceCode** is valid to inter-network short messages and Monternet short messages.<br>For intra-network short messages, the value is blank.<br>Can be null. |
| 29 | SourceGWID | Char[10] | Indicates the ID of the gateway that forwards short messages.<br>The field **SourceGWID** is valid to inter-network short messages and Monternet short messages.<br>For intra-network short messages, the value is blank.<br>Can be null. |
| 30 | PriorityFlag | Char[] | Indicates the priority level of a short message. A small value indicates a high priority.<br>The field **PriorityFlag** is valid to inter-network short messages and Monternet short messages.<br>For intra-network short messages, |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | the value is blank.<br>Can be null. |
| 31 | ChargingRate | Char[] | Indicates the charge rate.<br>The field **ChargingRate** is valid to inter-network short messages and Monternet short messages.<br>For intra-network short messages, the value is blank.<br>Can be null. |
| 32 | ChargingType | Char[] | Indicates the charging type, used in Monternet short messages and inter-network short messages.<br>The options are as follows:<br>• 0: No charge. Only the channel fee of the SP is deducted.<br>• 1: free of charge.<br>• 2: To charge by the number of SMS Messages.<br>• 3: To charge by months.<br>• 4: To charge by upper limit.<br>For inter-network short messages, the value is **2**.<br>For intra-network short messages, the value is blank.<br>This field is reserved in the CBS and is left blank. |
| 33 | CDRType | Char[] | Indicates the CDR type, used in Monternet short messages and inter-network short messages.<br>For inter-network short messages, the options are as follows:<br>• 11: The MO CDR that an inter-network short message interconnects with a short message of China Unicom.<br>• 12: The MT CDR that an inter-network short message interconnects with a short message of China Unicom<br>For inter-network short messages, the value is **11**.<br>For Monternet short messages, the options are as follows:<br>• 1: An MO CDR |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • 2: An MT CDR<br>• 3: Monthly SMS control<br>For intra-network short messages, the value is blank.<br>Can be null. |
| 34 | Discount | Char[] | Indicates the discount and unit is percent.<br>The value **100** indicates no discount.<br>The field **Discount** is valid to inter-network short messages and Monternet SMS Messages. For intra-network short messages, the value is blank.<br>Can be null. |
| 35 | GiftResult | Char[] | Indicates the presentation result.<br>The field **GiftResult** indicates the result of sending an inter-network short message or Monternet short message.<br>For Monternet SMS Messages, the options are as follows:<br>• 0: Failure<br>• 1: Success<br>For intra-network short messages, the value is blank.<br>Can be null. |
| 36 | Subscription-Id-Data | Char[64] | Indicates the end subscriber number. The number is a normalized number containing the country code.<br>Not null. |
| 37 | DiameterSession ID | Char[128] | Format: <DiameterIdentity>;<high>;<low>[;<optional value="">]</optional></low></high></DiameterIdentity><br>• <DiameterIdentity>: The value of this field is the same as the value of Origin-Host.<br>• <high>: Indicates the current system time.<br>• <low>: The value increases cyclically. The initial value is **0**. When the system is restarted, the value is set to **0**. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • <optional value="">: Reserved.<br>Separate each two fields with a semicolon (;).<br>Example: SCP001.huawei.com;1876543210;523<br>Can be null. |
| 38 | NPPrefix | Char[10] | Indicates the NP of called number. It is also called RN prefix.<br>In the SMS interface at Turkey Vodafone, the value maps the value of the **3GPP-IMSI-MCC-MNC** AVP.<br>Can be null. |
| 39 | CalledHomeNetWork | Char[10] | Indicates the home area network code of the called party after NP.<br>Can be null. |
| 40 | OpposeTenantID | Integer | Indicates the home tenant ID of the peer number.<br>Not null. |
| 41 | DCS | Integer | Indicates the mode for encoding the SMS messages to be sent.<br>The options are as follows:<br>• -1: The encoding modes do not need to be differentiated.<br>• 0: 7 bit (English)<br>• 8: UCS2 (Farsi/Other)<br>• 4: Binary code<br>Not null. |
| 42 | NumFormatOfCalling | Integer4 | Calling number type.<br>• 0: Unknown<br>• 1: National<br>• 2: International<br>This field corresponds to the format of **SourceAddr**. The format is normalized by the OCG. Therefore, this field has the fixed value of **2**.<br>Not null. |
| 43 | NumFormatOfCalled | Integer4 | Called number type.<br>• 0: Unknown<br>• 1: National<br>• 2: International |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | This field corresponds to the format of **CalledPartyBCDNu**, which indicates the original target number reported by the MSC.<br>Not null. |
| 44 | NumFormatOfOMSC | Integer4 | Calling number type of roaming MSC.<br>• 0: Unknown<br>• 1: National<br>• 2: International<br>Not null. |
| 45 | NumFormatOfTMSC | Integer4 | Called number type of roaming MSC.<br>• 0: Unknown<br>• 1: National<br>• 2: International<br>Not null. |
| 46 | CalledPartyBCDNu | Char[32] | Original number.<br>The value is the original target number reported by the MSC.<br>Can be null. |
| 47 | OFFLINEFILENAME | Char[32] | Reserved. The field is null. |
| 48 | OFFLINEFILELineNo | Integer4 | Reserved.<br>**NOTE**<br>The type of the field is integer, so the default value is **0**.<br>Not null. |
| 49 | TenantID | Integer | Home BE ID of the charged party.<br>Not null. |
| 50 | Brand | Integer/Char[20] | Brand of the charged party. |
| 51 | CallType | Integer | SMS type. The options are as follows:<br>• 1: national SMS message<br>• 2: international toll SMS message<br>• 3: international roaming SMS message<br>Not null. |
| 52 | OnNetFlag | Char[1] | Network flag.<br>• 0: inter-network |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • 1: intra-network<br>Not null. |
| 53 | Reserved | VARCHAR2[12] | Reserved.<br>Can be null. |
| 54 | Reserved | VARCHAR2[1024] | Reserved.<br>Can be null. |
| 55 | BYPASS_RESULT_CODE | VARCHAR2[10] | Error code for bypass.<br>Can be null. |
| 56 | Calling-Vlr-Number | VARCHAR2[20] | Indicates the VLR number of the visitor location of the calling party.<br>Format: CC + NDC + LSP<br>Can be null. |
| 57 | calling-Cellid | VARCHAR2[36] | Indicates the cell ID of the calling party.<br>Can be null. |
| 58 | Called-Vlr-Number | VARCHAR2[20] | Indicates the VLR number of the visitor location of the called party.<br>Format: CC + NDC + LSP<br>Can be null. |
| 59 | called-Cellid | VARCHAR2[36] | Indicates the cell ID of the called party.<br>Can be null. |
| 60 | IMEI | Char[32] | Mobile phone serial number.<br>This field is reported by the external system, it can be null if not reported.<br>This field is reported only in the CAP4 flow. |

 Copyright © Huawei Technologies Co., Ltd. 

# 4 Charging Output CDRs

## About This Chapter

This topic describes the file storage directories, file name formats, CDR fields, and field sequences of different types of charging output CDRs.

4.1 Basic Information About Charging Output CDRs

This topic describes basic information such as the file name formats and file storage directories of charging output CDRs.

4.2 Charging Output CDR Files

This topic describes charging output CDR files consisting of fixed-length arrays. In these CDR files, field lengths are fixed and the number of complex fields remains unchanged in different service scenarios. This type of CDR file is provided only for the report system.

4.3 Prepaid Transaction CDR Files

This topic describes the CDR file template provided in the baseline version for management flow services. Each site can customize CDR files based on the template.

4.4 Daily Dump Files

This section describes the dump files contents for loan.

## 4.1 Basic Information About Charging Output CDRs

This topic describes basic information such as the file name formats and file storage directories of charging output CDRs.

### 4.1.1 Charging Output CDR Storage Directories

This topic describes the directories for storing CDR files to be imported on the application node CDR2DB in the EDRDB and CDR files generated after CDR sorting. CDR sorting refers to a process of converting original CDR files generated by the CBP to the format required by an external system based on the service requirements.

 Copyright © Huawei Technologies Co., Ltd. 

### Directory for Storing CDR Files to Be Imported

The Mediation collects CDR files generated by the CBP and sends them to the CDR2DB in the EDRDB. You can configure the directory for storing CDR files to be imported by the CDR2DB on the **Invoicing** > **Bill Run Rule** > **Input File Management** page. For example, set the directory to ***$CBP_CDRPATH*/dispatchin/in**.

### Directories for Storing CDR Files Generated After Sorting

- You can configure the directories for storing CDR files generated after successful sorting on the CDR2DB on the **Invoicing** > **Bill Run Rule** > **Output File Management** page. Example:
  - Directory for storing CDR files generated after successful sorting for prepaid subscribers: ***$CBP_CDRPATH***/output/pps/normal
  - Directory for storing CDR files generated after successful sorting for postpaid subscribers: ***$CBP_CDRPATH***/output/pos/normal
- You can configure the directories for storing error CDR files generated after sorting on the CDR2DB on the **Invoicing** > **Bill Run Rule** > **Output File Management** page. Example:
  - Directory for storing error CDR files generated after sorting for prepaid subscribers: ***$CBP_CDRPATH***/output/pps/fail
  - Directory for storing error CDR files generated after sorting for postpaid subscribers: ***$CBP_CDRPATH***/output/pos/fail

**NOTE**

If CDR files that have been read are sent to the directory for storing CDR files to be sorted, they are not processed again and are moved to the ignored CDR file directory. You can configure the directory for storing CDR files that can be ignored on the **Invoicing** > **Bill Run Rule** > **Input File Management** page, for example, ***$CBP_CDRPATH***/dispatchin/ignore.

### Directory for Backing Up Input CDR Files for Sorting

You can configure the directory for backing up input CDR files for sorting on the CDR2DB on the **Invoicing** > **Bill Run Rule** > **Input File Management** page. For example, set the directory to **$CBP_CDRPATH/dispatchin/bak**.

## 4.1.2 Process of Generating Charging Output CDRs

The Mediation periodically obtains CDR files from the CBP and uses SFTP to send them to the application node CDR2DB in the EDRDB for importing and sorting.

The detailed process is described as follows:

1. The Mediation periodically collects CDR files from the CBP and uses SFTP to send them to the directory for storing CDR files to be imported on the application node CDR2DB in the EDRDB. The directory is ***$CBP_CDRPATH*/dispatchin/in**.
2. The CDR2DB sorts the CDR files as follows:
   a. The TSM invokes the scheduled task for sorting CDRs. The controller Cdr2DBAdapter periodically scans **$CBP_CDRPATH/dispatchin/in**. When any CDR files are found, the CDR2DB continues the process.
   b. The sorting service invokes the BOExchange to execute the TXT2BO conversion rule and convert the CDR files to BOs.
   c. The BOExchange sorts and converts the source BOs to target BOs.

d. The BOExchange executes the BO2TXT rule to convert the CDR BOs to CDR files and saves the CDRs generated after successful sorting to **$CBP_CDRPATH/dispatchout/out**.

## 4.1.3 Content Format of a Charging Output CDR File

This topic describes the content format and recording rules of a charging output CDR file.

- A charging output CDR file is stored as a text file.
- CDR fields are separated by vertical bars (|). If a field is empty, no value exists between two consecutive vertical bars, for example, ||.
- To ensure the CDR parsing success, the system escapes some special characters in the CDR file. The escaped special characters are described as follows:
  - **\0x1d**: carriage return (\r)
  - **\0x1e**: line feed (\n)
  - \|: vertical bar (|)
  - \\: backslash (\)
  - \{: left brace ({)
  - \}: right brace (})

## 4.1.4 File Name Format of Charging Output CDRs

This topic describes the file name format of sorted charging output CDRs.

### Description

Charging output CDR files are named in the format **{File Name Prefix}+{File Name Pattern}+{File Name Suffix}**. You can configure the file names using **File Name Prefix**, **File Name Pattern**, and **File Name Postfix** on the **Invoicing** > **Bill Run Rule** > **Output File Management** page.

If **File Name Pattern** is set to ***CDR type abbreviation*_$<DATE8>_$<NODEID>_$<BEID>_$<SNO6>**, the CDR file is named in the following format: {File Name Prefix}+{CDR type abbreviation}+{YYYYMMDD}+{_}+{NODEID}+{_}+{BEID}+{_}+{Six-digit sequence number}+{File Name Suffix}.

Table 4-1 describes the fields in the file name format for charging output CDRs.

**Table 4-1** Fields in the file name format for charging output CDRs

| Field | Description |
|---|---|
| File Name Prefix | Prefix of the CDR file name, for example, **rec_**. |
| SNO6 | Six-digit sequence number assigned to a CDR file on a certain day. |
| SNO3 | Three-digit sequence number assigned to a CDR file on a certain day. |
| DATE6 | Month in which a CDR file is generated, in the format *YYYYMM*. |

 Copyright © Huawei Technologies Co., Ltd. 

| Field | Description |
|---|---|
| DATE8 | Date on which a CDR file is generated, in the format *YYYYMMDD*. |
| TIME6 | CDR file generation time, in the format *HHMMSS*. |
| TIMEE | CDR file generation time, in the format *YYYYMMDDHHMMSS*. |
| _ | Underscore. |
| NODEID | Data node to which the charged object belongs. |
| CPID | Customer partition ID. |
| SRCNAME | Name of the source CDR file corresponding to the charging output CDR file. |
| BEID | BE ID. |
| File Name Suffix | Suffix of the CDR file name, for example, **.unl** or **.add**. |

## 4.1.5 Charging Output CDR Types

This topic describes the types of sorted charging output CDRs and the CDR generation scenarios.

Table 4-2 lists the charging output CDR types.

**Table 4-2** Charging output CDR types

| CDR Type | CDR Generation Scenario | Default CDR File Name |
|---|---|---|
| Voice CDR | The voice CDR records rating and charging information generated by the charging module in a voice call process, in addition to service scenario information reported by the call control component. | cbs_cdr_voice_YYYYMMDD_$<NodeID>_$<BEID>_$<SNO6>.add |
| SMS CDR | The SMS CDR records rating and charging information generated by the charging module in an SMS service process, in addition to service scenario information reported by an external NE. | cbs_cdr_sms_YYYYMMDD_$<NodeID>_$<BEID>_$<SNO6>.add |
| MMS CDR | The MMS CDR records rating and charging information generated by the charging module in an | cbs_cdr_mms_YYYYMMDD_$<NodeID>_$<BEID>_$<SNO6>.add |

 Copyright © Huawei Technologies Co., Ltd. 

| CDR Type | CDR Generation Scenario | Default CDR File Name |
|---|---|---|
| | MMS service process, in addition to service scenario information reported by an external NE. | |
| GPRS CDR | The GPRS CDR records rating and charging information generated by the charging module in a GPRS service process, in addition to service scenario information reported by an external NE. | cbs_cdr_data_YYYYMMDD_$<NodeID>_$<BEID>_$<SNO6>.add |
| Recurring charging CDR | The recurring charging CDR records recurring charges, including the rental, package fee, and subsequent installment rebates. | cbs_cdr_mon_YYYYMMDD_$<NodeID>_$<BEID>_$<SNO6>.add |
| Management CDR | The management CDR records one-off fees deducted in the management flow. | cbs_cdr_cm_YYYYMMDD_$<NodeID>_$<BEID>_$<SNO6>.add |
| Content CDR | The content CDR records content-based charging information (rated by the CBS or an external system) and one-off fees reported by external systems. | cbs_cdr_com_YYYYMMDD_$<NodeID>_$<BEID>_$<SNO6>.add |
| CLR CDR | The CLR CDR is generated during resource clearance for deregistered subscribers. | cbs_cdr_clr_YYYYMMDD_$<NodeID>_$<BEID>_$<SNO6>.add |
| Activation CDR | The activation CDR is generated when a prepaid subscriber is activated the first time. | cbs_cdr_first_YYYYMMDD_$<NodeID>_$<BEID>_$<SNO6>.add |
| Recharge CDR | The recharge CDR records the cash or voucher recharge information such as the information about the voucher, and change of the validity period and account after the recharge. The information about the rewards that are obtained immediately after the recharge is recorded in the recharge CDR. Other cycles of the installment rebate are | cbs_cdr_vou_YYYYMMDD_$<NodeID>_$<BEID>_$<SNO6>.add |

 Copyright © Huawei Technologies Co., Ltd. 

| CDR Type | CDR Generation Scenario | Default CDR File Name |
|---|---|---|
| | recorded in the periodic fee CDRs. | |
| Transfer CDR | The transfer CDR is generated upon transfer transactions. | cbs_cdr_transfer_YYYYMMDD_$<NodeID>_$<BEID>_$<SNO6>.add |
| Adjustment CDR | The adjustment CDR is generated upon adjustment transactions. | cbs_cdr_adj_YYYYMMDD_$<NodeID>_$<BEID>_$<SNO6>.add |
| Switch Primary Offering CDR | Switch Primary Offering CDR is generated when primary offering is switched. | SwitchPO_$<BEID>_YYYYMMDDHHMMSS_$<SNO6>.unl |
| Loan CDR | The loan CDR records the information about the loan information of a subscriber. | cbs_cdr_loan_$<AppNodeID>_$<DataNodeID>_$<BEID>_YYYYMMDDHHMMSS_$<SNO5>.add |

# 4.2 Charging Output CDR Files

This topic describes charging output CDR files consisting of fixed-length arrays. In these CDR files, field lengths are fixed and the number of complex fields remains unchanged in different service scenarios. This type of CDR file is provided only for the report system.

## 4.2.1 Common Fields in a Charging Output CDR File

This topic describes common fields in sorted charging output CDRs of various services in the baseline version. The number and meanings of these CDR fields are almost fixed. Fields that sites can expand are marked in this topic.

The last field **CHARGE_SERVICE_INFO** in charging output CDR files is provided for sites to expand. Sites can expand fields of a specific number for different services. The expanded fields can be added only to the **CHARGE_SERVICE_INFO** field. Generally, each CDR file has only one group of **CHARGE_SERVICE_INFO**. In baseline CDR files, basic extended fields are provided for **CHARGE_SERVICE_INFO** if services need to be differentiated. For details, see the 4.2.2 Extended Charging Service Information.

Table 4-3 describes common fields in a charging output CDR file.

### CDR File Format

**Table 4-3** Common fields in a charging output CDR file

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 1 | CDR_ID | NUMBER[20] | CDR ID. The ID is automatically generated by the sequencer.<br>This field cannot be left empty. | The first 32 fields record basic information in CDR files. The length of these fields is fixed. The 24th, 25th, and 32nd fields can be customized based on the site requirements. Other fields are inextensible. |
| 2 | CDR_SUB_ID | NUMBER[20] | ID of a sub CDR generated after CDR splitting.<br>If a CDR is not split, the field is set to **0**. If a CDR is split, the sub CDRs are sequentially identified by numbers 1, 2, and so on.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 3 | CDR_TYPE | VARCHAR2[1] | CDR type. The options are as follows:<br>• **N**: normal CDR<br>• **E**: error CDR<br>• **R**: recycling CDR<br>This field cannot be left empty. | |
| 4 | SPLIT_CDR_REASON | VARCHAR2[1] | Reason to split a CDR. The options are as follows:<br>• **N**: A CDR is not split. This is the default value.<br>• **L**: The call duration reaches the CDR splitting threshold. The CDR will be split into several CDRs with different CDR IDs.<br>• **B**: The current call straddles two bill cycles. The CDR will be split into two CDRs with different CDR IDs.<br>• **D**: The current call straddles two days. The CDR is split into two independent CDR IDs.<br>• **A**: The number of AC messages reaches the threshold.<br>• **V**: The traffic usage reaches the threshold, in bytes.<br>This field cannot be left empty. | |
| 5 | CDR_BATCH_ID | NUMBER[20] | Batch ID of a CDR.<br>For offline charging, set the field to the offline charging task ID. For online charging, set the field in the *YYYYMMDDHHmm* format. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | The default value is **0**.<br>This field cannot be left empty. | |
| 6 | SRC_REC_LINE_NO | NUMBER[10] | Original record line number.<br>Set this field to **0** for online charging or the CDR line number for offline charging.<br>This field cannot be left empty. | |
| 7 | SRC_CDR_ID | NUMBER[20] | Original ID of a CDR to be rerated.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 8 | SRC_CDR_NO | NUMBER[20] | Sequence number of the original CDR.<br>The value starts from **0** and the default value is **0**, indicating that the CDR is not split.<br>If the CDR is split into sub CDRs with different CDR IDs, the field is set to the **CDR_ID** value of the original CDR, indicating that the split sub CDRs belong to the same session.<br>This field cannot be left empty.<br>This field is reserved. | |
| 9 | STATUS | VARCHAR2[1] | CDR status. The options are as follows:<br>• **A**: valid<br>• **D**: invalid, reserved<br>This field has a fixed value of **A**.<br>This field cannot be left empty. | |
| 10 | RE_RATING_TIMES | NUMBER[3] | Number of times that a CDR is rerated.<br>If a CDR is not rerated, set the field to **0**.<br>This field cannot be left empty. | |
| 11 | CREATE_DATE | DATE[14] | UTC time in the system when a CDR is created.<br>This field cannot be left empty. | |
| 12 | START_DATE | DATE[14] | UTC time when a service starts.<br>This field cannot be left empty. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 13 | END_DATE | DATE[14] | UTC time when a service ends.<br>This field cannot be left empty. | |
| 14 | CUST_LOCAL_START_DATE | DATE[14] | Local time when a service starts.<br>This field cannot be left empty. | |
| 15 | CUST_LOCAL_END_DATE | DATE[14] | Local time when a service ends.<br>This field cannot be left empty. | |
| 16 | STD_EVT_TYPE_ID | NUMBER[10] | Standard charging event type ID.<br>For example, value **11000** indicates the voice online charging event. The options can be expanded. For details, see configurations on the CBS GUI.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 17 | EVT_SOURCE_CATEGORY | VARCHAR2[1] | Event source type. The options are as follows:<br>• **C**: offline charging request<br>• **D**: Diameter charging request<br>• **M**: management charging request<br>• **S**: system-triggered charging request, for example, recurring charging<br>This field cannot be left empty. | |
| 18 | OBJ_TYPE | VARCHAR2[1] | Type of the charged party. The options are as follows:<br>• **A**: account<br>• **C**: customer<br>• **S**: subscriber<br>• **G**: subscriber group<br>This field cannot be left empty. | |
| 19 | OBJ_ID | NUMBER[20] | ID of the charged party.<br>Set this field based on the **OBJ_TYPE** value.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 20 | OWNER_CUST_ID | NUMBER[20] | Registrant ID of the charged party.<br>The default value is **0**.<br>This field cannot be left empty. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 21 | DEFAULT_ACCT_ID | NUMBER[20] | Default account ID of the charged party.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 22 | PRI_IDENTITY | VARCHAR2[64] | Subscriber primary identifier.<br>In rental events where the subscriber number does not exist, for example, account, customer, and subscriber group rental events, this field can be left empty.<br>• If a primary identifier is an MSISDN or a PSTN, this field is set in the format **Country code + MSISDN** or **Country code + Area code + PSTN**.<br>• If a primary identifier is of other types, the value is the number that is transferred. | |
| 23 | BILL_CYCLE_ID | VARCHAR2[20] | Bill cycle ID of the default account corresponding to the charged party when a charging event occurs. | |
| 24 | SERVICE_CATEGORY | VARCHAR2[10] | Service type. The field can be customized. The example options are as follows:<br>• **1**: voice<br>• **2**: SMS<br>• **3**: MMS<br>• **4**: one-off fee deduction<br>• **5**: GPRS charging<br>• **6**: content-based charging<br>• **7**: recurring fee<br>• **8**: service processed on the management foreground<br>This field can be left empty. | |
| 25 | USAGE_SERVICE_TYPE | VARCHAR2[10] | Service subtype. The field can be customized.<br>The subtypes vary according to site, and the value is obtained from the charging event attribute.<br>The example options are as follows:<br>• **10**: local intra-network call<br>• **11**: local inter-network call | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **12**: national toll call<br>• **13**: international toll call<br>• **14**: national roaming call<br>• **15**: international roaming call<br>• **21**: intra-network SMS<br>• **22**: inter-network SMS<br>• **23**: special number SMS<br>• **24**: international SMS<br>• **25**: intra-network MMS<br>• **26**: inter-network MMS<br>• **27**: international MMS<br>• **31**: local data service<br>• **33**: roaming data service<br>• **4**: rental<br>• **5**: content-based charging<br>This field can be left empty. | |
| 26 | SESSION_ID | VARCHAR2[128] | Session ID.<br>In events such as rental events, this field can be left empty.<br>• For sessions in online charging, set the field to the session ID reported in a DCC message.<br>• For sessions in offline charging, set the field to the combination of the batch ID, original CDR file ID specified by **SRC_CDR_ID**, and source event ID.<br>• For sessions generated in other service management systems (such as the Billing Configurator and AR), set the field to the service sequence number. | |
| 27 | RESULT_CODE | NUMBER[10] | Internal result code.<br>• **0**: success<br>• Others: failure<br>This field cannot be left empty. | |
| 28 | RESULT_REASON | VARCHAR2[256] | Reason why a service ends.<br>This field is reserved. | |
| 29 | BE_ID | NUMBER[10] | ID of the lowest-level home BE of the charged object. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | The default value is **0**.<br>This field cannot be left empty. | |
| 30 | HOT_SEQ | NUMBER[10] | Sequence number of a CDR generated in bill on demand.<br>This field is set to the sequence number of the task for bill on demand in recurring charging CDRs and is set to **0** in other scenarios.<br>This field cannot be left empty. | |
| 31 | CP_ID | NUMBER[10] | Customer partition ID.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 32 | RECIPIENT_NUMBER | VARCHAR2[64] | Recipient number, which can be customized by a carrier.<br>For account, customer, and subscriber group rental events and GPRS events, this field can be left empty.<br>The number formats are as follows:<br>• If the recipient number is an MSISDN or a PSTN, this field is set in the format **Country code + MSISDN** or **Country code + Area code + PSTN**.<br>• When the recipient number is of other types, the value is the number that is transferred. | |
| 33 | USAGE_MEASURE_ID | NUMBER[10] | Service usage measurement unit ID.<br>For example, value **1003** indicates second. The options can be expanded. For details, see configurations on the CBS GUI. | The 33rd to 36th fields record the service usage of the first type in the charging process. If |
| 34 | ACTUAL_USAGE | NUMBER[20] | Actual service usage. | |
| 35 | RATE_USAGE | NUMBER[20] | Rated service usage. | |
| 36 | SERVICE_UNIT_TYPE | NUMBER[10] | Service usage type.<br>• **1**: duration<br>• **2**: traffic<br>• **3**: item<br>• **4**: currency | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **5**: times<br>• **6**: page<br>• **7**: special service type | no service usage is triggered in a service, such as rental collection and activation, these fields are set to **0** by default. |
| 37 | USAGE_MEASURE_ID2 | NUMBER[10] | Service usage measurement unit ID.<br>The default value is **0**. | The 37th to 40th fields record the service usage of the second type in the charging process. These fields are reserved currently |
| 38 | ACTUAL_USAGE2 | NUMBER[20] | Actual service usage.<br>The default value is **0**. | |
| 39 | RATE_USAGE2 | NUMBER[20] | Rated service usage.<br>The default value is **0**. | |
| 40 | SERVICE_UNIT_TYPE2 | NUMBER[10] | Service usage type.<br>The default value is **0**. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | and have a fixed value of **0**. |
| 41 | DEBIT_AMOUNT | NUMBER[20] | Actual amount that is deducted, which includes the amount deducted from prepaid main funds, bonuses, postpaid credits, and prepayments of all accounts (including payment accounts) used in a transaction but excludes the undebited amount. | The 41st to 48th fields record total funds (excluding bonuses) used in the charging process. |
| 42 | UN_DEBIT_AMOUNT | NUMBER[20] | Undebited amount. This field indicates the fee that is not debited when the balance is deducted to zero (that is, when the account balance is insufficient) in the case of prorated charging. | |
| 43 | DEBIT_FROM_PREPAID | NUMBER[20] | Total amount deducted from prepaid main funds and bonuses of all prepaid accounts, including payment accounts. | |
| 44 | DEBIT_FROM_ADVANCE_PREPAID | NUMBER[20] | Total amount deducted from prepaid main funds of all prepaid accounts, including payment accounts. | |
| 45 | DEBIT_FROM_POSTPAID | NUMBER[20] | Total amount deducted from credits, bonuses, deposits, and prepayments of all postpaid accounts, including payment accounts. | |
| 46 | DEBIT_FROM_ADVANCE_POSTPAID | NUMBER[20] | Total amount deducted from prepayments of all postpaid accounts, including payment accounts. | |
| 47 | DEBIT_FROM_CREDIT_POSTPAID | NUMBER[20] | Total amount deducted from credits of all postpaid accounts, including payment accounts. | |
| 48 | TOTAL_TAX | NUMBER[20] | Total tax amount. | |
| 49 | FREE_UNIT_AMOUNT_OF_TIMES | NUMBER[20] | Usage of free units that are charged by times. | The 49th to 51st fields record total free |
| 50 | FREE_UNIT_AMOUNT_OF_DURATION | NUMBER[20] | Usage of free units that are charged by duration.<br>The duration unit is defined by the | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | system. Generally, the unit is second. | units used in the charging process, excluding the rewarded free units. |
| 51 | FREE_UNIT_AMOUNT_OF_FLUX | NUMBER[20] | Usage of free units that are charged by traffic.<br>The traffic unit is defined by the system. Generally, the unit is byte. | |
| 52 | ACCT_ID | NUMBER[20] | Payment account ID. | The 52nd to 121st fields record 10 groups of balance change in the charging process, excluding the rewarded balance change.<br>The 52nd to 58th fields record the first group |
| 53 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 54 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 55 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 56 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 57 | CURRENCY_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 58 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | of balance change information. If *N* balance changes are involved, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 59 | ACCT_ID | NUMBER[20] | Account ID. | The 52nd to 121st fields record 10 groups of balance change in |
| 60 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 61 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 62 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 63 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 64 | CURRENCY_ | NUMBER[10] | Currency type ID. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | ID | | | the charging process, excluding the rewarded balance change. The 59th to 65th fields record the second group of balance change information. If *N* balance changes are involved, the first *N* groups of balance change fields are recorded and |
| 65 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | other groups of fields are left empty. |
| 66 | ACCT_ID | NUMBER[20] | Account ID. | The 52nd to 121st fields record 10 groups of balance change in the charging process, excluding the rewarded balance change. The 66th to 72nd fields record the third group of balance change information |
| 67 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 68 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 69 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 70 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 71 | CURRENCY_ID | NUMBER[10] | Currency type ID. | |
| 72 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | n. If *N* balance changes are involved, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 73 | ACCT_ID | NUMBER[20] | Account ID. | The 52nd to 121st fields record 10 groups of balance change in the charging process, excluding the |
| 74 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 75 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 76 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 77 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 78 | CURRENCY_ID | NUMBER[10] | Currency type ID. | |
| 79 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | rewarded balance change. The 73rd to 79th fields record the fourth group of balance change information. If *N* balance changes are involved, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 80 | ACCT_ID | NUMBER[20] | Account ID. | The 52nd to 121st fields record 10 groups of balance change in the charging process, excluding the rewarded balance change. The 80th to 86th fields record the fifth group of balance change information. If *N* balance changes are involved, the |
| 81 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 82 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 83 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 84 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 85 | CURRENCY_ID | NUMBER[10] | Currency type ID. | |
| 86 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 87 | ACCT_ID | NUMBER[20] | Account ID. | The 52nd to 121st fields record 10 groups of balance change in the charging process, excluding the rewarded balance change. The 87th to 93rd |
| 88 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 89 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 90 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 91 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 92 | CURRENCY_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 93 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | fields record the sixth group of balance change information. If *N* balance changes are involved, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 94 | ACCT_ID | NUMBER[20] | Account ID. | The 52nd to 121st fields record 10 groups of |
| 95 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 96 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 97 | CUR_BALANCE | NUMBER[20] | Current balance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 98 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | balance change in the charging process, excluding the rewarded balance change. The 94th to 100th fields record the seventh group of balance change information. If *N* balance changes are involved, the first *N* groups of balance change fields |
| 99 | CURRENCY_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 100 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | are recorded and other groups of fields are left empty. |
| 101 | ACCT_ID | NUMBER[20] | Account ID. | The 52nd to 121st fields record 10 groups of balance change in the charging process, excluding the rewarded balance change. The 101st to 107th fields record the eighth group of balance |
| 102 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 103 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 104 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 105 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 106 | CURRENCY_ID | NUMBER[10] | Currency type ID. | |
| 107 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | change information. If *N* balance changes are involved, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 108 | ACCT_ID | NUMBER[20] | Account ID. | The 52nd to 121st fields record 10 groups of balance change in the charging proce |
| 109 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 110 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 111 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 112 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 113 | CURRENCY_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 114 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows: | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | ss, excluding the rewarded balance change. The 108th to 114th fields record the ninth group of balance change information. If *N* balance changes are involved, the first *N* groups of balance change fields are recorded and other groups of fields are |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | left empty. |
| 115 | ACCT_ID | NUMBER[20] | Account ID. | The 52nd to 121st fields record 10 groups of balance change in the charging process, excluding the rewarded balance change. The 115th to 121st fields record the tenth group of balance change information. If *N* balance chang |
| 116 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 117 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 118 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 119 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 120 | CURRENCY_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 121 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | es are involved, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 122 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type.<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 122nd to 201st fields record 10 groups of free unit change in the charging process, excluding the change of free units that |
| 123 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 124 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 125 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 126 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 127 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 128 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 129 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows: | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | are rewarded and rolled over. The 122nd to 129th fields record the first group of free unit change information. If *N* free unit changes are involved, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 130 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type.<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 122nd to 201st fields record 10 groups of free unit change in the charging process, excluding the change of free units that are rewarded and rolled over. The 130th to 137th fields record the second group of free unit change information. If *N* free |
| 131 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 132 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 133 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 134 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 135 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 136 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 137 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | unit changes are involved, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 138 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type.<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 122nd to 201st fields record 10 groups of free unit change in the charging process, excluding the change of free |
| 139 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 140 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 141 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 142 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 143 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 144 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 145 | OPER_TYPE | NUMBER[10] | Operation type. The options are as | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | units that are rewarded and rolled over. The 138th to 145th fields record the third group of free unit change information. If *N* free unit changes are involved, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | . |
| 146 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type.<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 122nd to 201st fields record 10 groups of free unit change in the charging process, excluding the change of free units that are rewarded and rolled over. The 146th to 153rd fields record the fourth group of free unit change information. If |
| 147 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 148 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 149 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 150 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 151 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 152 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 153 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | *N* free unit changes are involved, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 154 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type.<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 122nd to 201st fields record 10 groups of free unit change in the charging process, excluding the change of |
| 155 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 156 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 157 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 158 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 159 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 160 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 161 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | free units that are rewarded and rolled over. The 154th to 161st fields record the fifth group of free unit change information. If *N* free unit changes are involved, the first *N* groups of free unit change fields are recorded and other groups of fields are left |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | empty. |
| 162 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type.<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 122nd to 201st fields record 10 groups of free unit change in the charging process, excluding the change of free units that are rewarded and rolled over. The 162nd to 169th fields record the sixth group of free unit change information |
| 163 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 164 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 165 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 166 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 167 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 168 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 169 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | n. If *N* free unit changes are involved, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 170 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type.<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 122nd to 201st fields record 10 groups of free unit change in the charging process, excluding the chang |
| 171 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 172 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 173 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 174 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 175 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 176 | FU_MEASUR | NUMBER[10] | Free unit measurement unit ID. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | E_ID | | | e of free units that are rewarded and rolled over. The 170th to 177th fields record the seventh group of free unit change information. If *N* free unit changes are involved, the first *N* groups of free unit change fields are recorded and other groups of fields |
| 177 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | are left empty. |
| 178 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type.<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 122nd to 201st fields record 10 groups of free unit change in the charging process, excluding the change of free units that are rewarded and rolled over. The 178th to 185th fields record the eighth group of free unit change |
| 179 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 180 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 181 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 182 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 183 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 184 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 185 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | information. If *N* free unit changes are involved, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 186 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type.<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 122nd to 201st fields record 10 groups of free unit change in the charging process, excluding |
| 187 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 188 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 189 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 190 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 191 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 192 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | the change of free units that are rewarded and rolled over. The 186th to 193rd fields record the ninth group of free unit change information. If *N* free unit changes are involved, the first *N* groups of free unit change fields are recorded and other groups of |
| 193 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | fields are left empty. |
| 194 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type.<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 122nd to 201st fields record 10 groups of free unit change in the charging process, excluding the change of free units that are rewarded and rolled over. The 194th to 201st fields record the tenth group of free unit chang |
| 195 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 196 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 197 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 198 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 199 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 200 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 201 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | e information. If *N* free unit changes are involved, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 202 | ACCT_ID | NUMBER[20] | Account ID. | The 202nd to 271st fields record 10 groups of bonus details in the charging process, excluding |
| 203 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | |
| 204 | BALANCE_TYPE | NUMBER[20] | Balance type. | |
| 205 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |
| 206 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | |
| 207 | CURRENCY_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 208 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | the bonus that is rewarded or rolled over. The 202nd to 208th fields record the first group of bonus details. If *N* bonuses are involved, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 209 | ACCT_ID | NUMBER[20] | Account ID. | The 202nd to 271st fields record |
| 210 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | |
| 211 | BALANCE_TYPE | NUMBER[20] | ID of a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 212 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | 10 groups of bonus details in the charging process, excluding the bonus that is rewarded or rolled over. The 209th to 215th fields record the second group of bonus details. If *N* bonuses are involved, the first *N* groups of bonus details fields are recorded and other |
| 213 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | |
| 214 | CURRENCY_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 215 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | groups of fields are left empty. |
| 216 | ACCT_ID | NUMBER[20] | Account ID. | The 202nd to 271st fields record 10 groups of bonus details in the charging process, excluding the bonus that is rewarded or rolled over. The 216th to 222nd fields record the third group of bonus details. If *N* bonuses are involved, |
| 217 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | |
| 218 | BALANCE_TYPE | NUMBER[20] | Balance type. | |
| 219 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |
| 220 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | |
| 221 | CURRENCY_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 222 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 223 | ACCT_ID | NUMBER[20] | Account ID. | The 202nd to 271st fields record 10 groups of bonus details in the charging process, excluding the bonus that is rewarded or rolled over. The 223rd to 229th |
| 224 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | |
| 225 | BALANCE_TYPE | NUMBER[20] | Balance type. | |
| 226 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |
| 227 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | |
| 228 | CURRENCY_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 229 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | fields record the fourth group of bonus details. If *N* bonuses are involved, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 230 | ACCT_ID | NUMBER[20] | Account ID. | The 202nd to 271st fields record 10 groups of bonus details in the charging process, |
| 231 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | |
| 232 | BALANCE_TYPE | NUMBER[20] | Balance type. | |
| 233 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |
| 234 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | |
| 235 | CURRENCY_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 236 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows: | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | excluding the bonus that is rewarded or rolled over. The 230th to 236th fields record the fifth group of bonus details. If *N* bonuses are involved, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 237 | ACCT_ID | NUMBER[20] | Account ID. | The 202nd to 271st |
| 238 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 239 | BALANCE_TYPE | NUMBER[20] | Balance type. | fields record 10 groups of bonus details sixth group of granted bonus in the charging process, excluding the bonus that is rewarded or rolled over. The 237th to 243rd fields record the sixth group of bonus details. If *N* bonuses are involved, the first *N* groups of bonus detail |
| 240 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |
| 241 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | |
| 242 | CURRENCY_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 243 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | s fields are recorded and other groups of fields are left empty. |
| 244 | ACCT_ID | NUMBER[20] | Account ID. | The 202nd to 271st fields record 10 groups of bonus details in the charging process, excluding the bonus that is rewarded or rolled over. The 244th to 250th fields record the seventh group |
| 245 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | |
| 246 | BALANCE_TYPE | NUMBER[20] | Balance type. | |
| 247 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |
| 248 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | |
| 249 | CURRENCY_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 250 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | of bonus details. If *N* bonuses are involved, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 251 | ACCT_ID | NUMBER[20] | Account ID. | The 202nd to 271st fields record 10 groups of bonus details in the charging process, excluding the bonus that is |
| 252 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | |
| 253 | BALANCE_TYPE | NUMBER[20] | Balance type. | |
| 254 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |
| 255 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | |
| 256 | CURRENCY_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 257 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | rewarded or rolled over. The 251st to 257th fields record the eighth group of bonus details. If *N* bonuses are involved, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 258 | ACCT_ID | NUMBER[20] | Account ID. | The 202nd to 271st fields record 10 groups of |
| 259 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | |
| 260 | BALANCE_TYPE | NUMBER[20] | ID of a balance account. | |
| 261 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 262 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | bonus details in the charging process, excluding the bonus that is rewarded or rolled over. The 258th to 264th fields record the ninth group of bonus details. If *N* bonuses are involved, the first *N* groups of bonus details fields are recorded and other groups of fields are |
| 263 | CURRENCY_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 264 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | left empty. |
| 265 | ACCT_ID | NUMBER[20] | Account ID. | The 202nd to 271st fields record 10 groups of bonus details in the charging process, excluding the bonus that is rewarded or rolled over. The 265th to 271st fields record the tenth group of bonus details. If *N* bonuses are involved, the first *N* groups of |
| 266 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | |
| 267 | BALANCE_TYPE | NUMBER[20] | ID of a balance account. | |
| 268 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |
| 269 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | |
| 270 | CURRENCY_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 271 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | bonus details fields are recorded and other groups of fields are left empty. |
| 272 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 272nd to 351st fields record 10 groups of free unit reward details in the charging process, including the free unit that is rewarded and rolled over. The 272nd to |
| 273 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 274 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 275 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 276 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 277 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 278 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 279 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | 279th fields record the first group of free unit reward details. If *N* free unit rewards are involved, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 280 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 272nd to 351st fields record 10 group |
| 281 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 282 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | s of free unit reward details in the charging process, including the free unit that is rewarded and rolled over. The 280th to 287th fields record the second group of free unit reward details. If *N* free unit rewards are involved, the first *N* groups of free |
| 283 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 284 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 285 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 286 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 287 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | unit reward details fields are recorded and other groups of fields are left empty. |
| 288 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 272nd to 351st fields record 10 groups of free unit reward details in the charging process, including the free unit that is rewarded and rolled over. The |
| 289 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 290 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 291 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 292 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 293 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 294 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 295 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | 288th to 295th fields record the third group of free unit reward details. If *N* free unit rewards are involved, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 296 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 272nd to 351st fields record |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 297 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | 10 groups of free unit reward details in the charging process, including the free unit that is rewarded and rolled over. The 296th to 303rd fields record the fourth group of free unit reward details. If *N* free unit rewards are involved, the first *N* groups of |
| 298 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 299 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 300 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 301 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 302 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 303 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | free unit reward details fields are recorded and other groups of fields are left empty. |
| 304 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 272nd to 351st fields record 10 groups of free unit reward details in the charging process, including the free unit that is rewarded and rolled over. |
| 305 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 306 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 307 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 308 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 309 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 310 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 311 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | The 304th to 311st fields record the fifth group of free unit reward details. If *N* free unit rewards are involved, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 312 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group | The 272nd to 351st |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **C**: customer | fields record 10 groups of free unit reward details in the charging process, including the free unit that is rewarded and rolled over. The 312nd to 319th fields record the sixth group of free unit reward details. If *N* free unit rewards are involved, the first *N* |
| 313 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 314 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 315 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 316 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 317 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 318 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 319 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 320 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 272nd to 351st fields record 10 groups of free unit reward details in the charging process, including the free unit that is rewarded and |
| 321 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 322 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 323 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 324 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 325 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 326 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 327 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | rolled over. The 320th to 327th fields record the seventh group of free unit reward details. If *N* free unit rewards are involved, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 328 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows: | The 272nd |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | to 351st fields record 10 groups of free unit reward details in the charging process, including the free unit that is rewarded and rolled over. The 328th to 335th fields record the eighth group of free unit reward details. If *N* free unit rewards are involved, |
| 329 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 330 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 331 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 332 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 333 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 334 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 335 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 336 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 272nd to 351st fields record 10 groups of free unit reward details in the charging process, including the free unit that is rewar |
| 337 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 338 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 339 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 340 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 341 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 342 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 343 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **5**: Add free units to an existing free unit instance. | ded and rolled over. The 336th to 343rd fields record the ninth group of free unit reward details. If *N* free unit rewards are involved, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 344 | FU_OWN_TY | VARCHAR2[ | Free unit owner type. The options are | The |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | PE | 1] | as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | 272nd to 351st fields record 10 groups of free unit reward details in the charging process, including the free unit that is rewarded and rolled over. The 344th to 351st fields record the tenth group of free unit reward details. If *N* free unit rewards are involv |
| 345 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 346 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 347 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 348 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 349 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 350 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 351 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | ed, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| - | CHARGE_SERVICE_INFO | STRING[2048] | Charging service information. | The **CHARGE_SERVICE_INFO** field is a complex field recording charging service information. This field can be exten |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | ded for each service to meet site requirements. For the basic extended information in baseline CDR files, see 4.2.2 Extended Charging Service Information. |

## 4.2.2 Extended Charging Service Information

This topic describes the charging service fields extended in baseline CDR files. Each site can customize more extended fields based on the site requirements.

### 4.2.2.1 Extended Charging Service Information in a Voice CDR

This topic describes extended fields in the charging service information in a voice CDR.

Table 4-4 describes extended fields in the charging service information in a voice CDR.

**Table 4-4** Extended charging service information in a voice CDR

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 352 | CallingPartyNu | VARCHAR2[64 | Calling number. |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | mber | ] | The number formats are as follows:<br>• Fixed-line number: Country code + Area code + PSTN<br>• Mobile number: Country code + MSISDN<br>• URI format: number reported by the network side<br>Generally, this field cannot be left empty. This field is left empty in scenarios where the calling number is not differentiated in the MT process. In these scenarios, the network side may not report the calling number. |
| 353 | CalledPartyNumber | VARCHAR2[64] | Called number.<br>The number formats are as follows:<br>• Fixed-line number: Country code + Area code + PSTN<br>• Mobile number: Country code + MSISDN<br>• URI format: number reported by the network side<br>This field cannot be left empty. |
| 354 | CallingPartyIMSI | VARCHAR2[64] | IMSI of the calling party. The value is reported by the network side. If no value is reported, this field is left empty.<br>If the value comes in DCC message that value will be stored in CDR. If no value was sent, then the DB value will be stored in CDR.<br>This field can be left empty. |
| 355 | CalledPartyIMSI | VARCHAR2[64] | IMSI of the called party. The value is reported by the network side. If no value is reported, this field is left empty.<br>This field can be left empty. |
| 356 | DialedNumber | VARCHAR2[64] | Number that is dialed.<br>The value is reported by the network side in the MO process. If no value is reported, this field is left empty. The value can be in any format.<br>This field can be left empty. |
| 357 | OriginalCalledParty | VARCHAR2[64] | Original called number in the MF process.<br>The number formats are as follows:<br>• Fixed-line number: Country code + Area code + PSTN |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • Mobile number: Country code + MSISDN<br>• URI format: number reported by the network side<br>This field can be left empty. |
| 358 | ServiceFlow | VARCHAR2[1] | Call process ID. The options are as follows:<br>• **1**: MO<br>• **2**: MT<br>• **3**: MF<br>This field cannot be left empty. |
| 359 | CallForwardIndicator | VARCHAR2[2] | Call forwarding flag. The options are as follows:<br>• **00**: no call forwarding<br>• **10**: call forwarding conditional due to an unknown reason<br>• **11**: call forwarding busy<br>• **12**: call forwarding no reply<br>• **13**: call forwarding unreachable<br>• **14**: call forwarding power-off<br>• **20**: call forwarding unconditional<br>• **21**: call forwarded to a voice mailbox<br>• **22**: international call forwarding<br>This field cannot be left empty. |
| 360 | CallingRoamInfo | VARCHAR2[20] | Roaming information about the calling party.<br>This field is used to analyze the calling party's roaming status and can be set to the value of fields such as **LocationNumber**, **MSCAddress**, or **VLRNumber**. The value depends on the control parameter specifying the roaming analysis method.<br>This field can be left empty. |
| 361 | CallingCellID | VARCHAR2[20] | Cell ID of the calling party, which is reported in an IDP message.<br>If the CBS does not need to analyze the visited area based on the cell ID, this field can be left empty.<br>The format is Three-digit MCC + Two-digit MNC + Five-digit LAC + Five-digit cell ID, for example, **460002230320412**. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 362 | CalledRoamInfo | VARCHAR2[20] | Roaming information about the called party.<br>This field is used to analyze the called party's roaming status and can be set to the value of fields such as **LocationNumber**, **MSCAddress**, or **VLRNumber**. The value depends on the control parameter specifying the roaming analysis method.<br>This field can be left empty. |
| 363 | CalledCellID | VARCHAR2[20] | Cell ID of the called party.<br>If the CBS does not need to analyze the visited area based on the cell ID, this field can be left empty.<br>The format is Three-digit MCC + Two-digit MNC + Five-digit LAC + Five-digit cell ID, for example, **460002230320412**. |
| 364 | TimeStampOfSSP | VARCHAR2[14] | Timestamp reported by the SSP.<br>Format: YYYYMMDDhhmmss<br>This field can be left empty. |
| 365 | TimeZoneOfSSP | NUMBER[10] | Time zone where the SSP locates.<br>• Empty: default time zone<br>• Non-empty: reported time zone<br>This field can be left empty. |
| 366 | BearerCapability | VARCHAR2[32] | Bearer capability reported by the OCG. The options are as follows:<br>• **8**: video call<br>• **9**: voice data<br>• **10**: voice fax<br>• **0**: normal call<br>The value is reported by external systems. If no value is reported, this field is left empty. The system considers that the value is **0** if this field is left empty. |
| 367 | ChargingTime | VARCHAR2[14] | Charging start time.<br>Format: YYYYMMDDhhmmss<br>This field cannot be left empty. |
| 368 | WaitDuration | NUMBER[10] | Waiting duration.<br>This field is reserved and has a fixed value of **0**. |
| 369 | TerminationReas | NUMBER[10] | Call termination reason. The options are |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | on | | as follows:<br>• **0**: Unknown.<br>• **1**: A subscriber hangs up the phone.<br>• **2**: The account balance is insufficient.<br>• **3**: The call duration reaches the maximum.<br>The default value is **0**.<br>This field cannot be left empty. |
| 370 | CallReferenceNumber | VARCHAR2[128] | Call reference number.<br>• On the GSM network, this field records the **CallReferenceNumber** value reported in an IDP message.<br>• On the CDMA network, this field records the **BillID** value reported in an ORREQ message.<br>• For a SIP call, this field records the **Call-ID** value reported in a SIP message.<br>• If an external system does not report the call reference number, the CBS generates one in the format YYYYMMDDhhmmss + Three-digit OCG ID + Four-digit automaton number.<br>**NOTE**<br>If the automaton number contains less than four digits, prefix the number with 0. If the automaton number contains more than four digits, obtain the last four digits.<br>The value is reported by external systems. If no value is reported, this field is left empty. |
| 371 | IMEI | VARCHAR2[24] | International mobile equipment identity.<br>The value is reported by external systems. If no value is reported, this field is left empty. |
| 372 | AccessPrefix | VARCHAR2[20] | Special prefix that a subscriber dials, for example, IP prefix, international gateway prefix, or a carrier's access code prefix.<br>This field can be left empty for non-special numbers. |
| 373 | RoutingPrefix | VARCHAR2[20] | Routing prefix for rerouting a call.<br>This field can be left empty. |
| 374 | RedirectingPartyID | VARCHAR2[64] | Redirected-to number in the MF process.<br>This field can be left empty in non-MF |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | processes. |
| 375 | MSCAddress | VARCHAR2[24] | MSC address.<br>If the CBS uses this field to analyze the visited area for the charged party, this field cannot be left empty. If the CBS does not use this field to analyze the visited area, this field can be left empty.<br>Format: Country code + NDC + LSP |
| 376 | BrandID | NUMBER[20] | Brand ID.<br>This field cannot be left empty.<br>The default value is **0**. |
| 377 | MainOfferingID | NUMBER[20] | Primary offering ID.<br>This field cannot be left empty.<br>The default value is **0**. |
| 378 | ChargingPartyNumber | VARCHAR2[64] | Charged number.<br>The number formats are as follows:<br>• Fixed-line number: Area code + PSTN<br>• Mobile number: MSISDN<br>• URI format<br>This field cannot be left empty. |
| 379 | ChargePartyIndicator | VARCHAR2[1] | Charged party. The options are as follows:<br>• **1**: calling party<br>• **2**: called party<br>• **3**: third party<br>• **4**: parent or child card subscriber<br>• **5**: calling party and corporate<br>This field cannot be left empty. |
| 380 | PayType | VARCHAR2[1] | Payment type of a subscriber. The options are as follows:<br>• **0**: prepaid<br>• **1**: postpaid<br>• **2**: hybrid<br>This field cannot be left empty. |
| 381 | ChargingType | VARCHAR2[1] | Charging type.<br>The options are as follows:<br>• **0**: V-H<br>• **1**: H-H<br>• **2**: V-V |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **3**: H-V<br>**NOTE**<br>In the option descriptions, V indicates the visited area and H indicates the home area. For example, value **0** indicates that the visited location of the calling party and the home location of the called party are used for number analysis.<br>This field cannot be left empty. |
| 382 | CallType | VARCHAR2[1] | Call type. The options are as follows:<br>• **0**: local call<br>• **1**: toll call within a charging area<br>• **2**: toll call between charging areas<br>• **3**: international toll call<br>This field cannot be left empty. |
| 383 | RoamState | VARCHAR2[1] | Roaming status of the charged party. The options are as follows:<br>• **0**: non-roaming<br>• **1**: roaming within a charging area<br>• **2**: roaming out of a charging area<br>• **3**: international roaming<br>This field cannot be left empty. |
| 384 | CallingHomeCountryCode | NUMBER[10] | Home country code of the calling party.<br>Generally, the 384th to 395th fields cannot be left empty. This field can be left empty in scenarios where the process of charging the calling or called party is irrelevant to the home area or visited area of the peer end. In these scenarios, the network side may not report the visited area or number information about the peer end. |
| 385 | CallingHomeAreaNumber | NUMBER[10] | Home area code of the calling party.<br>This field can be left empty. |
| 386 | CallingHomeNetworkCode | NUMBER[10] | Home network code of the calling party.<br>This field can be left empty. |
| 387 | CallingRoamCountryCode | NUMBER[10] | Roam-in country code of the calling party.<br>This field can be left empty. |
| 388 | CallingRoamAreaNumber | NUMBER[10] | Roam-in area code of the calling party.<br>This field can be left empty. |
| 389 | CallingRoamNet | NUMBER[10] | Roam-in network code of the calling |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | workCode | | party.<br>This field can be left empty. |
| 390 | CalledHomeCountryCode | NUMBER[10] | Home country code of the called party.<br>This field can be left empty. |
| 391 | CalledHomeAreaNumber | NUMBER[10] | Home area code of the called party.<br>This field can be left empty. |
| 392 | CalledHomeNetworkCode | NUMBER[10] | Home network code of the called party.<br>This field can be left empty. |
| 393 | CalledRoamCountryCode | NUMBER[10] | Roam-in country code of the called party.<br>This field can be left empty. |
| 394 | CalledRoamAreaNumber | NUMBER[10] | Roam-in area code of the called party.<br>This field can be left empty. |
| 395 | CalledRoamNetworkCode | NUMBER[10] | Roam-in network code of the called party.<br>This field can be left empty. |
| 396 | ServiceType | VARCHAR2[128] | List of product codes used to charge the charged party. Multiple product codes are separated with a colon (:).<br>This field can be left empty. |
| 397 | HotLineIndicator | NUMBER[10] | Special number type. The options are as follows:<br>• **0**: common number<br>• **1**: barred number<br>• **2**: free number<br>• **3**: Special-tariff number<br>• **9**: voice mail<br>The default value is **0**.<br>This field cannot be left empty. |
| 398 | HomeZoneID | NUMBER[10] | ID of the home zone where the subscriber enjoys a discount.<br>The default value is **0**.<br>This field cannot be left empty. |
| 399 | SpecialZoneID | NUMBER[10] | ID of the special zone where the subscriber enjoys a discount.<br>The default value is **0**.<br>This field cannot be left empty. |
| 400 | NPFlag | VARCHAR2[1] | NP flag. The options are as follows:<br>• **0**: not NP<br>• **1**: NP out |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | The default value is **0**.<br>This field cannot be left empty. |
| 401 | NPPrefix | VARCHAR2[6] | NP prefix.<br>• Set this field to the NP prefix of the called party in the MO process.<br>• Set this field to the NP prefix of the calling party in the MT process.<br>This field is left empty if NP is not executed. |
| 402 | CallingCUGNo | NUMBER[20] | CUG number of the calling party.<br>The default value is **0**.<br>This field cannot be left empty. |
| 403 | CalledCUGNo | NUMBER[20] | CUG number of the called party.<br>The default value is **0**.<br>This field cannot be left empty. |
| 404 | OpposeNumber Type | NUMBER[10] | Peer network type. The options are as follows:<br>• **1**: GSM<br>• **2**: CDMA<br>• **3**: ADSL<br>• **4**: PSTN<br>• **5**: WiMAX<br>• Others: unknown<br>This field cannot be left empty. |
| 405 | CallingNetwork Type | VARCHAR2[10 ] | Access network type of the calling party. The options are as follows:<br>• **1**: GSM<br>• **2**: CDMA<br>• **3**: ADSL<br>• **4**: PSTN<br>• **5**: WiMAX<br>• Others: unknown<br>This field cannot be left empty. |
| 406 | CalledNetworkT ype | VARCHAR2[10 ] | Access network type of the called party. The options are as follows:<br>• **1**: GSM<br>• **2**: CDMA<br>• **3**: ADSL<br>• **4**: PSTN<br>• **5**: WiMAX |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • Others: unknown<br>This field cannot be left empty. |
| 407 | CallingVPNTopGroupNumber | VARCHAR2[64] | Number of the top-level corporation to which the calling party belongs.<br>This field is valid only in the MO and MF processes where the calling party is a corporate member.<br>This field is empty when no corporation information exists.<br>This field can be left empty. |
| 408 | CallingVPNGroupNumber | VARCHAR2[64] | Number of the corporation to which the calling party belongs.<br>This field is valid only in the MO and MF processes where the calling party is a corporate member.<br>This field is empty when no corporation information exists.<br>This field can be left empty. |
| 409 | CallingVPNShortNumber | VARCHAR2[10] | Short number of the calling party.<br>This field is valid only in the MO and MF processes where the calling party is a corporate member.<br>This field can be left empty. |
| 410 | CalledVPNTopGroupNumber | VARCHAR2[64] | Number of the top-level corporation to which the called party belongs.<br>This field is valid only in the MT process where the called party is a corporate member.<br>This field is empty when no corporation information exists.<br>This field can be left empty. |
| 411 | CalledVPNGroupNumber | VARCHAR2[64] | Number of the corporation to which the called party belongs.<br>This field is valid only in the MT process where the called party is a corporate member.<br>This field is empty when no corporation information exists.<br>This field can be left empty. |
| 412 | CalledVPNShortNumber | VARCHAR2[10] | Short number of the called party.<br>This field is valid only in the MT process where the called party is a corporate member. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | This field can be left empty. |
| 413 | GroupCallType | NUMBER[10] | Corporate call type.<br>This field is valid only when the charged party is a corporate subscriber. The options are as follows:<br>• **0**: non-corporate call<br>• **1**: corporate intra-network call<br>• **2**: corporate inter-network call<br>The default value is **0**.<br>This field cannot be left empty. |
| 414 | OnlineChargingFlag | VARCHAR2[1] | Online charging flag. The options are as follows:<br>• **0**: online charging<br>• **1**: offline charging<br>This field cannot be left empty. |
| 415 | StartTimeOfBillCycle | VARCHAR2[14] | Bill cycle start time of the charged subscriber when a charging event occurs.<br>Format: YYYYMMDDhhmmss<br>This field cannot be left empty. |
| 416 | LastEffectOffering | NUMBER[20] | ID of the last offering that takes effect.<br>The default value is **0**.<br>This field cannot be left empty. |
| 417 | DTDiscount | NUMBER[10] | DT discount rate.<br>The default value is **0**.<br>This field cannot be left empty. |
| 418 | OpposeMainOfferingID | NUMBER[20] | Primary offering ID of the peer party's number.<br>The default value is **0**.<br>This field cannot be left empty. |
| 419 | MainBalanceInfo | VARCHAR2[255] | This field is reserved. |
| 420 | ChgBalanceInfo | VARCHAR2[255] | This field is reserved. |
| 421 | ChgFreeUnitInfo | VARCHAR2[255] | This field is reserved. |
| 422 | UserState | VARCHAR2[10] | Life cycle state and the management state of a subscriber.<br>The **UserState** parameter is a numeric string of seven digits, in the format *CCMMMMM*. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | The first and second digits C indicate the life cycle state of a subscriber. The first digit C indicates the state of a prepaid subscriber, and the second digit C indicates the state of a postpaid subscriber. The options are as follows:<br>• 0: Idle<br>• 1: Active<br>• 2: Suspended<br>• 3: Disable<br>• 4: Pool<br>• 5: Pool without activation<br>The next five digits *MMMMM* indicate the management state of a subscriber. The options are as follows:<br>• The third digit indicates whether a subscriber claims missing.<br>**0**: no<br>**1**: yes<br>• The fourth digit indicates whether a subscriber is barred or suspended upon subscriber request.<br>**0**: no<br>**1**: barred or suspended on subscriber request<br>**2**: barred on subscriber request<br>**3**: suspended on subscriber request<br>• The fifth digit indicates whether a subscriber is barred or suspended on arrears.<br>**0**: no<br>**1**: yes<br>• The sixth digit indicates whether a subscriber is barred or suspended on credit control. This digit is reserved.<br>**0**: no<br>**1**: yes<br>• The seventh digit indicates the blacklist flag.<br>**0**: not blacklisted<br>**1**: blacklisted<br>This field cannot be left empty. |
| 423 | GroupPayFlag | NUMBER[10] | Payment mode of the corporate member.<br>The options are as follows: |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **0**: personal payment<br>• **1**: group payment<br>• **2**: corporate and personal payment<br>The default value is **0**.<br>This field cannot be left empty. |
| 424 | RoamingZoneID | VARCHAR2[20] | Roaming zone ID.<br>This field can be left empty. |
| 425 | PrimaryOfferChgAmt | NUMBER[20] | Primary offering rating amount.<br>The default value is 0.<br>This field cannot be left empty |
| 426 | OriginatingIOI | VARCHAR2[128] | ID of the network from which a service is initiated.<br>For the VoLTE call, this field cannot be left empty. For other voice services, this field is left empty.<br>This field can be left empty. |
| 427 | TerminatingIOI | VARCHAR2[128] | ID of the network to which a service is triggered.<br>For the VoLTE call, this field cannot be left empty. For other voice services, this field is left empty.<br>This field can be left empty. |
| 428 | IMSChargingIdentifier | NUMBER[20] | IMS charging ID<br>For the VoLTE call, this field cannot be left empty. For other voice services, this field is left empty.<br>This field can be left empty. |
| 429 | ACCT_BAL_EXPIRE_TIME1 | DATE[14] | Expiration time of the 1st bonus account balance in the group from 202nd to 271st fields. |
| 430 | ACCT_BAL_EXPIRE_TIME2 | DATE[14] | Expiration time of the 2nd bonus account balance in the group from 202nd to 271st fields. |
| 431 | ACCT_BAL_EXPIRE_TIME3 | DATE[14] | Expiration time of the 3rd bonus account balance in the group from 202nd to 271st fields. |
| 432 | ACCT_BAL_EXPIRE_TIME4 | DATE[14] | Expiration time of the 4th bonus account balance in the group from 202nd to 271st fields. |
| 433 | ACCT_BAL_EXPIRE_TIME5 | DATE[14] | Expiration time of the 5th bonus account balance in the group from 202nd to 271st |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | fields. |
| 434 | ACCT_BAL_EXPIRE_TIME6 | DATE[14] | Expiration time of the 6th bonus account balance in the group from 202nd to 271st fields. |
| 435 | ACCT_BAL_EXPIRE_TIME7 | DATE[14] | Expiration time of the 7th bonus account balance in the group from 202nd to 271st fields. |
| 436 | ACCT_BAL_EXPIRE_TIME8 | DATE[14] | Expiration time of the 8th bonus account balance in the group from 202nd to 271st fields. |
| 437 | ACCT_BAL_EXPIRE_TIME9 | DATE[14] | Expiration time of the 9th bonus account balance in the group from 202nd to 271st fields. |
| 438 | ACCT_BAL_EXPIRE_TIME10 | DATE[14] | Expiration time of the 10th bonus account balance in the group from 202nd to 271st fields. |
| 439 | BONUS_FU_EXPIRE_TIME1 | DATE[14] | Expiration time of the 1st bonus free unit in the group from 272nd to 351st fields. |
| 440 | BONUS_FU_EXPIRE_TIME2 | DATE[14] | Expiration time of the 2nd bonus free unit in the group from 272nd to 351st fields. |
| 441 | BONUS_FU_EXPIRE_TIME3 | DATE[14] | Expiration time of the 3rd bonus free unit in the group from 272nd to 351st fields. |
| 442 | BONUS_FU_EXPIRE_TIME4 | DATE[14] | Expiration time of the 4th bonus free unit in the group from 272nd to 351st fields. |
| 443 | BONUS_FU_EXPIRE_TIME5 | DATE[14] | Expiration time of the 5th bonus free unit in the group from 272nd to 351st fields. |
| 444 | BONUS_FU_EXPIRE_TIME6 | DATE[14] | Expiration time of the 6th bonus free unit in the group from 272nd to 351st fields. |
| 445 | BONUS_FU_EXPIRE_TIME7 | DATE[14] | Expiration time of the 7th bonus free unit in the group from 272nd to 351st fields. |
| 446 | BONUS_FU_EXPIRE_TIME8 | DATE[14] | Expiration time of the 8th bonus free unit in the group from 272nd to 351st fields. |
| 447 | BONUS_FU_EXPIRE_TIME9 | DATE[14] | Expiration time of the 9th bonus free unit in the group from 272nd to 351st fields. |
| 448 | BONUS_FU_EXPIRE_TIME10 | DATE[14] | Expiration time of the 10th bonus free unit in the group from 272nd to 351st fields. |

 Copyright © Huawei Technologies Co., Ltd. 

### 4.2.2.2 Extended Charging Service Information in an SMS CDR

This topic describes extended fields in the charging service information in an SMS CDR.

Table 4-5 describes extended fields in the charging service information in an SMS CDR.

**Table 4-5** Extended charging service information in an SMS CDR

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 352 | CallingPartyNumber | VARCHAR2[64] | Sender number.<br>For numbers of the E.164 type, the number formats are as follows:<br>• Fixed-line number: Country code + Area code + PSTN<br>• Mobile number: Country code + MSISDN<br>For SP IDs, the reported number is used directly.<br>This field can be left empty. |
| 353 | CalledPartyNumber | VARCHAR2[64] | Recipient number.<br>For numbers of the E.164 type, the international number format is used.<br>• Fixed-line number: Country code + Area code + PSTN<br>• Mobile number: Country code + MSISDN<br>For SP IDs, the reported number is used directly.<br>This field can be left empty. |
| 354 | CallingPartyIMSI | VARCHAR2[64] | IMSI of the sender.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>If the value comes in DCC message that value will be stored in CDR. If no value was sent, then the DB value will be stored in CDR.<br>This field can be left empty. |
| 355 | CalledPartyIMSI | VARCHAR2[64] | IMSI of the recipient.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>This field can be left empty. |
| 356 | DialedNumber | VARCHAR2[64] | Number that is dialed.<br>The value is reported by the network side in the MO process. If no value is |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | reported, this field is left empty. The value can be in any format. |
| 357 | OriginalCalledParty | VARCHAR2[64] | Original called number in a forwarding process or special number reroute process. International number form in call forwarding, actual call number in special number reroute, filling in original called number when dialed through an international gateway office. (be valid in MF flow).<br>This field can be left empty. |
| 358 | ServiceFlow | VARCHAR2[1] | Call process ID. The options are as follows:<br>• **1**: MO<br>• **2**: MT<br>• **5**: delivery report<br>This field cannot be left empty. |
| 359 | CallForwardIndicator | VARCHAR2[1] | Call forwarding flag. The options are as follows:<br>• **0**: no call forwarding<br>• **1**: call forwarding conditional<br>• **2**: call forwarding unconditional<br>The default value is **0**.<br>This field cannot be left empty. |
| 360 | CallingRoamInfo | VARCHAR2[20] | Roaming information about the calling party.<br>This field is used to analyze the calling party's roaming status and can be set to the value of fields such as **LocationNumber**, **MSCAddress**, or **VLRNumber**. The value depends on the control parameter specifying the roaming analysis method.<br>For the calling number, it is recorded in the international number format by default. For other information, the reported one is recorded directly.<br>This field can be left empty. |
| 361 | CallingCellID | VARCHAR2[20] | Cell ID of the calling party.<br>If the CBS does not need to analyze the visited area based on the cell ID, this field can be left empty.<br>The format is Three-digit MCC + Two-digit MNC + Five-digit LAC + Five-digit cell ID, for example, |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | **460002230320412**.<br>This field can be left empty. |
| 362 | CalledRoamInfo | VARCHAR2[20] | Roaming information about the called party.<br>This field is used to analyze the called party's roaming status and can be set to the value of fields such as **LocationNumber**, **MSCAddress**, or **VLRNumber**. The value depends on the control parameter specifying the roaming analysis method.<br>This field can be left empty. |
| 363 | CalledCellID | VARCHAR2[20] | Cell ID of the called party.<br>If the CBS does not need to analyze the visited area based on the cell ID, this field can be left empty.<br>The format is Three-digit MCC + Two-digit MNC + Five-digit LAC + Five-digit cell ID, for example, **460002230320412**.<br>This field can be left empty. |
| 364 | TimeStampOfSSP | VARCHAR2[14] | Timestamp reported by the SSP.<br>Format: YYYYMMDDhhmmss<br>This field can be left empty. |
| 365 | TimeZoneOfSSP | NUMBER[10] | Time zone where the SSP locates.<br>• Empty: default time zone<br>• Non-empty: reported time zone<br>This field can be left empty. |
| 366 | BearerCapability | VARCHAR2[32] | This field is reserved. |
| 367 | ChargingTime | VARCHAR2[14] | Charging start time.<br>Format: YYYYMMDDhhmmss<br>This field cannot be left empty. |
| 368 | SendResult | NUMBER[10] | SMS message sending result. The options are as follows:<br>• **0**: successful<br>• Others: Enter the value transferred from the interface, for example, SMPP+ interface.<br>The default value is **0**.<br>This field cannot be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 369 | SMSID | VARCHAR2[20] | SMS message ID.<br>Set this field to the SMS message ID or request sequence number transferred from the SMPP+ interface. The value is reported by external systems.<br>This field cannot be left empty. |
| 370 | IMEI | VARCHAR2[24] | International mobile equipment identity.<br>This field can be left empty. |
| 371 | SMLength | NUMBER[10] | SMS message length.<br>This field is valid to sites that charge for SMS messages based on the SMS message length. If the SMS message length is not used as a charging factor, this field can be left empty or set to **0**.<br>This field can be left empty. |
| 372 | SMSCAddress | VARCHAR2[20] | SMSC address reported by external systems.<br>This field can be left empty. |
| 373 | RefundIndicator | VARCHAR2[20] | Fee deduction flag. The options are as follows:<br>• **0**: fee deduction<br>• **1**: refund<br>The default value is **0**.<br>This field cannot be left empty. |
| 374 | BrandID | NUMBER[20] | Brand ID.<br>The default value is **0**.<br>This field cannot be left empty. |
| 375 | MainOfferingID | NUMBER[20] | Primary offering ID.<br>The default value is **0**.<br>This field cannot be left empty. |
| 376 | ChargingPartyNumber | VARCHAR2[64] | Charged number.<br>The number formats are as follows:<br>• Fixed-line number: Area code + PSTN<br>• Mobile number: MSISDN<br>This field cannot be left empty. |
| 377 | ChargePartyIndicator | VARCHAR2[1] | Charged party. The options are as follows:<br>• **1**: calling party<br>• **2**: called party |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **3**: third party<br>• **4**: parent or child card subscriber<br>• **5**: calling party and corporate<br>This field cannot be left empty. |
| 378 | PayType | VARCHAR2[1] | Payment type of a subscriber. The options are as follows:<br>• **0**: prepaid<br>• **1**: postpaid<br>• **2**: hybrid<br>This field cannot be left empty. |
| 379 | ChargingType | VARCHAR2[1] | Charging type.<br>The options are as follows:<br>• **0**: V-H<br>• **1**: H-H<br>• **2**: V-V<br>• **3**: H-V<br>**NOTE**<br>In the option descriptions, V indicates the visited area and H indicates the home area. For example, value **0** indicates that the visited location of the calling party and the home location of the called party are used for number analysis.<br>This field cannot be left empty. |
| 380 | SMSType | NUMBER[10] | SMS message type. The options are as follows:<br>• **0**: local SMS message<br>• **1**: intra-province toll SMS message<br>• **2**: inter-province toll SMS message<br>• **3**: international toll SMS message<br>This field cannot be left empty. |
| 381 | OnNetIndicator | VARCHAR2[1] | Analyzed SMS message type according to the network. The options are as follows:<br>• **0**: intra-network<br>• **1**: inter-network<br>• **2**: unknown (This value is used when the CBS cannot determine the intra-network or inter-network type, for example, when a subscriber is roaming internationally.)<br>This field cannot be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 382 | RoamState | VARCHAR2[1] | Roaming status of the charged party. The options are as follows:<br>• **0**: non-roaming<br>• **1**: roaming within a charging area<br>• **2**: roaming out of a charging area<br>• **3**: international roaming<br>This field cannot be left empty. |
| 383 | CallingHomeCountryCode | NUMBER[10] | Home country code of the calling party.<br>Generally, the 383rd to 394th fields cannot be left empty. This field can be left empty in scenarios where the process of charging the calling or called party is irrelevant to the home area or visited area of the peer end. In these scenarios, the network side may not report the visited area or number information about the peer end.<br>This field can be left empty. |
| 384 | CallingHomeAreaNumber | NUMBER[10] | Home area code of the calling party.<br>This field can be left empty. |
| 385 | CallingHomeNetworkCode | NUMBER[10] | Home network code of the calling party.<br>This field can be left empty. |
| 386 | CallingRoamCountryCode | NUMBER[10] | Roam-in country code of the calling party.<br>This field can be left empty. |
| 387 | CallingRoamAreaNumber | NUMBER[10] | Roam-in area code of the calling party.<br>This field can be left empty. |
| 388 | CallingRoamNetworkCode | NUMBER[10] | Roam-in network code of the calling party.<br>This field can be left empty. |
| 389 | CalledHomeCountryCode | NUMBER[10] | Home country code of the called party.<br>This field can be left empty. |
| 390 | CalledHomeAreaNumber | NUMBER[10] | Home area code of the called party.<br>This field can be left empty. |
| 391 | CalledHomeNetworkCode | NUMBER[10] | Home network code of the called party.<br>This field can be left empty. |
| 392 | CalledRoamCountryCode | NUMBER[10] | Roam-in country code of the called party.<br>This field can be left empty. |
| 393 | CalledRoamAre | NUMBER[10] | Roam-in area code of the called party. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | aNumber | | This field can be left empty. |
| 394 | CalledRoamNetworkCode | NUMBER[10] | Roam-in network code of the called party.<br>This field can be left empty. |
| 395 | ServiceType | VARCHAR2[128] | List of product codes used to charge the charged party. Multiple product codes are separated with a colon (:).<br>This field can be left empty. |
| 396 | SpecialNumberIndicator | NUMBER[10] | Special number type. The options are as follows:<br>• **0**: common number<br>• **1**: barred number<br>• **2**: free number<br>• **3**: Special-tariff number<br>• **9**: voice mail<br>The default value is **0**.<br>This field cannot be left empty. |
| 397 | NPFlag | VARCHAR2[1] | NP flag. The options are as follows:<br>• **0**: not NP<br>• **1**: NP out<br>The default value is **0**.<br>This field cannot be left empty. |
| 398 | NPPrefix | VARCHAR2[6] | NP prefix.<br>• Set this field to the NP prefix of the called party in the MO process.<br>• Set this field to the NP prefix of the calling party in the MT process.<br>This field is left empty if NP is not executed. |
| 399 | CallingCUGNo | NUMBER[20] | CUG number of the calling party.<br>If the calling party does not join a CUG, this field is set to **0**.<br>This field cannot be left empty. |
| 400 | CalledCUGNo | NUMBER[20] | CUG number of the called party.<br>If the called party does not join a CUG, this field is set to **0**.<br>This field cannot be left empty. |
| 401 | OpposeNetworkType | NUMBER[10] | Peer network type. The options are as follows:<br>• **1**: GSM |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **2**: CDMA<br>• **3**: ADSL<br>• **4**: PSTN<br>• **5**: WiMAX<br>• Others: unknown<br>This field cannot be left empty.<br>This field is reserved. |
| 402 | OpposeNumberType | NUMBER[10] | Peer network type. The options are as follows:<br>• **1**: GSM<br>• **2**: CDMA<br>• **3**: ADSL<br>• **4**: PSTN<br>• **5**: WiMAX<br>• Others: unknown<br>This field cannot be left empty. |
| 403 | CallingNetworkType | VARCHAR2[10] | Access network type of the calling party.<br>• **1**: GSM<br>• **2**: CDMA<br>• **3**: ADSL<br>• **4**: PSTN<br>• **5**: WiMAX<br>• Others: unknown<br>This field can be left empty. |
| 404 | CalledNetworkType | VARCHAR2[10] | Access network type of the called party.<br>• **1**: GSM<br>• **2**: CDMA<br>• **3**: ADSL<br>• **4**: PSTN<br>• **5**: WiMAX<br>• Others: unknown<br>This field cannot be left empty. |
| 405 | CallingVPNTopGroupNumber | VARCHAR2[64] | Number of the top-level corporation to which the sender belongs.<br>This field is valid only in the MO process where the sender is a corporate member.<br>This field is empty when no corporation information exists.<br>This field can be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 406 | CallingVPNGroupNumber | VARCHAR2[64] | Number of the corporation to which the sender belongs.<br>This field is valid only in the MO process where the sender is a corporate member.<br>This field is empty when no corporation information exists.<br>This field can be left empty. |
| 407 | CallingVPNShortNumber | VARCHAR2[10] | Short number of the sender.<br>This field is valid only in the MO process where the sender is a corporate member.<br>This field can be left empty. |
| 408 | CalledVPNTopGroupNumber | VARCHAR2[64] | Number of the top-level corporation to which the recipient belongs.<br>This field is valid only in the MT process where the recipient is a corporate member.<br>This field is empty when no corporation information exists.<br>This field can be left empty. |
| 409 | CalledVPNGroupNumber | VARCHAR2[64] | Number of the corporation to which the recipient belongs.<br>This field is valid only in the MT process where the recipient is a corporate member.<br>This field is empty when no corporation information exists.<br>This field can be left empty. |
| 410 | CalledVPNShortNumber | VARCHAR2[10] | Short number of the recipient.<br>This field is valid only in the MT process where the recipient is a corporate member.<br>This field can be left empty. |
| 411 | GroupCallType | VARCHAR2[10] | Corporate call type.<br>This field is valid only when the charged party is a corporate subscriber. The options are as follows:<br>• **0**: non-corporate call<br>• **1**: corporate intra-network call<br>• **2**: corporate inter-network call<br>The default value is **0**.<br>This field cannot be left empty. |
| 412 | OnlineCharging | VARCHAR2[1] | Online charging flag. The options are as |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | Flag | | follows:<br>• **0**: online charging<br>• **1**: offline charging<br>This field cannot be left empty. |
| 413 | StartTimeOfBillCycle | VARCHAR2[14] | Bill cycle start time of the charged subscriber when a charging event occurs.<br>Format: YYYYMMDDhhmmss<br>This field cannot be left empty. |
| 414 | LastEffectOffering | NUMBER[20] | ID of the last offering that takes effect.<br>The default value is **0**.<br>This field cannot be left empty. |
| 415 | DTDiscount | NUMBER[10] | DT discount rate.<br>This field can be left empty. |
| 416 | OpposeMainOfferingID | NUMBER[20] | Primary offering ID of the peer party's number.<br>The default value is **0**.<br>This field cannot be left empty. |
| 417 | HomeZoneID | NUMBER[10] | Home zone ID.<br>When a subscriber enjoys the home zone discount, the value of this field is the home zone ID of the area where the subscriber currently locates.<br>The default value is **0**.<br>This field cannot be left empty. |
| 418 | SpecialZoneID | NUMBER[10] | Special zone ID.<br>When a subscriber enjoys the special zone discount, the value of this field is the special zone ID of the area where the subscriber currently locates.<br>The default value is **0**.<br>This field cannot be left empty. |
| 419 | MainBalanceInfo | VARCHAR2[255] | This field is reserved. |
| 420 | ChgBalanceInfo | VARCHAR2[255] | This field is reserved. |
| 421 | ChgFreeUnitInfo | VARCHAR2[255] | This field is reserved. |
| 422 | UserState | VARCHAR2[10] | This field is reserved. |
| 423 | GroupPayFlag | NUMBER[10] | This field is reserved. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 424 | RoamingZoneID | VARCHAR2[20] | Roaming zone ID.<br>This field can be left empty. |
| 425 | PrimaryOfferChgAmt | NUMBER[20] | Primary offering rating amount.<br>The default value is 0.<br>This field cannot be left empty |
| 426 | ACCT_BAL_EXPIRE_TIME1 | DATE[14] | Expiration time of the 1st bonus account balance in the group from 202nd to 271st fields. |
| 427 | ACCT_BAL_EXPIRE_TIME2 | DATE[14] | Expiration time of the 2nd bonus account balance in the group from 202nd to 271st fields. |
| 428 | ACCT_BAL_EXPIRE_TIME3 | DATE[14] | Expiration time of the 3rd bonus account balance in the group from 202nd to 271st fields. |
| 429 | ACCT_BAL_EXPIRE_TIME4 | DATE[14] | Expiration time of the 4th bonus account balance in the group from 202nd to 271st fields. |
| 430 | ACCT_BAL_EXPIRE_TIME5 | DATE[14] | Expiration time of the 5th bonus account balance in the group from 202nd to 271st fields. |
| 431 | ACCT_BAL_EXPIRE_TIME6 | DATE[14] | Expiration time of the 6th bonus account balance in the group from 202nd to 271st fields. |
| 432 | ACCT_BAL_EXPIRE_TIME7 | DATE[14] | Expiration time of the 7th bonus account balance in the group from 202nd to 271st fields. |
| 433 | ACCT_BAL_EXPIRE_TIME8 | DATE[14] | Expiration time of the 8th bonus account balance in the group from 202nd to 271st fields. |
| 434 | ACCT_BAL_EXPIRE_TIME9 | DATE[14] | Expiration time of the 9th bonus account balance in the group from 202nd to 271st fields. |
| 435 | ACCT_BAL_EXPIRE_TIME10 | DATE[14] | Expiration time of the 10th bonus account balance in the group from 202nd to 271st fields. |
| 436 | BONUS_FU_EXPIRE_TIME1 | DATE[14] | Expiration time of the 1st bonus free unit in the group from 272nd to 351st fields. |
| 437 | BONUS_FU_EXPIRE_TIME2 | DATE[14] | Expiration time of the 2nd bonus free unit in the group from 272nd to 351st fields. |
| 438 | BONUS_FU_EXPIRE_TIME3 | DATE[14] | Expiration time of the 3rd bonus free unit in the group from 272nd to 351st fields. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 439 | BONUS_FU_EXPIRE_TIME4 | DATE[14] | Expiration time of the 4th bonus free unit in the group from 272nd to 351st fields. |
| 440 | BONUS_FU_EXPIRE_TIME5 | DATE[14] | Expiration time of the 5th bonus free unit in the group from 272nd to 351st fields. |
| 441 | BONUS_FU_EXPIRE_TIME6 | DATE[14] | Expiration time of the 6th bonus free unit in the group from 272nd to 351st fields. |
| 442 | BONUS_FU_EXPIRE_TIME7 | DATE[14] | Expiration time of the 7th bonus free unit in the group from 272nd to 351st fields. |
| 443 | BONUS_FU_EXPIRE_TIME8 | DATE[14] | Expiration time of the 8th bonus free unit in the group from 272nd to 351st fields. |
| 444 | BONUS_FU_EXPIRE_TIME9 | DATE[14] | Expiration time of the 9th bonus free unit in the group from 272nd to 351st fields. |
| 445 | BONUS_FU_EXPIRE_TIME10 | DATE[14] | Expiration time of the 10th bonus free unit in the group from 272nd to 351st fields. |

### 4.2.2.3 Extended Charging Service Information in an MMS CDR

This topic describes extended fields in the charging service information in an MMS CDR.

Table 4-6 describes extended fields in the charging service information in an MMS CDR.

**Table 4-6** Extended charging service information in an MMS CDR

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 352 | CallingPartyNumber | VARCHAR2[64] | Sender number.<br>For numbers of the E.164 type, the number formats are as follows:<br>• Fixed-line number: Country code + Area code + PSTN<br>• Mobile number: Country code + MSISDN<br>For SP IDs, the reported number is used directly.<br>This field can be left empty. |
| 353 | CalledPartyNumber | VARCHAR2[64] | Recipient number.<br>For numbers of the E.164 type.<br>• Fixed-line number: Country code + Area code + PSTN<br>• Mobile number: Country code + MSISDN<br>For SP IDs, the reported number is used |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | directly.<br>This field can be left empty. |
| 354 | CallingPartyIMSI | VARCHAR2[64] | IMSI of the sender.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>If the value comes in DCC message that value will be stored in CDR. If no value was sent, then the DB value will be stored in CDR.<br>This field can be left empty. |
| 355 | CalledPartyIMSI | VARCHAR2[64] | IMSI of the recipient.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>This field can be left empty. |
| 356 | DialedNumber | VARCHAR2[64] | Number that is dialed.<br>The value is reported by the network side and can be in any format.<br>This field can be left empty. |
| 357 | ServiceFlow | VARCHAR2[1] | MMS process type. The options are as follows:<br>• **1**: MO<br>• **2**: MT<br>• **3**: MF (reserved)<br>• **4**: read-reply report<br>• **5**: delivery report<br>• **6**: reply report<br>This field cannot be left empty. |
| 358 | CallingRoamInfo | VARCHAR2[20] | Roaming information about the sender.<br>This field is used to analyze the calling party's roaming status and can be set to the value of fields such as **LocationNumber**, **MSCAddress**, or **VLRNumber**.<br>For the calling number, it is recorded in the international number format by default. For other information, the reported one is recorded directly.<br>This field can be left empty. |
| 359 | CallingCellID | VARCHAR2[20] | Cell ID of the sender.<br>The value is reported in IDP messages. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | If the CBS does not need to analyze the visited area based on the cell ID, this field can be left empty.<br>The format is Three-digit MCC + Two-digit MNC + Five-digit LAC + Five-digit cell ID, for example, **460002230320412**. |
| 360 | CalledRoamInfo | VARCHAR2[20] | Roaming information about the recipient.<br>This field is used to analyze the called party's roaming status and can be set to the value of fields such as **LocationNumber**, **MSCAddress**, or **VLRNumber**.<br>This field can be left empty. |
| 361 | CalledCellID | VARCHAR2[20] | Cell ID of the recipient.<br>If the CBS does not need to analyze the visited area based on the cell ID, this field can be left empty.<br>The format is Three-digit MCC + Two-digit MNC + Five-digit LAC + Five-digit cell ID, for example, **460002230320412**. |
| 362 | TimeStampOfSSP | VARCHAR2[14] | Timestamp reported by the SSP.<br>Format: YYYYMMDDhhmmss<br>This field can be left empty. |
| 363 | TimeZoneOfSSP | NUMBER[10] | Time zone where the SSP locates.<br>This field can be left empty. If this field is left empty, the time zone in the MSC is the same as that of the home server. |
| 364 | ChargingTime | VARCHAR2[14] | Charging start time.<br>Format: YYYYMMDDhhmmss<br>This field cannot be left empty. |
| 365 | SendResult | NUMBER[10] | MMS message sending result. The options are as follows:<br>• **0**: failure<br>• **1**: successful<br>The default value is **1**.<br>This field cannot be left empty. |
| 366 | MMSID | VARCHAR2[24] | MMS message ID or sequence number, which uniquely identifies a fee deduction request.<br>The value is reported by the network side. If no value is reported, this field is left |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | empty.<br>This field can be left empty. |
| 367 | IMEI | VARCHAR2[24] | International mobile equipment identity.<br>This field can be left empty. |
| 368 | MMSLength | NUMBER[10] | MMS message size reported by external systems.<br>If MMS messages are charged based on their sizes, this field cannot be left empty.<br>The default value is **0**.<br>This field cannot be left empty. |
| 369 | RefundIndicator | VARCHAR2[20] | Fee deduction flag. The options are as follows:<br>• **0**: fee deduction<br>• **1**: refund<br>This field cannot be left empty. |
| 370 | BrandID | NUMBER[20] | Brand ID.<br>The default value is **0**.<br>This field cannot be left empty. |
| 371 | MainOfferingID | NUMBER[20] | Primary offering ID.<br>The default value is **0**.<br>This field cannot be left empty. |
| 372 | ChargingPartyNumber | VARCHAR2[64] | Charged number.<br>The number formats are as follows:<br>• Fixed-line number: Area code + PSTN<br>• Mobile number: MSISDN<br>This field cannot be left empty. |
| 373 | ChargePartyIndicator | VARCHAR2[1] | Charged party. The options are as follows:<br>• **1**: calling party<br>• **2**: called party<br>• **3**: third party<br>• **4**: parent or child card subscriber<br>• **5**: calling party and corporate<br>This field cannot be left empty. |
| 374 | PayType | VARCHAR2[1] | Payment type of a subscriber. The options are as follows:<br>• **0**: prepaid<br>• **1**: postpaid |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **2**: hybrid<br>This field cannot be left empty. |
| 375 | ChargingType | VARCHAR2[1] | Charging type.<br>The options are as follows:<br>• **0**: V-H<br>• **1**: H-H<br>• **2**: V-V<br>• **3**: H-V<br>**NOTE**<br>In the option descriptions, V indicates the visited area and H indicates the home area. For example, value **0** indicates that the visited location of the calling party and the home location of the called party are used for number analysis.<br>This field cannot be left empty. |
| 376 | OnNetIndicator | VARCHAR2[1] | Analyzed MMS message type according to the network. The options are as follows:<br>• **0**: intra-network<br>• **1**: inter-network<br>• **2**: unknown (This value is used when the CBS cannot determine the intra-network or inter-network type, for example, when a subscriber is roaming internationally.)<br>This field cannot be left empty. |
| 377 | RoamState | VARCHAR2[1] | Roaming status of the charged party. The options are as follows:<br>• **0**: non-roaming<br>• **1**: roaming within a charging area<br>• **2**: roaming out of a charging area<br>• **3**: international roaming<br>This field cannot be left empty. |
| 378 | CallingHomeCountryCode | NUMBER[10] | Home country code of the MMS message sender.<br>Generally, the 378th to 389th fields cannot be left empty. This field can be left empty in scenarios where the process of charging the calling or called party is irrelevant to the home area or visited area of the peer end. In these scenarios, the network side may not report the visited area or number information about the peer end. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 379 | CallingHomeAreaNumber | NUMBER[10] | Home area code of the MMS message sender.<br>This field can be left empty. |
| 380 | CallingHomeNetworkCode | NUMBER[10] | Home network code of the MMS message sender.<br>This field can be left empty. |
| 381 | CallingRoamCountryCode | NUMBER[10] | Roaming country code of the MMS message sender.<br>This field can be left empty. |
| 382 | CallingRoamAreaNumber | NUMBER[10] | Roaming area code of the MMS message sender. |
| 383 | CallingRoamNetworkCode | NUMBER[10] | Roaming network code of the MMS message sender.<br>This field can be left empty. |
| 384 | CalledHomeCountryCode | NUMBER[10] | Home country code of the MMS message recipient.<br>This field can be left empty. |
| 385 | CalledHomeAreaNumber | NUMBER[10] | Home area code of the MMS message recipient.<br>This field can be left empty. |
| 386 | CalledHomeNetworkCode | NUMBER[10] | Home network code of the MMS message recipient.<br>This field can be left empty. |
| 387 | CalledRoamCountryCode | NUMBER[10] | Roaming country code of the MMS message recipient.<br>This field can be left empty. |
| 388 | CalledRoamAreaNumber | NUMBER[10] | Roaming area code of the MMS message recipient.<br>This field can be left empty. |
| 389 | CalledRoamNetworkCode | NUMBER[10] | Roaming network code of the MMS message recipient.<br>This field can be left empty. |
| 390 | ServiceType | VARCHAR2[128] | List of product codes used to charge the charged party. Multiple product codes are separated with a colon (:).<br>This field can be left empty. |
| 391 | SpecialNumberIndicator | NUMBER[10] | Special number type. The options are as follows:<br>• **0**: common number<br>• **1**: barred number |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **2**: free number<br>• **3**: Special-tariff number<br>• **9**: voice mail<br>The default value is **0**.<br>This field cannot be left empty. |
| 392 | NPFlag | VARCHAR2[1] | NP flag. The options are as follows:<br>• **0**: not NP<br>• **1**: NP out<br>The default value is **0**.<br>This field cannot be left empty. |
| 393 | NPPrefix | VARCHAR2[6] | NP prefix. This field is set to the recipient's NP prefix for the MMS message sender and the sender's NP prefix for the MMS message recipient.<br>This field is left empty if NP is not executed. |
| 394 | CallingCUGNo | NUMBER[20] | CUG ID of the MMS message sender.<br>The default value is **0**.<br>This field cannot be left empty. |
| 395 | CalledCUGNo | NUMBER[20] | CUG ID of the MMS message recipient.<br>The default value is **0**.<br>This field cannot be left empty. |
| 396 | OpposeNumber Type | NUMBER[10] | Peer network type. The options are as follows:<br>• **1**: GSM<br>• **2**: CDMA<br>• **3**: ADSL<br>• **4**: PSTN<br>• **5**: WiMAX<br>• Others: unknown<br>This field cannot be left empty. |
| 397 | CallingNetwork Type | VARCHAR2[10 ] | Access network type of the calling party.<br>• **1**: GSM<br>• **2**: CDMA<br>• **3**: ADSL<br>• **4**: PSTN<br>• **5**: WiMAX<br>• Others: unknown<br>This field cannot be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 398 | CalledNetworkType | VARCHAR2[10] | Access network type of the MMS message recipient. The options are as follows:<br>• **1**: GSM<br>• **2**: CDMA<br>• **3**: ADSL<br>• **4**: PSTN<br>• **5**: WiMAX<br>• Others: unknown<br>This field cannot be left empty. |
| 399 | CallingVPNTopGroupNumber | VARCHAR2[64] | Number of the top-level corporation to which the sender belongs.<br>This field is valid only in the MO process where the sender is a corporate member.<br>This field is empty when no corporation information exists.<br>This field can be left empty. |
| 400 | CallingVPNGroupNumber | VARCHAR2[64] | Number of the corporation to which the sender belongs.<br>This field is valid only in the MO process where the sender is a corporate member.<br>This field is empty when no corporation information exists.<br>This field can be left empty. |
| 401 | CallingVPNShortNumber | VARCHAR2[10] | Short number of the sender.<br>This field is valid only in the MO process where the sender is a corporate member.<br>This field can be left empty. |
| 402 | CalledVPNTopGroupNumber | VARCHAR2[64] | Number of the top-level corporation to which the recipient belongs.<br>This field is valid only in the MT process where the recipient is a corporate member.<br>This field is empty when no corporation information exists.<br>This field can be left empty. |
| 403 | CalledVPNGroupNumber | VARCHAR2[64] | Number of the corporation to which the recipient belongs.<br>This field is valid only in the MT process where the recipient is a corporate member.<br>This field is empty when no corporation |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | information exists.<br>This field can be left empty. |
| 404 | CalledVPNShortNumber | VARCHAR2[10] | Short number of the recipient.<br>This field is valid only in the MT process where the recipient is a corporate member.<br>This field can be left empty. |
| 405 | GroupCallType | VARCHAR2[10] | Corporate call type.<br>This field is valid only when the charged party is a corporate subscriber. The options are as follows:<br>• **0**: non-corporate call<br>• **1**: corporate intra-network call<br>• **2**: corporate inter-network call<br>The default value is **0**.<br>This field cannot be left empty. |
| 406 | OnlineChargingFlag | VARCHAR2[1] | Online charging flag. The options are as follows:<br>• **0**: online charging<br>• **1**: offline charging<br>This field cannot be left empty. |
| 407 | StartTimeOfBillCycle | VARCHAR2[14] | Bill cycle start time of the charged subscriber when a charging event occurs.<br>Format: YYYYMMDDhhmmss<br>This field cannot be left empty. |
| 408 | LastEffectOffering | NUMBER[20] | ID of the last offering that takes effect.<br>The default value is **0**.<br>This field cannot be left empty. |
| 409 | OriginAddressType | NUMBER[10] | Original sender address type.<br>• **0**: email address<br>• **1**: MSISDN<br>• **2**: IPv4 address<br>• **3**: IPv6 address<br>• **4**: digital short code<br>• **5**: alphabetical and digital short code<br>• **6**: others<br>The value is reported by external systems.<br>This field cannot be left empty. |
| 410 | DestAddressType | NUMBER[10] | Destination address type. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **0**: email address<br>• **1**: MSISDN<br>• **2**: IPv4 address<br>• **3**: IPv6 address<br>• **4**: digital short code<br>• **5**: alphabetical and digital short code<br>• **6**: others<br>The value is reported by external systems.<br>This field cannot be left empty. |
| 411 | Message-Type | NUMBER[10] | MMS message type.<br>• **1**: m-send-req<br>• **2**: m-send-conf<br>• **3**: m-notification-ind<br>• **4**: m-notifyresp-ind<br>• **5**: m-retrieve-conf<br>• **6**: m-acknowledge-ind<br>• **7**: m-delivery-ind<br>• **8**: m-read-rec-ind<br>• **9**: m-read-orig-ind<br>• **10**: m-forward-req<br>• **11**: m-forward-conf<br>• **12**: m-mbox-store-conf<br>• **13**: m-mbox-view-conf<br>• **14**: m-mbox-upl<br>• **101**: MOAT<br>• **102**: AOMT<br>• **103**: MOMT<br>• **104**: MOET<br>• **105**: EOMT<br>• **106**: DlvRpt<br>• **107**: RdRpt<br>• **108**: Reply<br>• **109**: reserved<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>This field can be left empty. |
| 412 | VASP-Id | VARCHAR2[20] | Service provider ID.<br>The value is reported by the network side. If no value is reported, this field is left |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | empty.<br>This field can be left empty. |
| 413 | VAS-Id | VARCHAR2[20] | Service ID.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>This field can be left empty. |
| 414 | Service-Id | VARCHAR2[20] | Value-added service ID.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>This field can be left empty. |
| 415 | DTDiscount | NUMBER[10] | DT discount rate.<br>This field can be left empty. |
| 416 | OpposeMainOfferingID | NUMBER[20] | Primary offering ID of the peer party's number.<br>The default value is **0**.<br>This field cannot be left empty. |
| 417 | MainBalanceInfo | VARCHAR2[255] | This field is reserved. |
| 418 | ChgBalanceInfo | VARCHAR2[255] | This field is reserved. |
| 419 | ChgFreeUnitInfo | VARCHAR2[255] | This field is reserved. |
| 420 | UserState | VARCHAR2[10] | This field is reserved. |
| 421 | GroupPayFlag | NUMBER[10] | This field is reserved. |
| 422 | RoamingZoneID | VARCHAR2[20] | Roaming zone ID.<br>This field can be left empty. |
| 423 | PrimaryOfferChgAmt | NUMBER[20] | Primary offering rating amount.<br>The default value is 0.<br>This field cannot be left empty |

### 4.2.2.4 Extended Charging Service Information in a GPRS CDR

This topic describes extended fields in the charging service information in a GPRS CDR.

Table 4-7 describes extended fields in the charging service information in a GPRS CDR.

**Table 4-7** Extended charging service information in a GPRS CDR

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 352 | CallingPartyNumber | VARCHAR2[64] | Calling number.<br>The number formats are as follows:<br>• Fixed-line number: Country code + Area code + PSTN<br>• Mobile number: Country code + MSISDN<br>• URI format<br>This field cannot be left empty. |
| 353 | APN | VARCHAR2[22] | Access point.<br>The value is reported by the network side. If no value is reported, this field is left empty. If charging is implemented based on the access point, this field cannot be left empty. |
| 354 | URL | VARCHAR2[22] | Visited URL.<br>The value is reported by the network side. If no value is reported, this field is left empty. |
| 355 | CallingPartyIMSI | VARCHAR2[64] | International mobile subscriber identity (IMSI) of the calling party.<br>This field can be left empty.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>If the value comes in DCC message that value will be stored in CDR. If no value was sent, then the DB value will be stored in CDR. |
| 356 | AccessNetworkAddress | VARCHAR2[22] | Address for accessing the network.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>This field can be left empty. |
| 357 | GGSNAddress | VARCHAR2[22] | GGSN address.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>This field can be left empty. |
| 358 | CallingRoamInfo | VARCHAR2[20] | Roaming information about the calling party.<br>This field is used to analyze the calling party's roaming status. The field depends |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | on the information reported by the network and can be set to the value of fields such as **MSCAddress** or **IPAddress**. The value depends on the control parameter specifying the roaming analysis method.<br>This field can be left empty. |
| 359 | CallingCellID | VARCHAR2[20] | Cell ID of the calling party.<br>If the CBS does not need to analyze the visited area based on the cell ID, this field can be left empty.<br>The format is Three-digit mobile country code (MCC) + Two-digit mobile network code (MNC) + Five-digit location area code (LAC) + Five-digit cell ID, for example, **460002230320412**. |
| 360 | TimeStampOfSGSN | VARCHAR2[14] | Service start time reported by the SGSN or an external NE.<br>Format: YYYYMMDDhhmmss<br>This field can be left empty. |
| 361 | TimeZoneOfSGSN | NUMBER[10] | Time zone where the SGSN or an external NE locates.<br>• Empty: default time zone<br>• Non-empty: reported time zone<br>This field can be left empty. |
| 362 | BearerCapability | VARCHAR2[32] | Bearer capability.<br>This field is left empty.<br>This field is reserved. |
| 363 | ChargingTime | VARCHAR2[14] | Charging start time.<br>Format: YYYYMMDDhhmmss<br>This field can be left empty. |
| 364 | TotalFlux | NUMBER[20] | Total traffic, in bytes.<br>The default value is **0**.<br>This field cannot be left empty. |
| 365 | UpFlux | NUMBER[20] | Upstream traffic, in bytes.<br>The default value is **0**.<br>This field cannot be left empty. |
| 366 | DownFlux | NUMBER[20] | Downstream traffic, in bytes.<br>The default value is **0**.<br>This field cannot be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 367 | ElapseDuration | NUMBER[10] | Service duration, in seconds.<br>The default value is **0**.<br>This field cannot be left empty. |
| 368 | IMEI | VARCHAR2[24] | International mobile equipment identity.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>This field can be left empty. |
| 369 | ServiceID | VARCHAR2[20] | Service ID.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>This field can be left empty. |
| 370 | SPID | VARCHAR2[20] | SP ID.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>This field can be left empty. |
| 371 | CategoryID | VARCHAR2[20] | Category ID.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>This field can be left empty. |
| 372 | ContentID | VARCHAR2[20] | Content ID.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>This field can be left empty. |
| 373 | QoS | VARCHAR2[30] | Service quality.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>This field can be left empty. |
| 374 | BearerProtocolType | NUMBER[10] | Protocol type used by an SP to provide bearer services.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>This field can be left empty. |
| 375 | StartTime | VARCHAR2[14] | Data connection start time.<br>The value is reported by the network side. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | If no value is reported, this field is left empty.<br>This field can be left empty. |
| 376 | StopTime | VARCHAR2[14] | Data connection end time.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>This field can be left empty. |
| 377 | ChargingID | VARCHAR2[20] | Charging ID.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>This field can be left empty. |
| 378 | TransitionID | VARCHAR2[32] | Transition ID.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>This field can be left empty. |
| 379 | ServiceLevel | NUMBER[10] | Service level.<br>The value is reported by the network side. If no value is reported, this field is left empty.<br>This field can be left empty. |
| 380 | BrandID | NUMBER[20] | Brand ID.<br>The default value is **0**.<br>This field cannot be left empty. |
| 381 | MainOfferingID | NUMBER[20] | Primary offering ID.<br>The default value is **0**.<br>This field cannot be left empty. |
| 382 | ChargingPartyNumber | VARCHAR2[64] | Charged number.<br>The number formats are as follows:<br>• Fixed-line number: Area code + PSTN<br>• Mobile number: MSISDN<br>• URI format<br>This field cannot be left empty. |
| 383 | PayType | VARCHAR2[1] | Payment type of a subscriber. The options are as follows:<br>• **0**: prepaid<br>• **1**: postpaid |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **2**: hybrid<br>This field cannot be left empty. |
| 384 | ChargingType | VARCHAR2[1] | Charging type.<br>The options are as follows:<br>• **0**: by duration<br>• **1**: by traffic<br>This field cannot be left empty. |
| 385 | RoamState | VARCHAR2[1] | Roaming status of the charged party. The options are as follows:<br>• **0**: non-roaming<br>• **1**: roaming within a charging area<br>• **2**: roaming out of a charging area<br>• **3**: international roaming<br>The default value is **0**.<br>This field cannot be left empty. |
| 386 | CallingHomeCountryCode | NUMBER[10] | Home country code of the calling party.<br>The default value is **0**.<br>This field can be left empty. |
| 387 | CallingHomeAreaNumber | NUMBER[10] | Home area code of the calling party.<br>The default value is **0**.<br>This field can be left empty. |
| 388 | CallingHomeNetworkCode | NUMBER[10] | Home network code of the calling party.<br>The default value is **0**.<br>This field can be left empty. |
| 389 | CallingRoamCountryCode | NUMBER[10] | Roam-in country code of the calling party.<br>The default value is **0**.<br>This field can be left empty. |
| 390 | CallingRoamAreaNumber | NUMBER[10] | Roam-in area code of the calling party.<br>The default value is **0**.<br>This field can be left empty. |
| 391 | CallingRoamNetworkCode | NUMBER[10] | Roam-in network code of the calling party.<br>The default value is **0**.<br>This field can be left empty. |
| 392 | ServiceType | VARCHAR2[128] | List of product codes used to charge the charged party. Multiple product codes are separated with a colon (:). |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | This field can be left empty. |
| 393 | CallingNetwork Type | VARCHAR2[10] | Local network type. The options are as follows:<br>• **1**: GSM<br>• **2**: CDMA<br>• **3**: ADSL<br>• **4**: PSTN<br>• **5**: WiMAX<br>• Others: unknown<br>This field can be left empty. |
| 394 | CallingVPNTop GroupNumber | VARCHAR2[64] | Number of the top-level corporation to which the calling party belongs.<br>This field is empty when no corporation information exists.<br>This field can be left empty. |
| 395 | CallingVPNGro upNumber | VARCHAR2[64] | Number of the corporation to which the calling party belongs.<br>This field is empty when no corporation information exists.<br>This field can be left empty. |
| 396 | OnlineCharging Flag | VARCHAR2[1] | Online charging flag. The options are as follows:<br>• **0**: online charging<br>• **1**: offline charging<br>This field cannot be left empty. |
| 397 | StartTimeOfBill Cycle | VARCHAR2[14] | Bill cycle start time of the charged subscriber when a charging event occurs.<br>Format: YYYYMMDDhhmmss<br>This field cannot be left empty. |
| 398 | LastEffectOfferi ng | NUMBER[20] | ID of the last offering that takes effect.<br>The default value is **0**.<br>This field cannot be left empty. |
| 399 | DTDiscount | NUMBER[10] | DT discount rate.<br>The default value is **0**.<br>This field cannot be left empty. |
| 400 | RatingGroup | NUMBER[10] | Rating group ID. This field is set to **0** if there is only one MSCC and is set to the actual rating group ID if there are multiple MSCCs.<br>This field cannot be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 401 | HomeZoneID | NUMBER[10] | Indicates the home zone ID.<br>When a subscriber enjoys the home zone discount, the value of this field is the home zone ID of the area where the subscriber currently locates.<br>The default value is **0**.<br>This field cannot be left empty. |
| 402 | SpecialZoneID | NUMBER[10] | Indicates the special zone ID.<br>When a subscriber enjoys the special zone discount, the value of this field is the special zone ID of the area where the subscriber currently locates.<br>The default value is **0**.<br>This field cannot be left empty. |
| 403 | DataZoneID | NUMBER[10] | Indicates the data zone ID.<br>When a subscriber enjoys the data zone discount, the value of this field is the data zone ID of the area where the subscriber currently locates.<br>The default value is **0**.<br>This field cannot be left empty. |
| 404 | MainBalanceInfo | VARCHAR2[255] | This field is reserved. |
| 405 | ChgBalanceInfo | VARCHAR2[255] | This field is reserved. |
| 406 | ChgFreeUnitInfo | VARCHAR2[255] | This field is reserved. |
| 407 | UserState | VARCHAR2[10] | This field is reserved. |
| 408 | GroupPayFlag | NUMBER[10] | This field is reserved. |
| 409 | RATType | Number[10] | This field is reserved. |
| 410 | ChargePartyIndicator | VARCHAR2[255] | This field is reserved. |
| 411 | RoamingZoneID | VARCHAR2[20] | Roaming zone ID.<br>This field can be left empty. |
| 412 | PrimaryOfferChgAmt | NUMBER[20] | Primary offering rating amount.<br>The default value is 0.<br>This field cannot be left empty |
| 413 | ACCT_BAL_EXPIRE_TIME1 | DATE[14] | Expiration time of the 1st bonus account balance in the group from 202nd to 271st |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | fields. |
| 414 | ACCT_BAL_EXPIRE_TIME2 | DATE[14] | Expiration time of the 2nd bonus account balance in the group from 202nd to 271st fields. |
| 415 | ACCT_BAL_EXPIRE_TIME3 | DATE[14] | Expiration time of the 3rd bonus account balance in the group from 202nd to 271st fields. |
| 416 | ACCT_BAL_EXPIRE_TIME4 | DATE[14] | Expiration time of the 4th bonus account balance in the group from 202nd to 271st fields. |
| 417 | ACCT_BAL_EXPIRE_TIME5 | DATE[14] | Expiration time of the 5th bonus account balance in the group from 202nd to 271st fields. |
| 418 | ACCT_BAL_EXPIRE_TIME6 | DATE[14] | Expiration time of the 6th bonus account balance in the group from 202nd to 271st fields. |
| 419 | ACCT_BAL_EXPIRE_TIME7 | DATE[14] | Expiration time of the 7th bonus account balance in the group from 202nd to 271st fields. |
| 420 | ACCT_BAL_EXPIRE_TIME8 | DATE[14] | Expiration time of the 8th bonus account balance in the group from 202nd to 271st fields. |
| 421 | ACCT_BAL_EXPIRE_TIME9 | DATE[14] | Expiration time of the 9th bonus account balance in the group from 202nd to 271st fields. |
| 422 | ACCT_BAL_EXPIRE_TIME10 | DATE[14] | Expiration time of the 10th bonus account balance in the group from 202nd to 271st fields. |
| 423 | BONUS_FU_EXPIRE_TIME1 | DATE[14] | Expiration time of the 1st bonus free unit in the group from 272nd to 351st fields. |
| 424 | BONUS_FU_EXPIRE_TIME2 | DATE[14] | Expiration time of the 2nd bonus free unit in the group from 272nd to 351st fields. |
| 425 | BONUS_FU_EXPIRE_TIME3 | DATE[14] | Expiration time of the 3rd bonus free unit in the group from 272nd to 351st fields. |
| 426 | BONUS_FU_EXPIRE_TIME4 | DATE[14] | Expiration time of the 4th bonus free unit in the group from 272nd to 351st fields. |
| 427 | BONUS_FU_EXPIRE_TIME5 | DATE[14] | Expiration time of the 5th bonus free unit in the group from 272nd to 351st fields. |
| 428 | BONUS_FU_EXPIRE_TIME6 | DATE[14] | Expiration time of the 6th bonus free unit in the group from 272nd to 351st fields. |
| 429 | BONUS_FU_E | DATE[14] | Expiration time of the 7th bonus free unit |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | XPIRE_TIME7 | | in the group from 272nd to 351st fields. |
| 430 | BONUS_FU_EXPIRE_TIME8 | DATE[14] | Expiration time of the 8th bonus free unit in the group from 272nd to 351st fields. |
| 431 | BONUS_FU_EXPIRE_TIME9 | DATE[14] | Expiration time of the 9th bonus free unit in the group from 272nd to 351st fields. |
| 432 | BONUS_FU_EXPIRE_TIME10 | DATE[14] | Expiration time of the 10th bonus free unit in the group from 272nd to 351st fields. |

### 4.2.2.5 Extended Charging Service Information in a Recurring Charging CDR

This topic describes extended fields in the charging service information in a recurring charging CDR.

Table 4-8 describes extended fields in the charging service information in a recurring charging CDR.

**Table 4-8** Extended charging service information in a recurring charging CDR

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 352 | BrandID | NUMBER[20] | Brand ID.<br>This field can be left empty for account-level rentals.<br>This field can be left empty. |
| 353 | MainOfferingID | NUMBER[20] | Primary offering ID.<br>This field can be left empty for account-level rentals.<br>This field can be left empty. |
| 354 | PayType | VARCHAR2[1] | Payment type of a subscriber. The options are as follows:<br>• **0**: prepaid<br>• **1**: postpaid<br>• **2**: hybrid<br>This field can be left empty for account-level rentals.<br>This field can be left empty. |
| 355 | ChargingPartyNumber | VARCHAR2[64] | Charged number.<br>The number formats are as follows:<br>• Fixed-line number: Area code + PSTN<br>• Mobile number: MSISDN |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • URI format<br>When **ChargingPartyType** is set to **1** or **2**, this field can be left empty. |
| 356 | ChargingPartyType | VARCHAR2[1] | Type of the charged party. The options are as follows:<br>• **0**: subscriber<br>• **1**: customer<br>• **2**: subscriber group<br>This field cannot be left empty. |
| 357 | CycleBeginTime | VARCHAR2[14] | Cycle start time of a rental product.<br>Format: YYYYMMDDHHMMSS<br>This field cannot be left empty. |
| 358 | CycleEndTime | VARCHAR2[14] | Cycle end time of a rental product.<br>Format: YYYYMMDDHHMMSS<br>This field cannot be left empty. |
| 359 | CycleType | NUMBER[10] | Recurring charging cycle type.<br>• **1**: bill cycle<br>• **2**: days<br>• **3**: weeks<br>• **4**: months<br>• **5**: natural months<br>• **6**: years<br>• **7**: hours<br>• **8**: calendar day<br>• **9**: calendar week<br>• **10**: calendar year<br>The options can be customized.<br>This field cannot be left empty. |
| 360 | CycleLength | NUMBER[10] | Cycle length.<br>The default value is **0**.<br>This field cannot be left empty. |
| 361 | ElapseCycles | NUMBER[10] | Sequence number of a cycle. The value can be the sequence number of a cycle in which the rental fails to be collected.<br>The default value is **0**.<br>This field cannot be left empty. |
| 362 | InnerCycleBeginTime | VARCHAR2[14] | Start time of a subcycle. The value may be different from that of the **CycleBeginTime** field if rentals are prorated upon subscription or the |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | recurring charges are collected by day.<br>For example, if a subscriber subscribes to a monthly offering on October 15, the cycle ranges from 00:00 on October 1 to 23:59 on October 31, and the subcycle start time is the subscription time on October 15.<br>Format: YYYYMMDDhhmmss<br>This field cannot be left empty. |
| 363 | InnerCycleEndTime | VARCHAR2[14] | End time of a subcycle. The value may be different from that of the **CycleEndTime** field if rentals are prorated upon unsubscription or the recurring charges are collected by day.<br>Format: YYYYMMDDhhmmss<br>This field cannot be left empty. |
| 364 | ProductID | VARCHAR2[20] | ID of a product or product package corresponding to a rental or package.<br>This field is reserved. |
| 365 | OfferingID | NUMBER[20] | Key of the offering to which a rental product belongs.<br>The default value is **0**.<br>This field cannot be left empty. |
| 366 | OfferingInstID | NUMBER[20] | Subscription key of the offering to which a rental product belongs.<br>The default value is **0**.<br>This field cannot be left empty. |
| 367 | OrderStatus | VARCHAR2[1] | Status of a subscription relationship. The options are as follows:<br>• **0**: normal<br>• **1**: suspended<br>• **2**: initial<br>• **3**: expired<br>This field can be left empty. |
| 368 | ProrateFlag | VARCHAR2[1] | Indicates whether to prorate the rental. The options are as follows:<br>• **0**: no<br>• **1**: yes<br>This field is reserved. |
| 369 | StartTimeOfBillCycle | VARCHAR2[14] | Start time of a bill cycle.<br>This field cannot be left empty. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 370 | ChargePartyIndicator | VARCHAR2[1] | Charged party. The options are as follows:<br>• **1**: calling party<br>• **2**: called party<br>• **3**: third party<br>• **4**: parent or child card subscriber<br>• **5**: calling party and corporate<br>This field has a fixed value of **1**.<br>This field cannot be left empty. |
| 371 | PosRentMode | VARCHAR2[1] | Rental deduction mode for postpaid subscribers. The options are as follows:<br>• A: The rental is collected at the beginning of a bill cycle.<br>• P: The rental is collected at the end of a bill cycle.<br>This field cannot be left empty for postpaid and hybrid subscribers. For prepaid subscribers, the fix value is **A**. |
| 372 | TriggerMode | VARCHAR2[1] | Trigger mode.<br>• **0**: recurring rental collection<br>• **1**: rental collection upon offering subscription<br>• **2**: rental collection upon offering unsubscription<br>• **3**: rental re-deduction upon recharge, transfer, or adjustment<br>• **4**: advance triggering of the real-time charging process (For example, there are five million subscribers at a site and a subscriber triggers real-time charging requests at 00:00 when the subscriber makes a call or goes online. If the recurring charge collection task has not been executed for the subscriber in this scenario, real-time rental collection is triggered to ensure that the recurring charge is collected in a timely manner.)<br>• **5**: rental collection triggered by WebService requests sent from third-party systems (This option is available only to specific sites.)<br>• **6**: rental collection triggered by advance rental collection task (This option is available only to specific sites.) |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **7**: real-time rental collection triggered by recharge, transfer, or adjustment<br>• **8**: rental collection triggered by first time activation<br>This field cannot be left empty. |
| 373 | ExecuteFlag | VARCHAR2[1] | Indicates whether a rental is collected at the beginning or end of a cycle. The options are as follows:<br>• At the beginning of a cycle<br>• At the end of a cycle<br>This field is reserved. |
| 374 | ProductCode | VARCHAR2[64] | This field is reserved. |
| 375 | MainBalanceInfo | VARCHAR2[255] | This field is reserved. |
| 376 | ChgBalanceInfo | VARCHAR2[255] | This field is reserved. |
| 377 | ChgFreeUnitInfo | VARCHAR2[255] | This field is reserved. |
| 378 | UserState | VARCHAR2[10] | This field is reserved. |
| 379 | CallingVPNTopGroupNumber | VARCHAR2[64] | This field is reserved. |
| 380 | CallingVPNGroupNumber | VARCHAR2[64] | This field is reserved. |
| 381 | GroupPayFlag | NUMBER[10] | This field is reserved. |
| 382 | OperatorID | VARCHAR2[255] | The external system operator id. |
| 383 | FAF Indicator | Varchar2[20] | This parameter is the FN offer id. If it is not FN Operation then this field can be NULL. |
| 384 | ACCT_BAL_EXPIRE_TIME1 | DATE[14] | Expiration time of the 1st bonus account balance in the group from 202nd to 271st fields. |
| 385 | ACCT_BAL_EXPIRE_TIME2 | DATE[14] | Expiration time of the 2nd bonus account balance in the group from 202nd to 271st fields. |
| 386 | ACCT_BAL_EXPIRE_TIME3 | DATE[14] | Expiration time of the 3rd bonus account balance in the group from 202nd to 271st fields. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 387 | ACCT_BAL_EXPIRE_TIME4 | DATE[14] | Expiration time of the 4th bonus account balance in the group from 202nd to 271st fields. |
| 388 | ACCT_BAL_EXPIRE_TIME5 | DATE[14] | Expiration time of the 5th bonus account balance in the group from 202nd to 271st fields. |
| 389 | ACCT_BAL_EXPIRE_TIME6 | DATE[14] | Expiration time of the 6th bonus account balance in the group from 202nd to 271st fields. |
| 390 | ACCT_BAL_EXPIRE_TIME7 | DATE[14] | Expiration time of the 7th bonus account balance in the group from 202nd to 271st fields. |
| 391 | ACCT_BAL_EXPIRE_TIME8 | DATE[14] | Expiration time of the 8th bonus account balance in the group from 202nd to 271st fields. |
| 392 | ACCT_BAL_EXPIRE_TIME9 | DATE[14] | Expiration time of the 9th bonus account balance in the group from 202nd to 271st fields. |
| 393 | ACCT_BAL_EXPIRE_TIME10 | DATE[14] | Expiration time of the 10th bonus account balance in the group from 202nd to 271st fields. |
| 394 | BONUS_FU_EXPIRE_TIME1 | DATE[14] | Expiration time of the 1st bonus free unit in the group from 272nd to 351st fields. |
| 395 | BONUS_FU_EXPIRE_TIME2 | DATE[14] | Expiration time of the 2nd bonus free unit in the group from 272nd to 351st fields. |
| 396 | BONUS_FU_EXPIRE_TIME3 | DATE[14] | Expiration time of the 3rd bonus free unit in the group from 272nd to 351st fields. |
| 397 | BONUS_FU_EXPIRE_TIME4 | DATE[14] | Expiration time of the 4th bonus free unit in the group from 272nd to 351st fields. |
| 398 | BONUS_FU_EXPIRE_TIME5 | DATE[14] | Expiration time of the 5th bonus free unit in the group from 272nd to 351st fields. |
| 399 | BONUS_FU_EXPIRE_TIME6 | DATE[14] | Expiration time of the 6th bonus free unit in the group from 272nd to 351st fields. |
| 400 | BONUS_FU_EXPIRE_TIME7 | DATE[14] | Expiration time of the 7th bonus free unit in the group from 272nd to 351st fields. |
| 401 | BONUS_FU_EXPIRE_TIME8 | DATE[14] | Expiration time of the 8th bonus free unit in the group from 272nd to 351st fields. |
| 402 | BONUS_FU_EXPIRE_TIME9 | DATE[14] | Expiration time of the 9th bonus free unit in the group from 272nd to 351st fields. |
| 403 | BONUS_FU_EXPIRE_TIME10 | DATE[14] | Expiration time of the 10th bonus free unit in the group from 272nd to 351st |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | fields. |

### 4.2.2.6 Extended Charging Service Information in a Management Flow CDR

This topic describes extended fields in the charging service information in a management flow CDR.

Table 4-9 describes extended fields in the charging service information in a management flow CDR.

**Table 4-9** Extended charging service information in a management flow CDR

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 352 | CallingPartyNumber | VARCHAR2[64] | Calling number.<br>The number formats are as follows:<br>• Fixed-line number: Country code + Area code + PSTN<br>• Mobile number: Country code + MSISDN<br>• URI format<br>This field cannot be left empty. |
| 353 | OperationID | NUMBER[10] | Operation ID.<br>The values are defined by the BM. For example, value **4057010** indicates the operation of changing offerings for subscribers.<br>The options can be customized based on site requirements.<br>This field cannot be left empty. |
| 354 | OperationType | NUMBER[10] | Operation type.<br>The options are as follows for the FN and Home Zone management services:<br>• **1**: add<br>• **2**: modify<br>• **3**: delete<br>• **0**: unspecified<br>The options can be customized based on operation IDs.<br>This field cannot be left empty. |
| 355 | BrandID | NUMBER[20] | Brand ID.<br>The default value is **0**. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | This field cannot be left empty. |
| 356 | MainOfferingID | NUMBER[20] | Primary offering ID.<br>The default value is **0**.<br>This field cannot be left empty. |
| 357 | PayType | VARCHAR2[4] | Payment type of a subscriber. The options are as follows:<br>• **0**: prepaid<br>• **1**: postpaid<br>• **2**: hybrid<br>This field cannot be left empty. |
| 358 | StartTimeOfBillCycle | VARCHAR2[14] | Start time of a bill cycle.<br>Format: YYYYMMDDhhmmss<br>This field cannot be left empty. |
| 359 | Reserve | VARCHAR2[20] | This field is reserved.<br>This field can be left empty. |
| 360 | Merchant | VARCHAR2[20] | This field is reserved.<br>This field can be left empty. |
| 361 | Service | VARCHAR2[20] | This field is reserved.<br>This field can be left empty. |
| 362 | MainBalanceInfo | VARCHAR2[255] | This field is reserved. |
| 363 | ChgBalanceInfo | VARCHAR2[255] | This field is reserved. |
| 364 | ChgFreeUnitInfo | VARCHAR2[255] | This field is reserved. |
| 365 | UserState | VARCHAR2[10] | This field is reserved. |
| 366 | OldUserState | VARCHAR2[10] | This field is reserved. |
| 367 | ValidDayAdded | NUMBER[10] | This field is reserved. |
| 368 | Oper_ID | NUMBER[20] | This field is reserved. |
| 369 | SPID | VARCHAR2[20] | This field is reserved. |
| 370 | ServiceID | VARCHAR2[20] | This field is reserved. |
| 371 | ServiceType | NUMBER[10] | This field is reserved. |
| 372 | ContentID | VARCHAR2[20 | This field is reserved. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | ] | |
| 373 | url | VARCHAR2[23] | This field is reserved. |
| 374 | TransactionID | VARCHAR2[32] | This field is reserved. |
| 375 | OldMainOfferingID | NUMBER[10] | This field is reserved. |
| 376 | AdditionalInfo | VARCHAR2[256] | Service additional infomation.<br>Records service additional information and redundant information. In most scenarios, the information is useful for specified carriers.<br>This field can be left empty. |
| 377 | NewOfferingID | NUMBER[10] | This field is reserved. |
| 378 | ExpireTimeofNewOffering | VARCHAR2[14] | This field is reserved. |
| 379 | ChargePartyIndicator | VARCHAR2[255] | This field is reserved. |
| 380 | AccessMethod | NUMBER[10] | This field is reserved. |
| 381 | OperatorID | VARCHAR2[255] | The external system operator id. |
| 382 | FAF Indicator | Varchar2[20] | This parameter is the FN offer id. If it is not FN Operation then this field can be NULL. |
| 383 | FAF Number | Varchar2[255] | This parameter is the FN number which is modified/added/deleted in the FN operation. If it is not FN Operation then this field can be NULL. |
| 384 | ACCT_BAL_EXPIRE_TIME1 | DATE[14] | Expiration time of the 1st bonus account balance in the group from 202nd to 271st fields. |
| 385 | ACCT_BAL_EXPIRE_TIME2 | DATE[14] | Expiration time of the 2nd bonus account balance in the group from 202nd to 271st fields. |
| 386 | ACCT_BAL_EXPIRE_TIME3 | DATE[14] | Expiration time of the 3rd bonus account balance in the group from 202nd to 271st fields. |
| 387 | ACCT_BAL_EXPIRE_TIME4 | DATE[14] | Expiration time of the 4th bonus account balance in the group from 202nd to 271st fields. |
| 388 | ACCT_BAL_E | DATE[14] | Expiration time of the 5th bonus account |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | XPIRE_TIME5 | | balance in the group from 202nd to 271st fields. |
| 389 | ACCT_BAL_EXPIRE_TIME6 | DATE[14] | Expiration time of the 6th bonus account balance in the group from 202nd to 271st fields. |
| 390 | ACCT_BAL_EXPIRE_TIME7 | DATE[14] | Expiration time of the 7th bonus account balance in the group from 202nd to 271st fields. |
| 391 | ACCT_BAL_EXPIRE_TIME8 | DATE[14] | Expiration time of the 8th bonus account balance in the group from 202nd to 271st fields. |
| 392 | ACCT_BAL_EXPIRE_TIME9 | DATE[14] | Expiration time of the 9th bonus account balance in the group from 202nd to 271st fields. |
| 393 | ACCT_BAL_EXPIRE_TIME10 | DATE[14] | Expiration time of the 10th bonus account balance in the group from 202nd to 271st fields. |
| 394 | BONUS_FU_EXPIRE_TIME1 | DATE[14] | Expiration time of the 1st bonus free unit in the group from 272nd to 351st fields. |
| 395 | BONUS_FU_EXPIRE_TIME2 | DATE[14] | Expiration time of the 2nd bonus free unit in the group from 272nd to 351st fields. |
| 396 | BONUS_FU_EXPIRE_TIME3 | DATE[14] | Expiration time of the 3rd bonus free unit in the group from 272nd to 351st fields. |
| 397 | BONUS_FU_EXPIRE_TIME4 | DATE[14] | Expiration time of the 4th bonus free unit in the group from 272nd to 351st fields. |
| 398 | BONUS_FU_EXPIRE_TIME5 | DATE[14] | Expiration time of the 5th bonus free unit in the group from 272nd to 351st fields. |
| 399 | BONUS_FU_EXPIRE_TIME6 | DATE[14] | Expiration time of the 6th bonus free unit in the group from 272nd to 351st fields. |
| 400 | BONUS_FU_EXPIRE_TIME7 | DATE[14] | Expiration time of the 7th bonus free unit in the group from 272nd to 351st fields. |
| 401 | BONUS_FU_EXPIRE_TIME8 | DATE[14] | Expiration time of the 8th bonus free unit in the group from 272nd to 351st fields. |
| 402 | BONUS_FU_EXPIRE_TIME9 | DATE[14] | Expiration time of the 9th bonus free unit in the group from 272nd to 351st fields. |
| 403 | BONUS_FU_EXPIRE_TIME10 | DATE[14] | Expiration time of the 10th bonus free unit in the group from 272nd to 351st fields. |

 Copyright © Huawei Technologies Co., Ltd. 

### 4.2.2.7 Extended Charging Service Information in the Content-based Charging Process

This topic describes extended fields in the charging service information in the content-based charging process.

Table 4-10 describes extended fields in the charging service information in the content-based charging process.

**Table 4-10** Extended charging service information in the content-based charging process

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 352 | CallingPartyNumber | VARCHAR2[64] | Calling number.<br>The number formats are as follows:<br>• Fixed-line number: Country code + Area code + PSTN<br>• Mobile number: Country code + MSISDN<br>• URI format<br>This field cannot be left empty. |
| 353 | CallingPartyIMSI | VARCHAR2[64] | IMSI of the calling party. The value is reported by the network side. If no value is reported, this field is left empty.<br>If the value comes in DCC message that value will be stored in CDR. If no value was sent, then the DB value will be stored in CDR.<br>This field can be left empty. |
| 354 | ChargingType | VARCHAR2[2] | Charging type. The value is reported by external systems. If no value is reported, this field is left empty.<br>Reserved. |
| 355 | ChargingUsageType | VARCHAR2[4] | Usage type. The options are as follows:<br>• **0**: by times<br>• **1**: by traffic<br>• **2**: by duration<br>The value is reported by external systems. If no value is reported, this field is left empty. |
| 356 | ChargeCode | VARCHAR2[16] | External charge code.<br>The value is recorded if external systems transfer this field.<br>This field is reserved. |
| 357 | FreeIndicator | VARCHAR2[1] | Exemption flag.<br>This field is reserved. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 358 | SPID | VARCHAR2[32] | SP ID. The value is reported by external systems. If no value is reported, this field is left empty. |
| 359 | CPID | VARCHAR2[32] | CP ID. The value is reported by external systems. If no value is reported, this field is left empty. |
| 360 | ServiceID | VARCHAR2[32] | Service ID.<br>The value is reported by external systems. If this field is used for charging, it must be reported and recorded. |
| 361 | ContentID | VARCHAR2[32] | Content ID.<br>The value is reported by external systems. If this field is used for charging, it must be reported and recorded. |
| 362 | ServiceType | VARCHAR2[32] | Service type, for example, news or weather broadcast.<br>The value is reported by external systems. If this field is used for charging, it must be reported and recorded. |
| 363 | ContentType | NUMBER[10] | Content type, for example, image, music, or movie.<br>The value is reported by external systems. If this field is used for charging, it must be reported and recorded. |
| 364 | ServiceCapability | NUMBER[10] | Service capability. The options are as follows:<br>• **0**: general<br>• **1**: SMS<br>• **2**: MSM<br>• **3**: WAP<br>• **4**: LCS<br>• **5**: streaming<br>• **6**: download<br>The value is defined and reported by external systems. The CBS records the value and uses it for charging.<br>This field is reserved and has a fixed value of **0**. |
| 365 | ProvisionType | NUMBER[10] | Content presentation type.<br>The options are as follows:<br>• **104**: movie series<br>• **105**: album |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **111**: RingBox<br>• **117**: TV series<br>This field is reserved and has a fixed value of **0**. |
| 366 | CategoryType | VARCHAR2[24] | Node type. If no value is reported, this field is left empty.<br>This field is reserved. |
| 367 | ProductCode | VARCHAR2[32] | Product code.<br>The value is defined and reported by external systems. The CBS records the value. |
| 368 | Times | NUMBER[20] | Number of use times.<br>The value is reported by external systems. If no value is reported, this field is left empty. |
| 369 | Duration | NUMBER[20] | Usage duration, in seconds.<br>The value is reported by external systems. If no value is reported, this field is left empty. |
| 370 | InputOctets | NUMBER[20] | Upstream traffic, in bytes.<br>The value is reported by external systems. If no value is reported, this field is left empty. |
| 371 | OutputOctets | NUMBER[20] | Downstream traffic, in bytes.<br>The value is reported by external systems. If no value is reported, this field is left empty. |
| 372 | TotalOctets | NUMBER[20] | Total traffic, in bytes.<br>The value is reported by external systems. If no value is reported, this field is left empty. |
| 373 | ServiceDelivery Status | NUMBER[10] | Service delivery status.<br>This field is reserved. |
| 374 | Remark | VARCHAR2[256] | Remarks.<br>This field is reserved. |
| 375 | BrandID | NUMBER[20] | Subscriber brand ID.<br>The default value is **0**.<br>This field cannot be left empty. |
| 376 | MainOfferingID | NUMBER[20] | Primary offering ID.<br>The default value is **0**. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | This field cannot be left empty. |
| 377 | ChargingPartyNumber | VARCHAR2[64] | Charged number.<br>The number formats are as follows:<br>• Fixed-line number: Area code + PSTN<br>• Mobile number: MSISDN<br>• URI format<br>This field cannot be left empty. |
| 378 | CallingNetworkType | VARCHAR2[10] | Type of the access network. The options are as follows:<br>• **1**: GSM<br>• **2**: CDMA<br>• **3**: ADSL<br>• **4**: PSTN<br>• **5**: WiMAX<br>• Others: unknown<br>This field cannot be left empty. |
| 379 | CallingVPNTopGroupNumber | VARCHAR2[64] | Number of the top-level corporation to which the calling party belongs.<br>This field is empty when no corporation information exists.<br>This field can be left empty. |
| 380 | CallingVPNGroupNumber | VARCHAR2[64] | Number of the corporation to which the calling party belongs.<br>This field is empty when no corporation information exists.<br>This field can be left empty. |
| 381 | OnlineChargingFlag | NUMBER[10] | Online charging flag. The options are as follows:<br>• **0**: online charging<br>• **1**: offline charging<br>This field cannot be left empty. |
| 382 | StartTimeOfBillCycle | VARCHAR2[14] | Start time of a bill cycle.<br>Format: YYYYMMDDhhmmss<br>This field cannot be left empty. |
| 383 | LastEffectOffering | NUMBER[20] | ID of the last offering that takes effect.<br>The default value is **0**.<br>This field cannot be left empty. |
| 384 | RequestAction | NUMBER[10] | Request type. The options are as follows: |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | • **0**: fee deduction<br>• **1**: refund<br>This field cannot be left empty. |
| 385 | MainBalanceInfo | VARCHAR2[255] | This field is reserved. |
| 386 | ChgBalanceInfo | VARCHAR2[255] | This field is reserved. |
| 387 | ChgFreeUnitInfo | VARCHAR2[255] | This field is reserved. |
| 388 | UserState | VARCHAR2[10] | This field is reserved. |
| 389 | GroupPayFlag | NUMBER[10] | This field is reserved. |
| 390 | PayType | VARCHAR2[1] | This field is reserved. |
| 391 | TransactionID | VARCHAR2[32] | This field is reserved. |
| 392 | AdditionalInfo | VARCHAR2[255] | This field is reserved. |
| 393 | ChargeMode | NUMBER[10] | This field is reserved. |
| 394 | CDRProductID | VARCHAR2[20] | This field is reserved. |
| 395 | CDRChargeMode | NUMBER[10] | This field is reserved. |
| 396 | CDRTimes | NUMBER[10] | This field is reserved. |
| 397 | CDRDuration | NUMBER[10] | This field is reserved. |
| 398 | CDRVolume | NUMBER[10] | This field is reserved. |
| 399 | CDRCDRType | NUMBER[10] | This field is reserved. |
| 400 | CDRServiceType | NUMBER[10] | This field is reserved. |
| 401 | CDRBeginTime | VARCHAR2[14] | This field is reserved. |
| 402 | CDREndTime | VARCHAR2[14] | This field is reserved. |
| 403 | CDRPkgSpid | VARCHAR2[20] | This field is reserved. |
| 404 | CDRPkgServiceid | VARCHAR2[20] | This field is reserved. |
| 405 | CDRPkgProduct | VARCHAR2[20 | This field is reserved. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | id | ] | |
| 406 | CDRSPName | VARCHAR2[20] | This field is reserved. |
| 407 | CDRServiceName | VARCHAR2[20] | This field is reserved. |
| 408 | ChargePartyIndicator | VARCHAR2[255] | This field is reserved. |
| 409 | Merchant | VARCHAR2[20] | This field is reserved. |
| 410 | Service | VARCHAR2[20] | This field is reserved. |
| 411 | ACCT_BAL_EXPIRE_TIME1 | DATE[14] | Expiration time of the 1st bonus account balance in the group from 202nd to 271st fields. |
| 412 | ACCT_BAL_EXPIRE_TIME2 | DATE[14] | Expiration time of the 2nd bonus account balance in the group from 202nd to 271st fields. |
| 413 | ACCT_BAL_EXPIRE_TIME3 | DATE[14] | Expiration time of the 3rd bonus account balance in the group from 202nd to 271st fields. |
| 414 | ACCT_BAL_EXPIRE_TIME4 | DATE[14] | Expiration time of the 4th bonus account balance in the group from 202nd to 271st fields. |
| 415 | ACCT_BAL_EXPIRE_TIME5 | DATE[14] | Expiration time of the 5th bonus account balance in the group from 202nd to 271st fields. |
| 416 | ACCT_BAL_EXPIRE_TIME6 | DATE[14] | Expiration time of the 6th bonus account balance in the group from 202nd to 271st fields. |
| 417 | ACCT_BAL_EXPIRE_TIME7 | DATE[14] | Expiration time of the 7th bonus account balance in the group from 202nd to 271st fields. |
| 418 | ACCT_BAL_EXPIRE_TIME8 | DATE[14] | Expiration time of the 8th bonus account balance in the group from 202nd to 271st fields. |
| 419 | ACCT_BAL_EXPIRE_TIME9 | DATE[14] | Expiration time of the 9th bonus account balance in the group from 202nd to 271st fields. |
| 420 | ACCT_BAL_EXPIRE_TIME10 | DATE[14] | Expiration time of the 10th bonus account balance in the group from 202nd to 271st fields. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 421 | BONUS_FU_EXPIRE_TIME1 | DATE[14] | Expiration time of the 1st bonus free unit in the group from 272nd to 351st fields. |
| 422 | BONUS_FU_EXPIRE_TIME2 | DATE[14] | Expiration time of the 2nd bonus free unit in the group from 272nd to 351st fields. |
| 423 | BONUS_FU_EXPIRE_TIME3 | DATE[14] | Expiration time of the 3rd bonus free unit in the group from 272nd to 351st fields. |
| 424 | BONUS_FU_EXPIRE_TIME4 | DATE[14] | Expiration time of the 4th bonus free unit in the group from 272nd to 351st fields. |
| 425 | BONUS_FU_EXPIRE_TIME5 | DATE[14] | Expiration time of the 5th bonus free unit in the group from 272nd to 351st fields. |
| 426 | BONUS_FU_EXPIRE_TIME6 | DATE[14] | Expiration time of the 6th bonus free unit in the group from 272nd to 351st fields. |
| 427 | BONUS_FU_EXPIRE_TIME7 | DATE[14] | Expiration time of the 7th bonus free unit in the group from 272nd to 351st fields. |
| 428 | BONUS_FU_EXPIRE_TIME8 | DATE[14] | Expiration time of the 8th bonus free unit in the group from 272nd to 351st fields. |
| 429 | BONUS_FU_EXPIRE_TIME9 | DATE[14] | Expiration time of the 9th bonus free unit in the group from 272nd to 351st fields. |
| 430 | BONUS_FU_EXPIRE_TIME10 | DATE[14] | Expiration time of the 10th bonus free unit in the group from 272nd to 351st fields. |

### 4.2.2.8 Extended Charging Service Information in a Resource Clearance CDR

This topic describes extended fields in the charging service information in a resource clearance CDR.

Table 4-11 describes extended fields in the charging service information in a resource clearance CDR.

**Table 4-11** Extended charging service information in a resource clearance CDR

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 352 | BrandID | NUMBER[10] | This field is reserved. |
| 353 | PrimaryOfferingID | NUMBER[10] | This field is reserved. |
| 354 | PaymentType | VARCHAR2[1] | This field is reserved. |
| 355 | UserState | VARCHAR2[10] | This field is reserved. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 356 | DisconnectionReason | Varchar2[1] | 0: LifeCycle change<br>1: Subscriber deletion |
| 357 | InitialAmount | NUMBER[20] | Initial loan amount. |
| 358 | InitialLoanPoundage | NUMBER[20] | Initial service charges to be paid by the end customer. |
| 359 | PaidAmount | NUMBER[20] | Paid amount (LoanAmt + LoanPoundage). |
| 360 | RemainingAmount | NUMBER[20] | Remaining amount to be paid (LoanAmt + LoanPoundage). |
| 361 | ACCT_BAL_EXPIRE_TIME1 | DATE[14] | Expiration time of the 1st bonus account balance in the group from 202nd to 271st fields. |
| 362 | ACCT_BAL_EXPIRE_TIME2 | DATE[14] | Expiration time of the 2nd bonus account balance in the group from 202nd to 271st fields. |
| 363 | ACCT_BAL_EXPIRE_TIME3 | DATE[14] | Expiration time of the 3rd bonus account balance in the group from 202nd to 271st fields. |
| 364 | ACCT_BAL_EXPIRE_TIME4 | DATE[14] | Expiration time of the 4th bonus account balance in the group from 202nd to 271st fields. |
| 365 | ACCT_BAL_EXPIRE_TIME5 | DATE[14] | Expiration time of the 5th bonus account balance in the group from 202nd to 271st fields. |
| 366 | ACCT_BAL_EXPIRE_TIME6 | DATE[14] | Expiration time of the 6th bonus account balance in the group from 202nd to 271st fields. |
| 367 | ACCT_BAL_EXPIRE_TIME7 | DATE[14] | Expiration time of the 7th bonus account balance in the group from 202nd to 271st fields. |
| 368 | ACCT_BAL_EXPIRE_TIME8 | DATE[14] | Expiration time of the 8th bonus account balance in the group from 202nd to 271st fields. |
| 369 | ACCT_BAL_EXPIRE_TIME9 | DATE[14] | Expiration time of the 9th bonus account balance in the group from 202nd to 271st fields. |
| 370 | ACCT_BAL_EXPIRE_TIME10 | DATE[14] | Expiration time of the 10th bonus account balance in the group from 202nd to 271st fields. |
| 371 | BONUS_FU_EXPIRE_TIME1 | DATE[14] | Expiration time of the 1st bonus free unit in the group from 272nd to 351st fields. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 372 | BONUS_FU_EXPIRE_TIME2 | DATE[14] | Expiration time of the 2nd bonus free unit in the group from 272nd to 351st fields. |
| 373 | BONUS_FU_EXPIRE_TIME3 | DATE[14] | Expiration time of the 3rd bonus free unit in the group from 272nd to 351st fields. |
| 374 | BONUS_FU_EXPIRE_TIME4 | DATE[14] | Expiration time of the 4th bonus free unit in the group from 272nd to 351st fields. |
| 375 | BONUS_FU_EXPIRE_TIME5 | DATE[14] | Expiration time of the 5th bonus free unit in the group from 272nd to 351st fields. |
| 376 | BONUS_FU_EXPIRE_TIME6 | DATE[14] | Expiration time of the 6th bonus free unit in the group from 272nd to 351st fields. |
| 377 | BONUS_FU_EXPIRE_TIME7 | DATE[14] | Expiration time of the 7th bonus free unit in the group from 272nd to 351st fields. |
| 378 | BONUS_FU_EXPIRE_TIME8 | DATE[14] | Expiration time of the 8th bonus free unit in the group from 272nd to 351st fields. |
| 379 | BONUS_FU_EXPIRE_TIME9 | DATE[14] | Expiration time of the 9th bonus free unit in the group from 272nd to 351st fields. |
| 380 | BONUS_FU_EXPIRE_TIME10 | DATE[14] | Expiration time of the 10th bonus free unit in the group from 272nd to 351st fields. |

### 4.2.2.9 Extended Charging Service Information in a First Time Activation CDR

An activation CDR is generated during activation. This topic describes extended fields in the charging service information in an activation CDR.

Table 4-12 describes extended fields in the charging service information in an activation CDR.

**Table 4-12** Extended charging service information in an activation CDR

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 352 | BrandID | NUMBER[10] | Brand ID.<br>The default value is **0**.<br>This field cannot be left empty. |
| 353 | PrimaryOfferingID | NUMBER[10] | Primary offering ID.<br>The default value is **0**.<br>This field cannot be left empty. |
| 354 | PaymentType | VARCHAR2[1] | Payment type of a subscriber. By default, the value is the payment type in the subscriber attribute table. The options are |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | as follows:<br>• **0**: prepaid<br>• **1**: postpaid<br>• **2**: hybrid<br>This field cannot be left empty. |
| 355 | OldUserStat | VARCHAR2[1] | Original subscriber status.<br>• **1**: idle<br>• **2**: active<br>• **3**: barred<br>• **4**: suspended<br>• **8**: pre-deregistered<br>• **9**: deregistered<br>Options 1 and 2 are fixed, and options 3 to 9 can be customized based on the site requirements.<br>This field cannot be left empty. |
| 356 | CurrUserStat | VARCHAR2[1] | Current subscriber status.<br>• **1**: inactive<br>• **2**: active<br>• **3**: barred<br>• **4**: suspended<br>• **8**: pre-deregistered<br>• **9**: deregistered<br>Options 1 and 2 are fixed, and options 3 to 9 can be customized based on the site requirements.<br>This field cannot be left empty. |
| 357 | BillCycleID | VARCHAR2[10] | Bill cycle ID.<br>This field cannot be left empty. |
| 358 | ChgBalanceInfo | VARCHAR2[1024] | This field is reserved. |
| 359 | ChgFreeUnitInfo | VARCHAR2[1024] | This field is reserved. |
| 360 | MainBalanceInfo | VARCHAR2[255] | This field is reserved. |
| 361 | UserState | VARCHAR2[10] | This field is reserved. |
| 362 | OldUserState | VARCHAR2[10] | This field is reserved. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 363 | Oper_ID | NUMBER[20] | This field is reserved. |
| 364 | THIRD_PARTY_NUMBER | VARCHAR2[32] | This field is reserved. |
| 365 | EXT_TRANS_ID | VARCHAR2[32] | This field is reserved. |
| 366 | EXT_TRANS_TYPE | VARCHAR2[32] | This field is reserved. |
| 367 | ACCESS_METHOD | NUMBER[10] | This field is reserved. |
| 368 | RechargeCellID | VARCHAR2[20] | This field is reserved. |
| 369 | AgentName | VARCHAR2[64] | This field is reserved. |
| 370 | AdditionalInfo | VARCHAR2[256] | This field is reserved. |
| 371 | SubIdentityType | NUMBER[10] | This field is reserved. |
| 372 | ACCT_BAL_EXPIRE_TIME1 | DATE[14] | Expiration time of the 1st bonus account balance in the group from 202nd to 271st fields. |
| 373 | ACCT_BAL_EXPIRE_TIME2 | DATE[14] | Expiration time of the 2nd bonus account balance in the group from 202nd to 271st fields. |
| 374 | ACCT_BAL_EXPIRE_TIME3 | DATE[14] | Expiration time of the 3rd bonus account balance in the group from 202nd to 271st fields. |
| 375 | ACCT_BAL_EXPIRE_TIME4 | DATE[14] | Expiration time of the 4th bonus account balance in the group from 202nd to 271st fields. |
| 376 | ACCT_BAL_EXPIRE_TIME5 | DATE[14] | Expiration time of the 5th bonus account balance in the group from 202nd to 271st fields. |
| 377 | ACCT_BAL_EXPIRE_TIME6 | DATE[14] | Expiration time of the 6th bonus account balance in the group from 202nd to 271st fields. |
| 378 | ACCT_BAL_EXPIRE_TIME7 | DATE[14] | Expiration time of the 7th bonus account balance in the group from 202nd to 271st fields. |
| 379 | ACCT_BAL_EXPIRE_TIME8 | DATE[14] | Expiration time of the 8th bonus account balance in the group from 202nd to 271st fields. |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 380 | ACCT_BAL_EXPIRE_TIME9 | DATE[14] | Expiration time of the 9th bonus account balance in the group from 202nd to 271st fields. |
| 381 | ACCT_BAL_EXPIRE_TIME10 | DATE[14] | Expiration time of the 10th bonus account balance in the group from 202nd to 271st fields. |
| 382 | BONUS_FU_EXPIRE_TIME1 | DATE[14] | Expiration time of the 1st bonus free unit in the group from 272nd to 351st fields. |
| 383 | BONUS_FU_EXPIRE_TIME2 | DATE[14] | Expiration time of the 2nd bonus free unit in the group from 272nd to 351st fields. |
| 384 | BONUS_FU_EXPIRE_TIME3 | DATE[14] | Expiration time of the 3rd bonus free unit in the group from 272nd to 351st fields. |
| 385 | BONUS_FU_EXPIRE_TIME4 | DATE[14] | Expiration time of the 4th bonus free unit in the group from 272nd to 351st fields. |
| 386 | BONUS_FU_EXPIRE_TIME5 | DATE[14] | Expiration time of the 5th bonus free unit in the group from 272nd to 351st fields. |
| 387 | BONUS_FU_EXPIRE_TIME6 | DATE[14] | Expiration time of the 6th bonus free unit in the group from 272nd to 351st fields. |
| 388 | BONUS_FU_EXPIRE_TIME7 | DATE[14] | Expiration time of the 7th bonus free unit in the group from 272nd to 351st fields. |
| 389 | BONUS_FU_EXPIRE_TIME8 | DATE[14] | Expiration time of the 8th bonus free unit in the group from 272nd to 351st fields. |
| 389 | BONUS_FU_EXPIRE_TIME9 | DATE[14] | Expiration time of the 9th bonus free unit in the group from 272nd to 351st fields. |
| 391 | BONUS_FU_EXPIRE_TIME10 | DATE[14] | Expiration time of the 10th bonus free unit in the group from 272nd to 351st fields. |

# 4.3 Prepaid Transaction CDR Files

This topic describes the CDR file template provided in the baseline version for management flow services. Each site can customize CDR files based on the template.

## 4.3.1 Recharge CDR

This topic describes fields in recharge CDRs.

Table 4-13 describes fields in recharge CDRs.

**Table 4-13** Recharge CDR fields

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 1 | RECHARGE_LOG_ID | NUMBER [20] | Recharge log ID. The ID is automatically generated by the sequencer.<br>The default value is **0**.<br>This field cannot be left empty. | The first 42 fields record basic recharge information. The meaning and length of these fields are fixed. |
| 2 | RECHARGE_CODE | NUMBER [10] | Recharge code, which uniquely identifies a recharge type.<br>This field has a fixed value of **0**.<br>This field is reserved. | |
| 3 | RECHARGE_AMT | NUMBER [20] | Actual recharge amount. If a foreign currency is used for recharge, this field specifies the recharge amount after conversion.<br>The recharge amount is saved in the minimum precision of the local currency, which is the default currency type of a subscriber's home BE.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 4 | ACCT_ID | NUMBER [20] | Recharge account ID.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 5 | SUB_ID | NUMBER [20] | ID of the subscriber whose account is recharged.<br>If no subscriber number is transferred in the process of recharging a specified account, this field is set to **0**.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 6 | PRI_IDENTITY | VARCHAR2[64] | Subscriber primary identifier.<br>If no subscriber number is transferred in the process of recharging a specified account, this field is left empty.<br>If a primary identifier is an MSISDN or a PSTN, the formats are as follows:<br>• Country code + MSISDN<br>• Country code + Area code + PSTN<br>If a primary identifier is of other types, the value is the number that is transferred.<br>This field can be left empty. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 7 | THIRD_PARTY_NUMBER | VARCHAR2[32] | Subscriber who recharges another subscriber's account.<br>This field can be left empty.<br>This field is reserved. | |
| 8 | CURRENCY_ID | NUMBER[5] | Currency type ID. This field is recorded when a foreign currency is used for recharge.<br>If this field is set to **0** or the default currency type of the home BE, the local currency is used for recharge.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 9 | ORIGINAL_AMT | NUMBER[20] | Original recharge amount when a foreign currency is used for recharge.<br>If the local currency is used for recharge, the value is the same as that of **RECHARGE_AMT**.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 10 | CURRENCY_RATE | NUMBER[20,6] | Exchange rate between a foreign currency and the local currency.<br>The default value is **0**, indicating that the local currency is used for recharge.<br>This field cannot be left empty. | |
| 11 | CONVERSION_AMT | NUMBER[20,6] | Recharge amount converted from a foreign currency to the local currency based on the exchange rate. The value can contain decimal places.<br>If the local currency is used for recharge, this field is set to **0**.<br>For example, if a subscriber recharges the account in US dollar while the local currency is pound, this field records the amount converted based on the exchange rate between dollar and pound, which is precise to penny.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 12 | RECHARGE_TRANS_ID | NUMBER[20] | Recharge transaction ID. This field is recorded in the recharge log. If a recharge needs to be reversed, the system queries the corresponding recharge record based on this | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | field.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 13 | EXT_TRANS_TYPE | VARCHAR2[32] | External transaction type, which is transferred from an external interface and is the same as the value of **BUSI_TYPE**.<br>This field is left empty if it is not transferred from an external interface.<br>This field can be left empty. | |
| 14 | EXT_TRANS_ID | VARCHAR2[32] | External sequence number of a transaction.<br>This field is left empty if it is not transferred from an external interface.<br>This field can be left empty. | |
| 15 | ACCESS_METHOD | NUMBER[10] | Recharge access mode. The options are as follows:<br>• **0**: IVR<br>• **1**: USSD<br>• **2**: SMS<br>• **3:** WebService<br>• **4**: GUI<br>• **5**: task (batch recharge triggered in the system)<br>• **6**: automatic (automatic recharge triggered in the system)<br>• **7**: reserved<br>• Other values can be extended based on the site requirements.<br>This field cannot be left empty. | |
| 16 | BATCH_NO | NUMBER[20] | Recharge batch number.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 17 | OFFERING_ID | VARCHAR2[32] | Recharge offering ID.<br>This field is reserved. | |
| 18 | PAYMENT_TYPE | VARCHAR2[1] | Payment type.<br>• **A**: cash<br>• **D**: debit card<br>• **C**: credit card<br>• **E**: check<br>• **V**: voucher | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **L**: e-voucher<br>This field cannot be left empty. | |
| 19 | RECHARGE_TAX | NUMBER[20] | Recharge tax.<br>If no tax needs to be collected, this field is set to **0**.<br>This field cannot be left empty. | |
| 20 | RECHARGE_PENALTY | NUMBER[20] | Recharge penalty.<br>If no penalty needs to be collected, this field is set to **0**.<br>Reserved | |
| 21 | RECHARGE_TYPE | VARCHAR2[24] | Recharge type. The options are as follows:<br>• **0**: voucher recharge<br>• **1**: cash recharge<br>• **2**: e-voucher recharge<br>• **3**: cash recharge reversal<br>This field cannot be left empty. | |
| 22 | CHANNEL_ID | VARCHAR2[8] | Recharge channel ID.<br>• **0**: IVR<br>• **1**: USSD<br>• **2**: SMS<br>• **3**: WebService<br>• **4**: GUI<br>• **5**: task (batch recharge triggered in the system)<br>• **6**: automatic (automatic recharge triggered in the system)<br>• **7**: IVRSM<br>• **9**: e-care<br>• **10**: IPCC IVR<br>• **11**: IPCC USSD<br>• **12**: IPCC SMS<br>• **99**: others<br>Other values can be extended based on the site requirements.<br>This field is reserved. | |
| 23 | RECHARGE_REASON | VARCHAR2[24] | Recharge reason.<br>This field is left empty if it is not transferred from an external interface or entered on the GUI. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | This field can be left empty. | |
| 24 | RESULT_CODE | NUMBER[10] | Internal recharge result code.<br>• **0**: The operation is successful.<br>• Others: The operation is unsuccessful.<br>This field cannot be left empty. | |
| 25 | ERROR_TYPE | VARCHAR2[16] | Error type. The options are as follows:<br>• **-1**: Default error type.<br>• **0**: The operation is successful.<br>• **1**: The operation cannot be performed repeatedly.<br>• **2**: No record is found.<br>• **3**: The balance or free unit has been used and the transaction cannot be reversed.<br>• **4**: No available resource is found.<br>• **5**: Invalid data.<br>• **6**: The specified operation is not allowed.<br>• **7**: Authentication failed.<br>This field can be left empty. | |
| 26 | VALID_DAY_ADDED | NUMBER[10] | Number of validity days extended after a recharge.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 27 | DIAMETER_SESSIONID | VARCHAR2[128] | ID of the Diameter session initiated in a recharge.<br>If a recharge is not performed based on Diameter, this field is left empty.<br>This field can be left empty. | |
| 28 | OPER_ID | NUMBER[20] | ID of the operator who performs the recharge operation.<br>If this field is not transferred, it is set to **0** by default.<br>This field cannot be left empty. | |
| 29 | DEPT_ID | NUMBER[20] | Department ID of the operator who performs the recharge operation.<br>If this field is not transferred, it is set to **0** by default.<br>This field cannot be left empty. | |
| 30 | ENTRY_DA | DATE[14] | Time when a recharge record is created. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | TE | | This field cannot be left empty. | |
| 31 | RECON_DATE | DATE[14] | Recharge reconciliation date.<br>This field can be left empty.<br>This field is reserved. | |
| 32 | RECON_STATUS | VARCHAR2[1] | Recharge reconciliation status.<br>This field can be left empty.<br>This field is reserved. | |
| 33 | REVERSAL_TRANS_ID | NUMBER[20] | Recharge reversal transaction ID.<br>For a non-recharge reversal transaction, this field is set to **0**.<br>This field cannot be left empty. | |
| 34 | REVERSAL_REASON_CODE | VARCHAR2[16] | Recharge reversal reason code.<br>For a non-recharge reversal transaction, this field is left empty. | |
| 35 | REVERSAL_OPER_ID | VARCHAR2[24] | ID of the operator who reverses the recharge.<br>For a non-recharge reversal transaction, this field is left empty. | |
| 36 | REVERSAL_DEPT_ID | VARCHAR2[24] | Department ID of the operator who reverses the recharge.<br>For a non-recharge reversal transaction, this field is left empty. | |
| 37 | REVERSAL_DATE | DATE[14] | Time when a recharge is reversed.<br>For a non-recharge reversal transaction, this field is left empty. | |
| 38 | STATUS | VARCHAR2[1] | Status of a recharge record.<br>• **F**: finish (This value is recorded in a recharge CDR.)<br>• **R**: reversal (This value is recorded in a recharge reversal CDR.)<br>This field cannot be left empty. | |
| 39 | REMARK | VARCHAR2[128] | Remarks.<br>This field is left empty if it is not transferred from an external interface or entered on the GUI. | |
| 40 | BE_ID | NUMBER[10] | ID of the lowest-level home BE.<br>The default value is **0**.<br>This field cannot be left empty. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 41 | BE_CODE | VARCHAR2[256] | Code of the lowest-level home BE.<br>This field is reserved. | |
| 42 | REGION_ID | NUMBER[10] | ID of the home management region.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 43 | REGION_CODE | VARCHAR2[256] | Code of the home management region.<br>This field can be left empty. | |
| 44 | CARD_SEQUENCE | VARCHAR2[20] | Voucher serial number consisting of 17 or 20 digits.<br>If a recharge is not performed by using a voucher, this field is left empty. | The 44th to 52nd fields record extended voucher information. These fields are provided in the baseline version and can be extended based on the site requirements. |
| 45 | CARD_PIN_NUMBER | VARCHAR2[20] | This field is reserved. | |
| 46 | CARD_BATCH_NO | VARCHAR2[20] | Voucher batch number.<br>If a recharge is not performed by using a voucher, this field is left empty. | |
| 47 | CARD_STATUS | VARCHAR2[1] | Voucher status.<br>• **0**: invalid (A voucher is invalidated after successful recharge.)<br>• **1**: valid (A voucher is valid after a recharge is reversed upon failure.)<br>This field is reserved. | |
| 48 | CARD_COS_ID | NUMBER[4] | Voucher type, which is defined in the UVC and reported through an interface.<br>If a recharge is not performed by using a voucher, this field is set to **0**. | |
| 49 | CARD_SP_ID | VARCHAR2[20] | Dealer ID, which is defined in the UVC and reported through an interface.<br>If a recharge is not performed by using a voucher, this field is set to **0**. | |
| 50 | CARD_AMOUNT | NUMBER[20] | Recharge amount, in the minimum currency unit.<br>If a recharge is not performed by using a voucher, this field is set to **0**. | |
| 51 | CARD_VALIDITY | NUMBER[10] | Validity period extended after voucher recharge.<br>If a recharge is not performed by using a voucher, this field is set to **0**. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 52 | VOUCHER_ENCRYPT_NUMBER | VARCHAR2[22] | This field is reserved. | |
| 53 | CHECK_NO | VARCHAR2[64] | Check number.<br>This field can be left empty.<br>This field is reserved. | The 53rd to 63rd fields record bank information. |
| 54 | CHECK_DATE | DATE[14] | Check date.<br>This field can be left empty.<br>This field is reserved. | |
| 55 | CREDIT_CARD_NO | VARCHAR2[64] | This field is reserved. | |
| 56 | CREDIT_CARD_NAME | VARCHAR2[64] | Credit card name.<br>This field can be left empty.<br>This field is reserved. | |
| 57 | CREDIT_CARD_TYPE_ID | NUMBER[8] | Credit card type.<br>This field can be left empty.<br>This field is reserved. | |
| 58 | CC_EXPIRY_DATE | VARCHAR2[32] | Expiration date of a credit card.<br>This field can be left empty.<br>This field is reserved. | |
| 59 | CC_AUTHORIZATION_CODE | VARCHAR2[16] | This field is reserved. | |
| 60 | BANK_CODE | VARCHAR2[32] | Bank code.<br>This field can be left empty.<br>This field is reserved. | |
| 61 | BANK_BRANCH_CODE | VARCHAR2[32] | Branch code.<br>This field can be left empty.<br>This field is reserved. | |
| 62 | ACCT_NO | VARCHAR2[192] | Bank account code.<br>This field can be left empty.<br>This field is reserved. | |
| 63 | BANK_ACCT_NAME | VARCHAR2[192] | Bank account name.<br>This field can be left empty.<br>This field is reserved. | |
| 64 | LOAN_AMO | NUMBER | Paid-off loan amount. | The |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | UNT | [20] | The default value is **0**.<br>This field cannot be left empty. | 64th to 65th fields record loan information. |
| 65 | LOAN_POUNDATE | NUMBER [20] | Loan payment handling fee.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 66 | ACCT_ID | NUMBER [20] | Account ID. | The 66th to 165th fields record 10 groups of balance change information. The 66th to 75th fields record the first group of balance change information. If *N* balance changes are involved in a recharge, the first *N* groups of balance change fields |
| 67 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 68 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 69 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 70 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 71 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 72 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 73 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 74 | CURRENCYE_ID | NUMBER [10] | Currency type ID. | |
| 75 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | are recorded and other groups of fields are left empty. |
| 76 | ACCT_ID | NUMBER [20] | Account ID. | The 66th to 165th fields record 10 groups of balance change information. The 76th to 85th fields record the second group of balance change information. If *N* balance changes are involved in a recharge, the first *N* groups of balance |
| 77 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 78 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 79 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 80 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 81 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 82 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 83 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 84 | CURRENCYE_ID | NUMBER [10] | Currency type ID. | |
| 85 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | change fields are recorded and other groups of fields are left empty. |
| 86 | ACCT_ID | NUMBER [20] | Account ID. | The 66th to 165th fields record 10 groups of balance change information. The 86th to 95th fields record the third group of balance change information. If *N* balance changes are involved in a recharge, the first *N* groups of |
| 87 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 88 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 89 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 90 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 91 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 92 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 93 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 94 | CURRENCYE_ID | NUMBER [10] | Currency type ID. | |
| 95 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | balance change fields are recorded and other groups of fields are left empty. |
| 96 | ACCT_ID | NUMBER [20] | Account ID. | The 66th to 165th fields record 10 groups of balance change information. The 96th to 105th fields record the fourth group of balance change information. If *N* balance changes are involved in a recharge, the first *N* |
| 97 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 98 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 99 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 100 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 101 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 102 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 103 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 104 | CURRENCYE_ID | NUMBER [10] | Currency type ID. | |
| 105 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | groups of balance change fields are recorded and other groups of fields are left empty. |
| 106 | ACCT_ID | NUMBER [20] | Account ID. | The 66th to 165th fields record 10 groups of balance change information. The 106th to 115th fields record the fifth group of balance change information. If *N* balance changes are involved in a |
| 107 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 108 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 109 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 110 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 111 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 112 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 113 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 114 | CURRENCYE_ID | NUMBER [10] | Currency type ID. | |
| 115 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | recharge, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 116 | ACCT_ID | NUMBER [20] | Account ID. | The 66th to 165th fields record 10 groups of balance change information. The 116th to 125th fields record the sixth group of balance change information. If *N* balance change |
| 117 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 118 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 119 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 120 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 121 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 122 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 123 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 124 | CURRENCYE_ID | NUMBER [10] | Currency type ID. | |
| 125 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | balance account. | s are involved in a recharge, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 126 | ACCT_ID | NUMBER [20] | Account ID. | The 66th to 165th fields record 10 groups of balance change information. The 126th to 135th fields record the seventh group of balance change information. |
| 127 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 128 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 129 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 130 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 131 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 132 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 133 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 134 | CURRENCYE_ID | NUMBER [10] | Currency type ID. | |
| 135 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | If *N* balance changes are involved in a recharge, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 136 | ACCT_ID | NUMBER [20] | Account ID. | The 66th to 165th fields record 10 groups of balance change information. The 136th to 145th fields record the eighth group of balance |
| 137 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 138 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 139 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 140 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 141 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 142 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 143 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 144 | CURRENCYE_ID | NUMBER [10] | Currency type ID. | |
| 145 | OPER_TYPE | NUMBER | Operation type. The options are as follows: | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | [10] | • **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | change information. If *N* balance changes are involved in a recharge, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 146 | ACCT_ID | NUMBER [20] | Account ID. | The 66th to 165th fields record 10 groups of balance change information. The 146th to 155th fields record the ninth |
| 147 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 148 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 149 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 150 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 151 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 152 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 153 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 154 | CURRENCYE_ID | NUMBER [10] | Currency type ID. | group of balance change information. If *N* balance changes are involved in a recharge, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 155 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |
| 156 | ACCT_ID | NUMBER [20] | Account ID. | The 66th to 165th fields record 10 groups of balance change information. The 156th to 165th fields |
| 157 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 158 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 159 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 160 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 161 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 162 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 163 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | record the tenth group of balance change information. If *N* balance changes are involved in a recharge, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 164 | CURRENCYE_ID | NUMBER[10] | Currency type ID. | |
| 165 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |
| 166 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 166th to 275th fields record 10 groups of free unit change information. The 166th |
| 167 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 168 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 169 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 170 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | to 176th fields record the first group of free unit change information. If *N* free unit changes are involved in a recharge, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 171 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 172 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 173 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 174 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 175 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 176 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |
| 177 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 166th to 275th fields record 10 groups of free unit change information. The |
| 178 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 179 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 180 | FREE_UNIT | NUMBER | Free unit type. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | _TYPE | [20] | | 177th to 187th fields record the second group of free unit change information. If *N* free unit changes are involved in a recharge, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 181 | CUR_AMOUNT | NUMBER [20] | Current free unit amount. | |
| 182 | CHG_AMOUNT | NUMBER [20] | Free unit change amount. | |
| 183 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 184 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 185 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 186 | FU_MEASURE_ID | NUMBER [10] | Free unit measurement unit ID. | |
| 187 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |
| 188 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 166th to 275th fields record 10 groups of free unit change information. |
| 189 | FU_OWN_ID | NUMBER [20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 190 | FREE_UNIT_ID | NUMBER [20] | Free unit ID. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 191 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | The 188th to 198th fields record the third group of free unit change information. If *N* free unit changes are involved in a recharge, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 192 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 193 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 194 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 195 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 196 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 197 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 198 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |
| 199 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 166th to 275th fields record 10 groups of free unit change inform |
| 200 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 201 | FREE_UNIT | NUMBER | Free unit ID. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | _ID | [20] | | ation. The 199th to 209th fields record the fourth group of free unit change information. If *N* free unit changes are involved in a recharge, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 202 | FREE_UNIT_TYPE | NUMBER [20] | Free unit type. | |
| 203 | CUR_AMOUNT | NUMBER [20] | Current free unit amount. | |
| 204 | CHG_AMOUNT | NUMBER [20] | Free unit change amount. | |
| 205 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 206 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 207 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 208 | FU_MEASURE_ID | NUMBER [10] | Free unit measurement unit ID. | |
| 209 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |
| 210 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 166th to 275th fields record 10 groups of free unit |
| 211 | FU_OWN_ID | NUMBER [20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 212 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | change information. The 210th to 220th fields record the fifth group of free unit change information. If *N* free unit changes are involved in a recharge, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 213 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 214 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 215 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 216 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 217 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 218 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 219 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 220 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |
| 221 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 166th to 275th fields record 10 groups of free |
| 222 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | **FU_OWN_TYPE** value. | unit change information. The 221st to 231st fields record the sixth group of free unit change information. If *N* free unit changes are involved in a recharge, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 223 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 224 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 225 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 226 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 227 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 228 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 229 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 230 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 231 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |
| 232 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 166th to 275th fields record 10 groups |
| 233 | FU_OWN_ID | NUMBER | Free unit owner ID. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | [20] | Set this field based on the **FU_OWN_TYPE** value. | of free unit change information. The 232nd to 242nd fields record the seventh group of free unit change information. If *N* free unit changes are involved in a recharge, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 234 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 235 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 236 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 237 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 238 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 239 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 240 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 241 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 242 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |
| 243 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 166th to 275th fields record |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 244 | FU_OWN_ID | NUMBER [20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | 10 groups of free unit change information. The 243rd to 253rd fields record the eighth group of free unit change information. If *N* free unit changes are involved in a recharge, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 245 | FREE_UNIT_ID | NUMBER [20] | Free unit ID. | |
| 246 | FREE_UNIT_TYPE | NUMBER [20] | Free unit type. | |
| 247 | CUR_AMOUNT | NUMBER [20] | Current free unit amount. | |
| 248 | CHG_AMOUNT | NUMBER [20] | Free unit change amount. | |
| 249 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 250 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 251 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 252 | FU_MEASURE_ID | NUMBER [10] | Free unit measurement unit ID. | |
| 253 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |
| 254 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group | The 166th to 275th |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **C**: customer | fields record 10 groups of free unit change information. The 254th to 264th fields record the ninth group of free unit change information. If *N* free unit changes are involved in a recharge, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 255 | FU_OWN_ID | NUMBER [20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 256 | FREE_UNIT_ID | NUMBER [20] | Free unit ID. | |
| 257 | FREE_UNIT_TYPE | NUMBER [20] | Free unit type. | |
| 258 | CUR_AMOUNT | NUMBER [20] | Current free unit amount. | |
| 259 | CHG_AMOUNT | NUMBER [20] | Free unit change amount. | |
| 260 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 261 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 262 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 263 | FU_MEASURE_ID | NUMBER [10] | Free unit measurement unit ID. | |
| 264 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |
| 265 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber | The 166th to |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **G**: subscriber group<br>• **C**: customer | 275th fields record 10 groups of free unit change information. The 265th to 275th fields record the tenth group of free unit change information. If *N* free unit changes are involved in a recharge, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 266 | FU_OWN_ID | NUMBER [20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 267 | FREE_UNIT_ID | NUMBER [20] | Free unit ID. | |
| 268 | FREE_UNIT_TYPE | NUMBER [20] | Free unit type. | |
| 269 | CUR_AMOUNT | NUMBER [20] | Current free unit amount. | |
| 270 | CHG_AMOUNT | NUMBER [20] | Free unit change amount. | |
| 271 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 272 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 273 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 274 | FU_MEASURE_ID | NUMBER [10] | Free unit measurement unit ID. | |
| 275 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |
| 276 | ACCT_ID | NUMBER [20] | Account ID. | The 276th |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 277 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | to 375th fields record 10 groups of bonus details. The 276th to 285th fields record the first group of bonus details. If *N* bonuses are involved in a recharge, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 278 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 279 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |
| 280 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | |
| 281 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 282 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 283 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 284 | CURRENCY_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 285 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |
| 286 | ACCT_ID | NUMBER[20] | Account ID. | The 276th to 375th fields record 10 |
| 287 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | |
| 288 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 289 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | groups of bonus details. The 286th to 295th fields record the second group of bonus details. If *N* bonuses are involved in a recharge, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 290 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | |
| 291 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 292 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 293 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 294 | CURRENCY_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 295 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |
| 296 | ACCT_ID | NUMBER[20] | Account ID. | The 276th to 375th fields record 10 groups of bonus details. The |
| 297 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | |
| 298 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 299 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |
| 300 | CURRENT_ | NUMBER | Current fund balance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | BALANCE | [20] | | 296th to 305th fields record the third group of bonus details. If *N* bonuses are involved in a recharge, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 301 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 302 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 303 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 304 | CURRENCY_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 305 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |
| 306 | ACCT_ID | NUMBER[20] | Account ID. | The 276th to 375th fields record 10 groups of bonus details. The 306th to 315th fields record |
| 307 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | |
| 308 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 309 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |
| 310 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | |
| 311 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 312 | PRE_EXPIR | DATE[14] | Original expiration time of the account | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | E_TIME | | book. | the fourth group of bonus details. If *N* bonuses are involved in a recharge, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 313 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 314 | CURRENCY_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 315 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |
| 316 | ACCT_ID | NUMBER[20] | Account ID. | The 276th to 375th fields record 10 groups of bonus details. The 316th to 325th fields record the fifth group of |
| 317 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | |
| 318 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 319 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |
| 320 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | |
| 321 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 322 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 323 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 324 | CURRENCY_ID | NUMBER [10] | Currency type ID, which can be customized by a carrier. | bonus details. If *N* bonuses are involved in a recharge, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 325 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |
| 326 | ACCT_ID | NUMBER [20] | Account ID. | The 276th to 375th fields record 10 groups of bonus details. The 326th to 335th fields record the sixth group of bonus details. If *N* bonuses are |
| 327 | ACCT_BALANCE_ID | NUMBER [20] | Account book ID. | |
| 328 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 329 | BONUS_AMOUNT | NUMBER [20] | Bonus amount. | |
| 330 | CURRENT_BALANCE | NUMBER [20] | Current fund balance. | |
| 331 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 332 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 333 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 334 | CURRENCY_ID | NUMBER [10] | Currency type ID, which can be customized by a carrier. | |
| 335 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows: | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | involved in a recharge, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 336 | ACCT_ID | NUMBER [20] | Account ID. | The 276th to 375th fields record 10 groups of bonus details. The 336th to 345th fields record the seventh group of bonus details. If *N* bonuses are involved in a recharge, the |
| 337 | ACCT_BALANCE_ID | NUMBER [20] | Account book ID. | |
| 338 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 339 | BONUS_AMOUNT | NUMBER [20] | Bonus amount. | |
| 340 | CURRENT_BALANCE | NUMBER [20] | Current fund balance. | |
| 341 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 342 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 343 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 344 | CURRENCY_ID | NUMBER [10] | Currency type ID, which can be customized by a carrier. | |
| 345 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 346 | ACCT_ID | NUMBER [20] | Account ID. | The 276th to 375th fields record 10 groups of bonus details. The 346th to 355th fields record the eighth group of bonus details. If *N* bonuses are involved in a recharge, the first *N* groups of bonus details |
| 347 | ACCT_BALANCE_ID | NUMBER [20] | Account book ID. | |
| 348 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 349 | BONUS_AMOUNT | NUMBER [20] | Bonus amount. | |
| 350 | CURRENT_BALANCE | NUMBER [20] | Current fund balance. | |
| 351 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 352 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 353 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 354 | CURRENCY_ID | NUMBER [10] | Currency type ID, which can be customized by a carrier. | |
| 355 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | fields are recorded and other groups of fields are left empty. |
| 356 | ACCT_ID | NUMBER [20] | Account ID. | The 276th to 375th fields record 10 groups of bonus details. The 356th to 365th fields record the ninth group of bonus details. If *N* bonuses are involved in a recharge, the first *N* groups of bonus details fields are recorded and other |
| 357 | ACCT_BALANCE_ID | NUMBER [20] | Account book ID. | |
| 358 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 359 | BONUS_AMOUNT | NUMBER [20] | Bonus amount. | |
| 360 | CURRENT_BALANCE | NUMBER [20] | Current fund balance. | |
| 361 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 362 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 363 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 364 | CURRENCY_ID | NUMBER [10] | Currency type ID, which can be customized by a carrier. | |
| 365 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | groups of fields are left empty. |
| 366 | ACCT_ID | NUMBER [20] | Account ID. | The 276th to 375th fields record 10 groups of bonus details. The 366th to 375th fields record the tenth group of bonus details. If *N* bonuses are involved in a recharge, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 367 | ACCT_BALANCE_ID | NUMBER [20] | Account book ID. | |
| 368 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 369 | BONUS_AMOUNT | NUMBER [20] | Bonus amount. | |
| 370 | CURRENT_BALANCE | NUMBER [20] | Current fund balance. | |
| 371 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 372 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 373 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 374 | CURRENCY_ID | NUMBER [10] | Currency type ID, which can be customized by a carrier. | |
| 375 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 376 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 376th to 485th fields record 10 groups of free unit reward details. The 376th to 386th fields record the first group of free unit reward details. If *N* free unit rewards are involved in a recharge, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 377 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 378 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 379 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 380 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 381 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 382 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 383 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 384 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 385 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 386 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 387 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 376th to 485th fields record 10 groups of free unit reward details. The 387th to 397th fields record the second group of free unit reward details. If *N* free unit rewards are involved in a recharge, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 388 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 389 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 390 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 391 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 392 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 393 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 394 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 395 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 396 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 397 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 398 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 376th to 485th fields record 10 groups of free unit reward details. The 398th to 408th fields record the third group of free unit reward details. If *N* free unit rewards are involved in a recharge, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 399 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 400 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 401 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 402 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 403 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 404 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 405 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 406 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 407 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 408 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 409 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 376th to 485th fields record 10 groups of free unit reward details. The 409th to 419th fields record the fourth group of free unit reward details. If *N* free unit rewards are involved in a recharge, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 410 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 411 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 412 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 413 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 414 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 415 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 416 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 417 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 418 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 419 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 420 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 376th to 485th fields record 10 groups of free unit reward details. The 420th to 430th fields record the fifth group of free unit reward details. If *N* free unit rewards are involved in a recharge, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 421 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 422 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 423 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 424 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 425 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 426 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 427 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 428 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 429 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 430 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 431 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 376th to 485th fields record 10 groups of free unit reward details. The 431st to 441st fields record the sixth group of free unit reward details. If *N* free unit rewards are involved in a recharge, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 432 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 433 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 434 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 435 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 436 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 437 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 438 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 439 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 440 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 441 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 442 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 376th to 485th fields record 10 groups of free unit reward details. The 442nd to 452nd fields record the seventh group of free unit reward details. If *N* free unit rewards are involved in a recharge, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left |
| 443 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 444 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 445 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 446 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 447 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 448 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 449 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 450 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 451 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 452 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | empty. |
| 453 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 376th to 485th fields record 10 groups of free unit reward details. The 453rd to 463rd fields record the eighth group of free unit reward details. If *N* free unit rewards are involved in a recharge, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left |
| 454 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 455 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 456 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 457 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 458 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 459 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 460 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 461 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 462 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 463 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | empty. |
| 464 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 376th to 485th fields record 10 groups of free unit reward details. The 464th to 474th fields record the ninth group of free unit reward details. If *N* free unit rewards are involved in a recharge, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left |
| 465 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 466 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 467 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 468 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 469 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 470 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 471 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 472 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 473 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 474 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | empty. |
| 475 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 376th to 485th fields record 10 groups of free unit reward details. The 475th to 485th fields record the tenth group of free unit reward details. If *N* free unit rewards are involved in a recharge, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left |
| 476 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 477 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 478 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 479 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 480 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 481 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 482 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 483 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 484 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 485 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | empty. |
| 486 | RechargeAreaCode | VARCHAR2[10] | Code of the area where a recharge request is initiated. If this field is not transferred through an interface, value **0** is used, indicating an unknown area.<br>The default value is **0**. | The 486th to 505th fields record additional recharge information. These fields are provided in the baseline version and can be extended based on the site requirements. |
| 487 | RechargeCellID | VARCHAR2[20] | Visited cell ID of the subscriber who initiates a recharge request.<br>This field can be left empty. | |
| 488 | BrandID | NUMBER[10] | Subscriber brand ID.<br>In the process of recharging a specified account, this field can be left empty. | |
| 489 | MainOfferingID | NUMBER[10] | Primary offering ID.<br>In the process of recharging a specified account, this field can be left empty. | |
| 490 | PayType | VARCHAR2[1] | Payment type of a subscriber. The options are as follows:<br>• **0**: prepaid<br>• **1**: postpaid<br>• **2**: hybrid<br>In the process of recharging a specified account, this field can be left empty. | |
| 491 | StartTimeOfBillCycle | VARCHAR2[14] | Bill cycle start time, in the format *YYYYMMDDHHMMSS*. | |
| 492 | Account | VARCHAR2[256] | This field is reserved. | |
| 493 | MainBalanceInfo | VARCHAR2[255] | This field is reserved. | |
| 494 | ChgBalanceInfo | VARCHAR2[1024] | This field is reserved. | |
| 495 | ChgFreeUnitInfo | VARCHAR2[1024] | This field is reserved. | |
| 496 | UserState | VARCHAR2[10] | This field is reserved. | |
| 497 | OldUserState | VARCHAR2[10] | This field is reserved. | |
| 498 | CardValueAdded | NUMBER[20] | This field is reserved. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 499 | ValidityAdded | NUMBER[10] | This field is reserved. | |
| 500 | TradeType | NUMBER[10] | This field is reserved. | |
| 501 | AgentName | VARCHAR2[64] | This field is reserved. | |
| 502 | AdditionalInfo | VARCHAR2[256] | This field is reserved. | |
| 503 | BankCode | VARCHAR2[20] | This field is reserved. | |
| 504 | SubIdentityType | NUMBER[10] | This field is reserved. | |
| 505 | OriginOperatorID | VARCHAR2[32] | From DCC/IDL, this parameter will come in the request of Recharge, same need to pass from BM to RB in the Recharge IDL in the Additional Property and same to be recorded in CDR.<br>Simple Property = C_ORIGINOPERATORID<br>This parameter will come in case of external recharge cases.<br>Can be null | |
| 506 | CARDGROUP | VARCHAR2[8] | From DCC/IDL , this parameter will come in the request of recharge, same need to pass from BM to RB in the Recharge IDL in the Additional Property and same to be recorded in CDR.<br>This is the cardtype field in DCC or IDL<br>Can be null | |
| 507 | NodeId | NUMBER[10] | CBP Node ID | |
| 508 | ExternalAcctID1 | NUMBER[10] | The Mapped Account ID1 of the account which is mapped to external system.<br>This field can be collected from the mapped table "CB_EXIN_TYPE_ID_MAPPIN" for the account which is used in the charging process.<br>For those existing Accounts which are not mapped in CB_EXIN_TYPE_ID_MAPPING , their Internal type ID will be displayed. This applies to all the below ExternalAcctID | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | fields.<br>Can be null | |
| 509 | ExternalAcctID2 | NUMBER [10] | The Mapped Account ID2 of the account which is mapped to external system.<br>This field can be collected from the mapped table "CB_EXIN_TYPE_ID_MAPPIN" for the account which is used in the charging process.<br>For those existing Accounts which are not mapped in CB_EXIN_TYPE_ID_MAPPING , their Internal type ID will be displayed.<br>Can be null | |
| 510 | ExternalAcctID3 | NUMBER [10] | The Mapped Account ID3 of the account which is mapped to external system.<br>This field can be collected from the mapped table "CB_EXIN_TYPE_ID_MAPPIN" for the account which is used in the charging process.<br>For those existing Accounts which are not mapped in CB_EXIN_TYPE_ID_MAPPING , their Internal type ID will be displayed.<br>Can be null | |
| 511 | ExternalAcctID4 | NUMBER [10] | The Mapped Account ID4 of the account which is mapped to external system.<br>This field can be collected from the mapped table "CB_EXIN_TYPE_ID_MAPPIN" for the account which is used in the charging process.<br>For those existing Accounts which are not mapped in CB_EXIN_TYPE_ID_MAPPING , their Internal type ID will be displayed.<br>Can be null | |
| 512 | ExternalAcctID5 | NUMBER [10] | The Mapped Account ID5 of the account which is mapped to external system.<br>This field can be collected from the mapped table "CB_EXIN_TYPE_ID_MAPPIN" for the account which is used in the charging process.<br>For those existing Accounts which are not mapped in CB_EXIN_TYPE_ID_MAPPING , their | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | Internal type ID will be displayed.<br>Can be null | |
| 513 | ExternalAcctID6 | NUMBER [10] | The Mapped Account ID6 of the account which is mapped to external system.<br>This field can be collected from the mapped table "CB_EXIN_TYPE_ID_MAPPIN" for the account which is used in the charging process.<br>For those existing Accounts which are not mapped in CB_EXIN_TYPE_ID_MAPPING , their Internal type ID will be displayed.<br>Can be null | |
| 514 | ExternalAcctID7 | NUMBER [10] | The Mapped Account ID7 of the account which is mapped to external system.<br>This field can be collected from the mapped table "CB_EXIN_TYPE_ID_MAPPIN" for the account which is used in the charging process.<br>For those existing Accounts which are not mapped in CB_EXIN_TYPE_ID_MAPPING , their Internal type ID will be displayed.<br>Can be null | |
| 515 | ExternalAcctID8 | NUMBER [10] | The Mapped Account ID8 of the account which is mapped to external system.<br>This field can be collected from the mapped table "CB_EXIN_TYPE_ID_MAPPIN" for the account which is used in the charging process.<br>For those existing Accounts which are not mapped in CB_EXIN_TYPE_ID_MAPPING , their Internal type ID will be displayed.<br>Can be null | |
| 516 | ExternalAcctID9 | NUMBER [10] | The Mapped Account ID9 of the account which is mapped to external system.<br>This field can be collected from the mapped table "CB_EXIN_TYPE_ID_MAPPIN" for the account which is used in the charging process.<br>For those existing Accounts which are not mapped in CB_EXIN_TYPE_ID_MAPPING , their | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | Internal type ID will be displayed.<br>Can be null | |
| 517 | ExternalAcctID10 | NUMBER[10] | The Mapped Account ID10 of the account which is mapped to external system.<br>This field can be collected from the mapped table "CB_EXIN_TYPE_ID_MAPPIN" for the account which is used in the charging process.<br>For those existing Accounts which are not mapped in CB_EXIN_TYPE_ID_MAPPING , their Internal type ID will be displayed.<br>Can be null | |
| 518 | External Data1 | VARCHAR2[255] | From IDL, this parameter will come in the request of recharge, same need to pass from BM to RB in the Recharge IDL in the Additional Property and same to be recorded in CDR.<br>Simple Property = C_EXTARNALDATA1<br>Can be null | |
| 519 | External Data2 | VARCHAR2[255] | From IDL , this parameter will come in the request of recharge, same need to pass from BM to RB in the Recharge IDL in the Additional Property and same to be recorded in CDR.<br>Simple Property = C_EXTARNALDATA2<br>Can be null | |
| 520 | BarringEndDateBefore | DATE[8] | Barring End Date before the operation. | |
| 521 | BarringEndDateAfter | DATE[8] | Barring End Date After the operation. | |
| 522 | ActiveEndDateBefore | DATE[8] | Active End date before the operation | |
| 523 | ActiveEndDateAfter | DATE[8] | Active End date After the operation | |
| 524 | ActivationDate | DATE[14] | The First Activation Date of the subscriber.<br>This field value can be taken from the field ACTIVE_TIME of BC_SUBSCRIBER table and keep in the CDR.<br>Cannot be null | |
| 525 | CUGID1Befo | NUMBER | If subscriber have subscribed to any CUG | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | re | [10] | then CUG Group ID1 before the operation need to be recorded in this Field.<br>Can be null | |
| 526 | CUGID2Before | NUMBER [10] | If subscriber have subscribed to any CUG then CUG Group ID2 before the operation need to be recorded in this Field.<br>Can be null | |
| 527 | CUGID3Before | NUMBER [10] | If subscriber have subscribed to any CUG then CUG Group ID3 before the operation need to be recorded in this Field.<br>Can be null | |
| 528 | CUGID1After | NUMBER [10] | If subscriber have subscribed to any CUG then CUG Group ID1 after the operation need to be recorded in this Field.<br>Can be null | |
| 529 | CUGID2After | NUMBER [10] | If subscriber have subscribed to any CUG then CUG Group ID2 after the operation need to be recorded in this Field.<br>Can be null | |
| 530 | CUGID3After | NUMBER [10] | If subscriber have subscribed to any CUG then CUG Group ID1 after the operation need to be recorded in this Field. | |
| 531 | OriginNodeID | NUMBER [10] | From IDL , this parameter will come in the request of recharge, same need to pass from BM to RB in the Recharge IDL in the Additional Property and same to be recorded in CDR.<br>Can be null | |
| 532 | LocationNumber | VARCHAR[20] | The Location Number of the subscriber.<br>If RB can get the location number in the request then write the information in this field.<br>The parameter can be passed only in IDL and not in DCC request.<br>Can be null | |
| 533 | ErrorCode | NUMBER [10] | If there is some issue with the Voucher, then UVC/BM sends the error code to RB and RB will write this information in this field.<br>Can be null | |
| 534 | ErrorDesc | VARCHA | If there is some issue with the Voucher, | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | R[255] | then UVC/BM sends the error description to RB and RB will write this information in this field.<br>Can be null | |

## 4.3.2 Transfer CDR

This topic describes fields in transfer CDRs.

Table 4-14 describes fields in transfer CDRs.

**Table 4-14** Transfer CDR fields

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 1 | TRANSFER_LOG_ID | NUMBER[20] | Transfer log ID.<br>The default value is **0**.<br>This field cannot be left empty. | The first 36 fields record basic transfer information. The meaning and length of these fields are fixed. |
| 2 | PAY_TYPE | VARCHAR2[1] | Payment type of an account.<br>• **0**: prepaid<br>• **1**: postpaid<br>If the transferor or transferee is an external subscriber, this field is left empty. | |
| 3 | ACCT_ID | NUMBER[20] | Transfer account ID.<br>In transfer-out CDRs, this field is set to the transferor account ID. In transfer-in CDRs, this field is set to the transferee account ID.<br>This field cannot be left empty. | |
| 4 | CUST_ID | NUMBER[20] | Customer ID.<br>In transfer-out CDRs, this field is set to the transferor customer ID. In transfer-in CDRs, this field is set to the transferee customer ID.<br>If the transferor or transferee is an external subscriber, this field is left empty. | |
| 5 | SUB_ID | NUMBER[20] | Subscriber ID.<br>In transfer-out CDRs, this field is set to the transferor subscriber ID. In transfer-in CDRs, this field is set to the transferee subscriber ID.<br>If the transferor or transferee is an external | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | subscriber, this field is left empty. | |
| 6 | PRI_IDENTITY | VARCHAR2[64] | Primary identifier.<br>In transfer-out CDRs, this field is set to the transferor primary identifier. In transfer-in CDRs, this field is set to the transferee primary identifier.<br>If the transferor or transferee is an external subscriber, this field is left empty.<br>If a primary identifier is an MSISDN or a PSTN, the formats are as follows:<br>• Country code + MSISDN<br>• Country code + Area code + PSTN<br>If a primary identifier is of other types, the value is the number that is transferred. | |
| 7 | BATCH_NO | NUMBER[20] | Transfer batch number.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 8 | CHANNEL_ID | VARCHAR2[8] | Transfer channel ID.<br>This field can be left empty.<br>This field is reserved. | |
| 9 | REASON_CODE | VARCHAR2[16] | Transfer reason code.<br>This field is left empty if it is not transferred from an external interface or entered on the GUI.<br>This field can be left empty. | |
| 10 | RESULT_CODE | NUMBER[10] | Internal transfer result code.<br>• **0**: The operation is successful.<br>• Others: The operation failed.<br>This field cannot be left empty. | |
| 11 | ERROR_TYPE | VARCHAR2[32] | Error type. The options are as follows:<br>• **-1**: Default error type.<br>• **0**: The operation is successful.<br>• **1**: The operation cannot be performed repeatedly.<br>• **2**: No record is found.<br>• **4**: No available resource is found.<br>• **5**: Invalid data.<br>• **6**: The specified operation is not allowed. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **7**: Authentication failed.<br>This field cannot be left empty. | |
| 12 | REQUEST_ACCT_BALANCE_ID | NUMBER[20] | Instance ID of the transfer-out balance account.<br>If the transferor or transferee is an external subscriber or a transfer is not performed for a specified account book, this field is set to **0**.<br>This field cannot be left empty. | |
| 13 | DEST_ACCT_ID | NUMBER[20] | Transfer-in account ID.<br>If the transferor or transferee is an external subscriber, this field is set to **0**.<br>This field cannot be left empty. | |
| 14 | DEST_ACCT_BALANCE_ID | NUMBER[20] | Instance ID of the transfer-in balance account.<br>If the transferor or transferee is an external subscriber, this field is set to **0**.<br>This field cannot be left empty. | |
| 15 | TRANSFER_TYPE | NUMBER[10] | Transfer type. The options are as follows:<br>• **0**: transfer-in<br>• **1**: transfer-out<br>This field cannot be left empty. | |
| 16 | TRANSFER_AMT | NUMBER[20] | Transfer amount.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 17 | TRANSFER_DATE | DATE[14] | Time when a transfer transaction is executed.<br>This field cannot be left empty. | |
| 18 | TRANSFER_TRANS_ID | NUMBER[20] | Transfer transaction ID.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 19 | EXT_TRANS_TYPE | VARCHAR2[32] | External transaction type, which is transferred from an external interface and is the same as the value of **BUSI_TYPE**.<br>This field is left empty if it is not transferred from an external interface. | |
| 20 | EXT_TRANS_ID | VARCHAR2[32] | External sequence number of a transaction.<br>This field is left empty if it is not transferred from an external interface. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | This field can be left empty. | |
| 21 | ACCESS_METHOD | NUMBER[10] | Transfer access method. The options are as follows:<br>• **0**: IVR<br>• **1**: USSD<br>• **2**: SMS<br>• **3**: WebService<br>• **4**: GUI<br>Other values can be extended based on the site requirements.<br>This field cannot be left empty. | |
| 22 | DIAMETER_SESSIONID | VARCHAR2[128] | ID of the Diameter session initiated in a transfer.<br>If a transfer is not performed based on Diameter, this field is left empty. | |
| 23 | HANDLING_CHARGE | NUMBER[20] | Transfer handling fee.<br>If no handling fee needs to be collected, this field is set to **0**.<br>This field cannot be left empty. | |
| 24 | REVERSAL_TRANS_ID | NUMBER[20] | Transfer reversal transaction ID.<br>For a non-transfer reversal transaction, this field is set to **0**.<br>This field cannot be left empty. | |
| 25 | REVERSAL_REASON_CODE | VARCHAR2[16] | Transfer reversal reason code.<br>For a non-transfer reversal transaction, this field is left empty. | |
| 26 | REVERSAL_DATE | DATE[14] | Time when a transfer is reversed.<br>For a non-transfer reversal transaction, this field is left empty. | |
| 27 | EXT_REF_ID | VARCHAR2[64] | External reference ID.<br>This field is left empty if it is not transferred from an external interface. | |
| 28 | STATUS | VARCHAR2[1] | Transfer request status. The options are as follows:<br>• **F**: Finished<br>• **R**: Reversed<br>The default value is **F**.<br>This field cannot be left empty. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 29 | ENTRY_DATE | DATE[14] | Time when a transfer record is created.<br>This field cannot be left empty. | |
| 30 | REMARK | VARCHAR2[128] | Remarks.<br>This field is left empty if it is not transferred from an external interface. | |
| 31 | OPER_ID | NUMBER[20] | ID of the operator who performs the transfer operation.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 32 | DEPT_ID | NUMBER[20] | Department ID of the operator who performs the transfer operation.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 33 | BE_ID | NUMBER[10] | ID of the lowest-level home BE.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 34 | BE_CODE | VARCHAR2[256] | Code of the lowest-level home BE.<br>This field is reserved. | |
| 35 | REGION_ID | NUMBER[10] | ID of the home management region.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 36 | REGION_CODE | VARCHAR2[256] | Code of the home management region.<br>This field can be left empty. | |
| 37 | ACCT_ID | NUMBER[20] | Account ID. | The 37th to 136th fields record 10 groups of balance change information. The 37th to 46th fields |
| 38 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 39 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 40 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 41 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 42 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 43 | PRE_EXPIR | DATE[14] | Original expiration time of the account | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | E_TIME | | book. | record the first group of balance change information. If *N* balance changes are involved in a transfer, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 44 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 45 | CURRENCYE_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 46 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |
| 47 | ACCT_ID | NUMBER[20] | Account ID. | The 37th to 136th fields record 10 groups of balance change information. The |
| 48 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 49 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 50 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 51 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 52 | PRE_APPLY | DATE[14] | Original effective time of the account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | _TIME | | | 47th to 56th fields record the second group of balance change information. If *N* balance changes are involved in a transfer, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 53 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 54 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 55 | CURRENCYE_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 56 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |
| 57 | ACCT_ID | NUMBER[20] | Account ID. | The 37th to 136th fields record 10 groups of balance change inform |
| 58 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 59 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 60 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 61 | CHG_BALA | NUMBER | Change amount of the balance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | NCE | [20] | | ation. The 57th to 66th fields record the third group of balance change information. If *N* balance changes are involved in a transfer, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 62 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 63 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 64 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 65 | CURRENCYE_ID | NUMBER [10] | Currency type ID, which can be customized by a carrier. | |
| 66 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |
| 67 | ACCT_ID | NUMBER [20] | Account ID. | The 37th to 136th fields record 10 groups of balance |
| 68 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 69 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 70 | CUR_BALANCE | NUMBER [20] | Current balance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 71 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | change information. The 67th to 76th fields record the fourth group of balance change information. If *N* balance changes are involved in a transfer, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 72 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 73 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 74 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 75 | CURRENCYE_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 76 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |
| 77 | ACCT_ID | NUMBER[20] | Account ID. | The 37th to 136th fields record 10 groups |
| 78 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 79 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 80 | CUR_BALANCE | NUMBER[20] | Current balance. | of balance change information. The 77th to 86th fields record the fifth group of balance change information. If *N* balance changes are involved in a transfer, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 81 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 82 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 83 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 84 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 85 | CURRENCYE_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 86 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |
| 87 | ACCT_ID | NUMBER[20] | Account ID. | The 37th to 136th fields record |
| 88 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 89 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | 10 groups of balance change information. The 87th to 96th fields record the sixth group of balance change information. If *N* balance changes are involved in a transfer, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 90 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 91 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 92 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 93 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 94 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 95 | CURRENCYE_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 96 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |
| 97 | ACCT_ID | NUMBER[20] | Account ID. | The 37th to |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 98 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | 136th fields record 10 groups of balance change information. The 97th to 106th fields record the seventh group of balance change information. If *N* balance changes are involved in a transfer, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 99 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 100 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 101 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 102 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 103 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 104 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 105 | CURRENCYE_ID | NUMBER[10] | Currency type ID, which can be customized by a carrier. | |
| 106 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 107 | ACCT_ID | NUMBER [20] | Account ID. | The 37th to 136th fields record 10 groups of balance change information. The 107th to 116th fields record the eighth group of balance change information. If *N* balance changes are involved in a transfer, the first *N* groups of balance change fields are recorded and other groups of fields |
| 108 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 109 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 110 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 111 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 112 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 113 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 114 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 115 | CURRENCYE_ID | NUMBER [10] | Currency type ID, which can be customized by a carrier. | |
| 116 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | are left empty. |
| 117 | ACCT_ID | NUMBER [20] | Account ID. | The 37th to 136th fields record 10 groups of balance change information. The 117th to 126th fields record the ninth group of balance change information. If *N* balance changes are involved in a transfer, the first *N* groups of balance change fields are recorded and other |
| 118 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 119 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 120 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 121 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 122 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 123 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 124 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 125 | CURRENCYE_ID | NUMBER [10] | Currency type ID, which can be customized by a carrier. | |
| 126 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | groups of fields are left empty. |
| 127 | ACCT_ID | NUMBER [20] | Account ID. | The 37th to 136th fields record 10 groups of balance change information. The 127th to 136th fields record the tenth group of balance change information. If *N* balance changes are involved in a transfer, the first *N* groups of balance change fields are |
| 128 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 129 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 130 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 131 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 132 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 133 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 134 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 135 | CURRENCYE_ID | NUMBER [10] | Currency type ID, which can be customized by a carrier. | |
| 136 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | recorded and other groups of fields are left empty. |
| 137 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 137th to 246th fields record 10 groups of free unit change information. The 137th to 147th fields record the first group of free unit change information. If *N* free unit changes are involved in a transfer, the first *N* groups of free unit change fields |
| 138 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 139 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 140 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 141 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 142 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 143 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 144 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 145 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 146 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 147 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | are recorded and other groups of fields are left empty. |
| 148 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 137th to 246th fields record 10 groups of free unit change information. The 148th to 158th fields record the second group of free unit change information. If *N* free unit changes are involved in a transfer, the first *N* groups of free unit change |
| 149 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 150 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 151 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 152 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 153 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 154 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 155 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 156 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 157 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 158 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | fields are recorded and other groups of fields are left empty. |
| 159 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 137th to 246th fields record 10 groups of free unit change information. The 159th to 169th fields record the third group of free unit change information. If *N* free unit changes are involved in a transfer, the first *N* groups of free unit |
| 160 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 161 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 162 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 163 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 164 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 165 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 166 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 167 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 168 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 169 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | change fields are recorded and other groups of fields are left empty. |
| 170 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 137th to 246th fields record 10 groups of free unit change information. The 170th to 180th fields record the fourth group of free unit change information. If *N* free unit changes are involved in a transfer, the first *N* groups of free |
| 171 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 172 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 173 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 174 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 175 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 176 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 177 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 178 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 179 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 180 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | unit change fields are recorded and other groups of fields are left empty. |
| 181 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 137th to 246th fields record 10 groups of free unit change information. The 181st to 191st fields record the fifth group of free unit change information. If *N* free unit changes are involved in a transfer, the first *N* groups |
| 182 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 183 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 184 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 185 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 186 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 187 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 188 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 189 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 190 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 191 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | free unit instance. | of free unit change fields are recorded and other groups of fields are left empty. |
| 192 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 137th to 246th fields record 10 groups of free unit change information. The 192nd to 202nd fields record the sixth group of free unit change information. If *N* free unit changes are involved in a transfer, the first *N* |
| 193 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 194 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 195 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 196 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 197 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 198 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 199 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 200 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 201 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 202 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **2**: Increase the income. That is, add a free unit instance. | groups of free unit change fields are recorded and other groups of fields are left empty. |
| 203 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 137th to 246th fields record 10 groups of free unit change information. The 203rd to 213rd fields record the seventh group of free unit change information. If *N* free unit changes are involved in a transfe |
| 204 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 205 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 206 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 207 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 208 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 209 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 210 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 211 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 212 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 213 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | r, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 214 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 137th to 246th fields record 10 groups of free unit change information. The 214th to 224th fields record the eighth group of free unit change information. If *N* free unit changes are involved in a |
| 215 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 216 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 217 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 218 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 219 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 220 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 221 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 222 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 223 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 224 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows: | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | transfer, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 225 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 137th to 246th fields record 10 groups of free unit change information. The 225th to 235th fields record the ninth group of free unit change information. If *N* free unit changes are involv |
| 226 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 227 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 228 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 229 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 230 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 231 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 232 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 233 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 234 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 235 | OPER_TYPE | NUMBER | Operation type. The options are as follows: | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | [10] | • **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | ed in a transfer, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 236 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 137th to 246th fields record 10 groups of free unit change information. The 236th to 246th fields record the tenth group of free unit change information. If *N* free unit changes are |
| 237 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 238 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 239 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 240 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 241 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 242 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 243 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 244 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 245 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 246 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | involved in a transfer, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 247 | ACCT_ID | NUMBER [20] | Account ID. | The 247th to 346th fields record 10 groups of bonus details. The 247th to 256th fields record the first group of bonus details. If *N* bonuses are involved in a transfer, the first *N* |
| 248 | ACCT_BALANCE_ID | NUMBER [20] | Account book ID. | |
| 249 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 250 | BONUS_AMOUNT | NUMBER [20] | Bonus amount. | |
| 251 | CURRENT_BALANCE | NUMBER [20] | Current fund balance. | |
| 252 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 253 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 254 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 255 | CURRENCY_ID | NUMBER [10] | Currency type ID. | |
| 256 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | groups of bonus details fields are recorded and other groups of fields are left empty. |
| 257 | ACCT_ID | NUMBER [20] | Account ID. | The 247th to 346th fields record 10 groups of bonus details. The 257th to 266th fields record the second group of bonus details. If *N* bonuses are involved in a transfer, the first *N* groups of bonus details fields |
| 258 | ACCT_BALANCE_ID | NUMBER [20] | Account book ID. | |
| 259 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 260 | BONUS_AMOUNT | NUMBER [20] | Bonus amount. | |
| 261 | CURRENT_BALANCE | NUMBER [20] | Current fund balance. | |
| 262 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 263 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 264 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 265 | CURRENCY_ID | NUMBER [10] | Currency type ID. | |
| 266 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | are recorded and other groups of fields are left empty. |
| 267 | ACCT_ID | NUMBER [20] | Account ID. | The 247th to 346th fields record 10 groups of bonus details. The 267th to 276th fields record the third group of bonus details. If *N* bonuses are involved in a transfer, the first *N* groups of bonus details fields are recorded and other groups |
| 268 | ACCT_BALANCE_ID | NUMBER [20] | Account book ID. | |
| 269 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 270 | BONUS_AMOUNT | NUMBER [20] | Bonus amount. | |
| 271 | CURRENT_BALANCE | NUMBER [20] | Current fund balance. | |
| 272 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 273 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 274 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 275 | CURRENCY_ID | NUMBER [10] | Currency type ID. | |
| 276 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | of fields are left empty. |
| 277 | ACCT_ID | NUMBER [20] | Account ID. | The 247th to 346th fields record 10 groups of bonus details. The 277th to 286th fields record the fourth group of bonus details. If *N* bonuses are involved in a transfer, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 278 | ACCT_BALANCE_ID | NUMBER [20] | Account book ID. | |
| 279 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 280 | BONUS_AMOUNT | NUMBER [20] | Bonus amount. | |
| 281 | CURRENT_BALANCE | NUMBER [20] | Current fund balance. | |
| 282 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 283 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 284 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 285 | CURRENCY_ID | NUMBER [10] | Currency type ID. | |
| 286 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 287 | ACCT_ID | NUMBER [20] | Account ID. | The 247th to 346th fields record 10 groups of bonus details. The 287th to 296th fields record the fifth group of bonus details. If *N* bonuses are involved in a transfer, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 288 | ACCT_BALANCE_ID | NUMBER [20] | Account book ID. | |
| 289 | BALANCE_TYPE | NUMBER [20] | ID of the balance account type, which can be customized by a carrier. | |
| 290 | BONUS_AMOUNT | NUMBER [20] | Bonus amount. | |
| 291 | CURRENT_BALANCE | NUMBER [20] | Current fund balance. | |
| 292 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 293 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 294 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 295 | CURRENCY_ID | NUMBER [10] | Currency type ID. | |
| 296 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |
| 297 | ACCT_ID | NUMBER [20] | Account ID. | The 247th to 346th fields |
| 298 | ACCT_BALANCE_ID | NUMBER [20] | Account book ID. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 299 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | record 10 groups of bonus details. The 297th to 306th fields record the sixth group of bonus details. If *N* bonuses are involved in a transfer, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 300 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |
| 301 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | |
| 302 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 303 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 304 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 305 | CURRENCY_ID | NUMBER[10] | Currency type ID. | |
| 306 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |
| 307 | ACCT_ID | NUMBER[20] | Account ID. | The 247th to 346th fields record 10 groups of bonus |
| 308 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | |
| 309 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 310 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 311 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | details. The 307th to 316th fields record the seventh group of bonus details. If *N* bonuses are involved in a transfer, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 312 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 313 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 314 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 315 | CURRENCY_ID | NUMBER[10] | Currency type ID. | |
| 316 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |
| 317 | ACCT_ID | NUMBER[20] | Account ID. | The 247th to 346th fields record 10 groups of bonus details. The 317th |
| 318 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | |
| 319 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 320 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |
| 321 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 322 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | to 326th fields record the eighth group of bonus details. If *N* bonuses are involved in a transfer, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 323 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 324 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 325 | CURRENCY_ID | NUMBER[10] | Currency type ID. | |
| 326 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |
| 327 | ACCT_ID | NUMBER[20] | Account ID. | The 247th to 346th fields record 10 groups of bonus details. The 327th to 336th fields record the |
| 328 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | |
| 329 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 330 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |
| 331 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | |
| 332 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 333 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 334 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | ninth group of bonus details. If *N* bonuses are involved in a transfer, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 335 | CURRENCY_ID | NUMBER[10] | Currency type ID. | |
| 336 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |
| 337 | ACCT_ID | NUMBER[20] | Account ID. | The 247th to 346th fields record 10 groups of bonus details. The 337th to 346th fields record the tenth group of bonus details. |
| 338 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | |
| 339 | BALANCE_TYPE | NUMBER[20] | ID of the balance account type, which can be customized by a carrier. | |
| 340 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |
| 341 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | |
| 342 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 343 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 344 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 345 | CURRENCY | NUMBER | Currency type ID. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | _ID | [10] | | If *N* bonuses are involved in a transfer, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 346 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |
| 347 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 347th to 456th fields record 10 groups of free unit reward details. The 347th to 357th fields record the first group of free unit reward details. If *N* free unit |
| 348 | FU_OWN_ID | NUMBER [20] | Free unit owner ID. | |
| 349 | FREE_UNIT_TYPE | NUMBER [20] | Free unit type. | |
| 350 | FREE_UNIT_ID | NUMBER [20] | Free unit ID. | |
| 351 | BONUS_AMOUNT | NUMBER [20] | Rewarded free unit amount. | |
| 352 | CURRENT_AMOUNT | NUMBER [20] | Current free unit amount. | |
| 353 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 354 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 355 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 356 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | rewards are involved in a transfer, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 357 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 358 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 347th to 456th fields record 10 groups of free unit reward details. The 358th to 368th fields record the second group of free unit reward details. If *N* free unit |
| 359 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 360 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 361 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 362 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 363 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 364 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 365 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 366 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 367 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | rewards are involved in a transfer, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 368 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 369 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 347th to 456th fields record 10 groups of free unit reward details. The 369th to 379th fields record the third group of free unit reward details. If *N* free unit |
| 370 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 371 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 372 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 373 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 374 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 375 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 376 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 377 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 378 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | rewards are involved in a transfer, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 379 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 380 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 347th to 456th fields record 10 groups of free unit reward details. The 380th to 390th fields record the fourth group of free unit reward details. If *N* free unit |
| 381 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 382 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 383 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 384 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 385 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 386 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 387 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 388 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 389 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | rewards are involved in a transfer, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 390 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 391 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 347th to 456th fields record 10 groups of free unit reward details. The 391st to 401st fields record the fifth group of free unit reward details. If *N* free unit |
| 392 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 393 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 394 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 395 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 396 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 397 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 398 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 399 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 400 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | rewards are involved in a transfer, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 401 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 402 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 347th to 456th fields record 10 groups of free unit reward details. The 402nd to 412nd fields record the sixth group of free unit reward details. If *N* free unit |
| 403 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 404 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 405 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 406 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 407 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 408 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 409 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 410 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 411 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | rewards are involved in a transfer, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 412 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 413 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 347th to 456th fields record 10 groups of free unit reward details. The 413rd to 423rd fields record the seventh group of free unit reward details. If *N* free |
| 414 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 415 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 416 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 417 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 418 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 419 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 420 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 421 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 422 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | unit rewards are involved in a transfer, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 423 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 424 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 347th to 456th fields record 10 groups of free unit reward details. The 424th to 434th fields record the eighth group of free unit reward details. If *N* free |
| 425 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 426 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 427 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 428 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 429 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 430 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 431 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 432 | CUR_EXPIR | DATE[14] | Current expiration time of free units. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | E_TIME | | | unit rewards are involved in a transfer, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 433 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 434 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 435 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 347th to 456th fields record 10 groups of free unit reward details. The 435th to 445th fields record the ninth group of free unit reward details. If *N* free |
| 436 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 437 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 438 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 439 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 440 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 441 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 442 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 443 | CUR_EXPIR | DATE[14] | Current expiration time of free units. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | E_TIME | | | unit rewards are involved in a transfer, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 444 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 445 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 446 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 347th to 456th fields record 10 groups of free unit reward details. The 446th to 456th fields record the tenth group of free unit reward details. If *N* free |
| 447 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 448 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 449 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 450 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 451 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 452 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 453 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 454 | CUR_EXPIR | DATE[14] | Current expiration time of free units. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | E_TIME | | | unit rewards are involved in a transfer, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 455 | FU_MEASURE_ID | NUMBER [10] | Free unit measurement unit ID. | |
| 456 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 457 | BrandID | NUMBER [10] | Brand ID.<br>In the process of transferring an amount for a specified account, this field can be left empty.<br>This field can be left empty. | The 457th to 474th fields record additional transfer information. These fields are provided in the baseline version and can be extended based |
| 458 | MainOfferingID | NUMBER [10] | Primary offering ID.<br>In the process of transferring an amount for a specified account, this field can be left empty.<br>This field can be left empty. | |
| 459 | PayType | VARCHAR2[1] | Payment type of a subscriber.<br>• **0**: prepaid<br>• **1**: postpaid<br>• **2**: Hybrid<br>In the process of transferring an amount for a specified account, this field can be left empty.<br>This field can be left empty. | |
| 460 | StartTimeOfBillCycle | VARCHAR2[14] | Bill cycle start time, in the format *YYYYMMDDHHMMSS*.<br>This field cannot be left empty. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 461 | DETAIL_FEE | VARCHAR2[1024] | This field is reserved. | on the site requirements. |
| 462 | Account | VARCHAR2[1024] | This field is reserved. | |
| 463 | MainBalanceInfo | VARCHAR2[255] | This field is reserved. | |
| 464 | ChgBalanceInfo | VARCHAR2[1024] | This field is reserved. | |
| 465 | ChgFreeUnitInfo | VARCHAR2[1024] | This field is reserved. | |
| 466 | UserState | VARCHAR2[10] | This field is reserved. | |
| 467 | oldUserState | VARCHAR2[10] | This field is reserved. | |
| 468 | TransferType | NUMBER[10] | This field is reserved. | |
| 469 | Dest_Pri_Identity | VARCHAR2[36] | This field is reserved. | |
| 470 | SPID | VARCHAR2[20] | This field is reserved. | |
| 471 | AdditionalInfo | VARCHAR2[256] | This field is reserved. | |
| 472 | Merchant | VARCHAR2[20] | This field is reserved. | |
| 473 | Service | VARCHAR2[20] | This field is reserved. | |

## 4.3.3 Adjustment CDR

This topic describes fields in adjustment CDRs.

Table 4-15 describes fields in adjustment CDRs.

**Table 4-15** Adjustment CDR fields

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 1 | ADJUST_LO | NUMBER | Adjustment log ID. | The |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | G_ID | [20] | The default value is **0**.<br>This field cannot be left empty. | first 29 fields record basic adjustment information. The meaning and length of these fields are fixed. |
| 2 | ACCT_ID | NUMBER [20] | ID of the adjustment account.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 3 | CUST_ID | NUMBER [20] | ID of the customer whose account is adjusted.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 4 | SUB_ID | NUMBER [20] | ID of the subscriber whose account is adjusted.<br>This field is used for account-level adjustments. If no subscriber is transferred in an account-level adjustment, this field is set to **0**.<br>This field cannot be left empty. | |
| 5 | PRI_IDENTITY | VARCHAR2[64] | Subscriber primary identifier.<br>This field is used for account-level adjustments. If no subscriber is transferred in an account-level adjustment, this field is left empty.<br>If a primary identifier is an MSISDN or a PSTN, the formats are as follows:<br>• Country code + MSISDN<br>• Country code + Area code + PSTN<br>If a primary identifier is of other types, the value is the number that is transferred.<br>This field can be left empty. | |
| 6 | PAY_TYPE | VARCHAR2[1] | Payment type of an account. The options are as follows:<br>• **0**: prepaid<br>• **1**: postpaid<br>This field cannot be left empty. | |
| 7 | BATCH_NO | NUMBER [20] | Adjustment batch number.<br>For a single adjustment, this field is set to **0**.<br>This field cannot be left empty. | |
| 8 | CHANNEL_ID | VARCHAR2[8] | Adjustment channel ID.<br>This field is left empty if it is not transferred from an external interface or entered on the | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | GUI.<br>• **0**: IVR<br>• **1**: USSD<br>• **2**: SMS<br>• **3**: WebService<br>• **4**: GUI<br>Other values can be extended based on the site requirements.<br>This field can be left empty. | |
| 9 | REASON_CODE | VARCHAR2[16] | Adjustment reason code.<br>This field is left empty if it is not transferred from an external interface or entered on the GUI. | |
| 10 | RESULT_CODE | NUMBER[10] | Internal adjustment result code.<br>• **0**: The operation is successful.<br>• Others: The operation failed.<br>This field cannot be left empty. | |
| 11 | ERROR_TYPE | VARCHAR2[32] | Error type. The options are as follows:<br>• **-1**: Default error type.<br>• **0**: The operation is successful.<br>• **1**: The operation cannot be performed repeatedly.<br>• **2**: No record is found.<br>• **4**: No available resource is found.<br>• **5**: Invalid data.<br>• **6**: The specified operation is not allowed.<br>• **7**: Authentication failed.<br>This field can be left empty. | |
| 12 | ACCT_BALANCE_ID | NUMBER[20] | Instance ID of the adjusted balance account.<br>For an account-level adjustment transaction, this field is set to **0**.<br>This field cannot be left empty. | |
| 13 | ADJUST_AMT | NUMBER[20] | Adjusted amount.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 14 | ADJUST_TRANS_ID | NUMBER[20] | Adjustment transaction ID.<br>The default value is **0**. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | This field cannot be left empty. | |
| 15 | EXT_TRANS_TYPE | VARCHAR2[32] | External transaction type, which is transferred from an external interface and is the same as the value of **BUSI_TYPE**.<br>This field is left empty if it is not transferred from an external interface. | |
| 16 | EXT_TRANS_ID | VARCHAR2[32] | External sequence number of a transaction.<br>This field is left empty if it is not transferred from an external interface. | |
| 17 | ACCESS_METHOD | NUMBER[10] | Adjustment access method. The options are as follows:<br>• **0**: IVR<br>• **1**: USSD<br>• **2**: SMS<br>• **3**: WebService<br>• **4**: GUI<br>Other values can be extended based on the site requirements.<br>This field is reserved. | |
| 18 | REVERSAL_TRANS_ID | NUMBER[20] | Adjustment reversal transaction ID.<br>For a non-adjustment reversal transaction, this field is set to **0**.<br>This field cannot be left empty. | |
| 19 | REVERSAL_REASON_CODE | VARCHAR2[16] | Adjustment reversal reason code.<br>In the non-adjustment reversal process or in the scenario where this field is not transferred from an external interface or entered on the GUI, this field is left empty. | |
| 20 | REVERSAL_DATE | DATE[14] | Time when an adjustment is reversed.<br>For a non-adjustment reversal transaction, this field is left empty. | |
| 21 | STATUS | VARCHAR2[1] | Adjustment request status. The options are as follows:<br>• **F**: Finished<br>• **R**: Reversed<br>The default value is **F**.<br>This field cannot be left empty. | |
| 22 | ENTRY_DATE | DATE[14] | Time when an adjustment record is created.<br>This field cannot be left empty. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 23 | OPER_ID | NUMBER [20] | ID of the operator who performs the adjustment operation.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 24 | DEPT_ID | NUMBER [20] | Department ID of the operator who performs the adjustment operation.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 25 | REMARK | VARCHAR2[128] | Remarks.<br>This field is left empty if it is not transferred from an external interface or entered on the GUI.<br>This field can be left empty. | |
| 26 | BE_ID | NUMBER [10] | ID of the lowest-level home BE.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 27 | BE_CODE | VARCHAR2[256] | Code of the lowest-level home BE.<br>This field is reserved. | |
| 28 | REGION_ID | NUMBER [10] | ID of the home management region.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 29 | REGION_CODE | VARCHAR2[256] | Code of the home management region.<br>This field can be left empty. | |
| 30 | DEBIT_AMOUNT | NUMBER [20] | Actual amount that is deducted, which includes the amount deducted from prepaid main funds, bonuses, postpaid credits, and prepayments of all accounts (including payment accounts) used in a transaction but excludes the undebited amount. | The 30th to 37th fields record total fund information. |
| 31 | UN_DEBIT_AMOUNT | NUMBER [20] | Undebited amount.<br>This field indicates the fee that is not debited when the balance is deducted to zero (that is, when the account balance is insufficient) in the case of prorated charging. | |
| 32 | DEBIT_FROM_PREPAID | NUMBER [20] | Total amount deducted from prepaid main funds and bonuses of all prepaid accounts, including payment accounts. | |
| 33 | DEBIT_FRO | NUMBER | Total amount deducted from prepaid main | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | M_ADVANCE_PREPAID | [20] | funds of all prepaid accounts, including payment accounts. | |
| 34 | DEBIT_FROM_POSTPAID | NUMBER [20] | Total amount deducted from credits, bonuses, deposits, and prepayments of all postpaid accounts, including payment accounts. | |
| 35 | DEBIT_FROM_ADVANCE_POSTPAID | NUMBER [20] | Total amount deducted from prepayments of all postpaid accounts, including payment accounts. | |
| 36 | DEBIT_FROM_CREDIT_POSTPAID | NUMBER [20] | Total amount deducted from credits of all postpaid accounts, including payment accounts. | |
| 37 | TOTAL_TAX | NUMBER [20] | Total tax amount. | |
| 38 | FREE_UNIT_AMOUNT_OF_TIMES | NUMBER [20] | Number of free units charged per use. | The 38th to 40th fields record free unit information. There can be zero or one group of free unit information based on the service requirements. |
| 39 | FREE_UNIT_AMOUNT_OF_DURATION | NUMBER [20] | Usage of free units that are charged by duration.<br>The duration unit is defined by the system. Generally, the unit is second. | |
| 40 | FREE_UNIT_AMOUNT_OF_FLUX | NUMBER [20] | Usage of free units that are charged by traffic.<br>The traffic unit is defined by the system. Generally, the unit is byte. | |
| 41 | ACCT_ID | NUMBER [20] | Account ID. | The 41st to 140th fields record 10 groups of balanc |
| 42 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 43 | BALANCE_TYPE | NUMBER [20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 44 | CUR_BALANCE | NUMBER[20] | Current balance. | e change information. The 41st to 50th fields record the first group of balance change information. If *N* balance changes are involved in an adjustment, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 45 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 46 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 47 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 48 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 49 | CURRENCYE_ID | NUMBER[10] | Currency type ID. | |
| 50 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |
| 51 | ACCT_ID | NUMBER[20] | Account ID. | The 41st to 140th fields record |
| 52 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 53 | BALANCE_TYPE | NUMBER[20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | 10 groups of balance change information. The 51st to 60th fields record the second group of balance change information. If *N* balance changes are involved in an adjustment, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 54 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 55 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 56 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 57 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 58 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 59 | CURRENCY_ID | NUMBER[10] | Currency type ID. | |
| 60 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |
| 61 | ACCT_ID | NUMBER | Account ID. | The |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | [20] | | 41st to 140th fields record 10 groups of balance change information. The 61st to 70th fields record the third group of balance change information. If *N* balance changes are involved in an adjustment, the first *N* groups of balance change fields are recorded and other groups of fields |
| 62 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 63 | BALANCE_TYPE | NUMBER [20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | |
| 64 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 65 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 66 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 67 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 68 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 69 | CURRENCYE_ID | NUMBER [10] | Currency type ID. | |
| 70 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | are left empty. |
| 71 | ACCT_ID | NUMBER [20] | Account ID. | The 41st to 140th fields record 10 groups of balance change information. The 71st to 80th fields record the fourth group of balance change information. If *N* balance changes are involved in an adjustment, the first *N* groups of balance change fields are recorded and |
| 72 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 73 | BALANCE_TYPE | NUMBER [20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | |
| 74 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 75 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 76 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 77 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 78 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 79 | CURRENCYE_ID | NUMBER [10] | Currency type ID. | |
| 80 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | other groups of fields are left empty. |
| 81 | ACCT_ID | NUMBER [20] | Account ID. | The 41st to 140th fields record 10 groups of balance change information. The 81st to 90th fields record the fifth group of balance change information. If *N* balance changes are involved in an adjustment, the first *N* groups of balance change |
| 82 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 83 | BALANCE_TYPE | NUMBER [20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | |
| 84 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 85 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 86 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 87 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 88 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 89 | CURRENCYE_ID | NUMBER [10] | Currency type ID. | |
| 90 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | fields are recorded and other groups of fields are left empty. |
| 91 | ACCT_ID | NUMBER [20] | Account ID. | The 41st to 140th fields record 10 groups of balance change information. The 91st to 100th fields record the sixth group of balance change information. If *N* balance changes are involved in an adjustment, the first *N* groups |
| 92 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 93 | BALANCE_TYPE | NUMBER [20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | |
| 94 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 95 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 96 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 97 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 98 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 99 | CURRENCYE_ID | NUMBER [10] | Currency type ID. | |
| 100 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | of balance change fields are recorded and other groups of fields are left empty. |
| 101 | ACCT_ID | NUMBER [20] | Account ID. | The 41st to 140th fields record 10 groups of balance change information. The 101st to 110th fields record the seventh group of balance change information. If *N* balance changes are involved in |
| 102 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 103 | BALANCE_TYPE | NUMBER [20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | |
| 104 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 105 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 106 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 107 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 108 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 109 | CURRENCYE_ID | NUMBER [10] | Currency type ID. | |
| 110 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | an adjustment, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 111 | ACCT_ID | NUMBER [20] | Account ID. | The 41st to 140th fields record 10 groups of balance change information. The 111st to 120th fields record the eighth group of balance change information. If *N* balanc |
| 112 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 113 | BALANCE_TYPE | NUMBER [20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | |
| 114 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 115 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 116 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 117 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 118 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 119 | CURRENCYE_ID | NUMBER [10] | Currency type ID. | |
| 120 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | e changes are involved in an adjustment, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 121 | ACCT_ID | NUMBER [20] | Account ID. | The 41st to 140th fields record 10 groups of balance change information. The 121st to 130th fields record the ninth group of balance |
| 122 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 123 | BALANCE_TYPE | NUMBER [20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | |
| 124 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 125 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 126 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 127 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 128 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 129 | CURRENCYE_ID | NUMBER [10] | Currency type ID. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 130 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | change information. If *N* balance changes are involved in an adjustment, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 131 | ACCT_ID | NUMBER [20] | Account ID. | The 41st to 140th fields record 10 groups of balance change information. The 131st to 140th fields record the |
| 132 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 133 | BALANCE_TYPE | NUMBER [20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | |
| 134 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 135 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 136 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 137 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 138 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | tenth group of balance change information. If *N* balance changes are involved in an adjustment, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 139 | CURRENCYE_ID | NUMBER[10] | Currency type ID. | |
| 140 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend an amount.<br>• **1**: Perform accounting. That is, settle a postpaid account.<br>• **2**: Update the income. That is, add an amount to an existing balance account.<br>• **3**: Increase the income. That is, add a balance account. | |
| 141 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 141st to 250th fields record 10 groups of free unit change information. The 141st |
| 142 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 143 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 144 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 145 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | to 151st fields record the first group of free unit change information. If *N* free unit changes are involved in an adjustment, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 146 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 147 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 148 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 149 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 150 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 151 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |
| 152 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 141st to 250th fields record 10 groups of free unit change inform |
| 153 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 154 | FREE_UNIT | NUMBER | Free unit ID. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | _ID | [20] | | ation. The 152nd to 162nd fields record the second group of free unit change information. If *N* free unit changes are involved in an adjustment, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 155 | FREE_UNIT_TYPE | NUMBER [20] | Free unit type. | |
| 156 | CUR_AMOUNT | NUMBER [20] | Current free unit amount. | |
| 157 | CHG_AMOUNT | NUMBER [20] | Free unit change amount. | |
| 158 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 159 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 160 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 161 | FU_MEASURE_ID | NUMBER [10] | Free unit measurement unit ID. | |
| 162 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |
| 163 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 141st to 250th fields record 10 groups of free |
| 164 | FU_OWN_ID | NUMBER [20] | Free unit owner ID.<br>Set this field based on the | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | **FU_OWN_TYPE** value. | unit change information. The 163rd to 173rd fields record the third group of free unit change information. If *N* free unit changes are involved in an adjustment, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 165 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 166 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 167 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 168 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 169 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 170 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 171 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 172 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 173 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |
| 174 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 141st to 250th fields record |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 175 | FU_OWN_ID | NUMBER [20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | 10 groups of free unit change information. The 174th to 184th fields record the fourth group of free unit change information. If *N* free unit changes are involved in an adjustment, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 176 | FREE_UNIT_ID | NUMBER [20] | Free unit ID. | |
| 177 | FREE_UNIT_TYPE | NUMBER [20] | Free unit type. | |
| 178 | CUR_AMOUNT | NUMBER [20] | Current free unit amount. | |
| 179 | CHG_AMOUNT | NUMBER [20] | Free unit change amount. | |
| 180 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 181 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 182 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 183 | FU_MEASURE_ID | NUMBER [10] | Free unit measurement unit ID. | |
| 184 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |
| 185 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber | The 141st to |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **G**: subscriber group<br>• **C**: customer | 250th fields record 10 groups of free unit change information. The 185th to 195th fields record the fifth group of free unit change information. If *N* free unit changes are involved in an adjustment, the first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 186 | FU_OWN_ID | NUMBER [20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 187 | FREE_UNIT_ID | NUMBER [20] | Free unit ID. | |
| 188 | FREE_UNIT_TYPE | NUMBER [20] | Free unit type. | |
| 189 | CUR_AMOUNT | NUMBER [20] | Current free unit amount. | |
| 190 | CHG_AMOUNT | NUMBER [20] | Free unit change amount. | |
| 191 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 192 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 193 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 194 | FU_MEASURE_ID | NUMBER [10] | Free unit measurement unit ID. | |
| 195 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 196 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 141st to 250th fields record 10 groups of free unit change information. The 196th to 206th fields record the sixth group of free unit change information. If *N* free unit changes are involved in an adjustment, the first *N* groups of free unit change fields are recorded and other groups of fields |
| 197 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 198 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 199 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 200 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 201 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 202 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 203 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 204 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 205 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 206 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | are left empty. |
| 207 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 141st to 250th fields record 10 groups of free unit change information. The 207th to 217th fields record the seventh group of free unit change information. If *N* free unit changes are involved in an adjustment, the first *N* groups of free unit change fields are recorded and |
| 208 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 209 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 210 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 211 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 212 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 213 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 214 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 215 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 216 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 217 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | other groups of fields are left empty. |
| 218 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 141st to 250th fields record 10 groups of free unit change information. The 218th to 228th fields record the eighth group of free unit change information. If *N* free unit changes are involved in an adjustment, the first *N* groups of free unit change fields |
| 219 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 220 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 221 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 222 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 223 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 224 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 225 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 226 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 227 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 228 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | are recorded and other groups of fields are left empty. |
| 229 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 141st to 250th fields record 10 groups of free unit change information. The 229th to 239th fields record the ninth group of free unit change information. If *N* free unit changes are involved in an adjustment, the first *N* groups of free |
| 230 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 231 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 232 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 233 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 234 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 235 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 236 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 237 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 238 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 239 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a free unit instance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | unit change fields are recorded and other groups of fields are left empty. |
| 240 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 141st to 250th fields record 10 groups of free unit change information. The 240th to 250th fields record the tenth group of free unit change information. If *N* free unit changes are involved in an adjustment, the |
| 241 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 242 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 243 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 244 | CUR_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 245 | CHG_AMOUNT | NUMBER[20] | Free unit change amount. | |
| 246 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 247 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 248 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 249 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 250 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: Expend a free unit.<br>• **1**: Update the income. That is, add free units to an existing free unit instance.<br>• **2**: Increase the income. That is, add a | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | free unit instance. | first *N* groups of free unit change fields are recorded and other groups of fields are left empty. |
| 251 | ACCT_ID | NUMBER [20] | Account ID. | The 251st to 350th fields record 10 groups of bonus details. The 251st to 260th fields record the first group of bonus details. If *N* bonuses are involved in an adjustment, the first *N* groups of |
| 252 | ACCT_BALANCE_ID | NUMBER [20] | Account book ID. | |
| 253 | BALANCE_TYPE | NUMBER [20] | Balance type. | |
| 254 | BONUS_AMOUNT | NUMBER [20] | Bonus amount. | |
| 255 | CURRENT_BALANCE | NUMBER [20] | Current fund balance. | |
| 256 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 257 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 258 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 259 | CURRENCY_ID | NUMBER [10] | Currency type ID. | |
| 260 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | bonus details fields are recorded and other groups of fields are left empty. |
| 261 | ACCT_ID | NUMBER [20] | Account ID. | The 251st to 350th fields record 10 groups of bonus details. The 261st to 270th fields record the second group of bonus details. If *N* bonuses are involved in an adjustment, the first *N* groups of bonus details fields |
| 262 | ACCT_BALANCE_ID | NUMBER [20] | Account book ID. | |
| 263 | BALANCE_TYPE | NUMBER [20] | Balance type. | |
| 264 | BONUS_AMOUNT | NUMBER [20] | Bonus amount. | |
| 265 | CURRENT_BALANCE | NUMBER [20] | Current fund balance. | |
| 266 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 267 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 268 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 269 | CURRENCY_ID | NUMBER [10] | Currency type ID. | |
| 270 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | are recorded and other groups of fields are left empty. |
| 271 | ACCT_ID | NUMBER [20] | Account ID. | The 251st to 350th fields record 10 groups of bonus details. The 271st to 280th fields record the third group of bonus details. If *N* bonuses are involved in an adjustment, the first *N* groups of bonus details fields are recorded and |
| 272 | ACCT_BALANCE_ID | NUMBER [20] | Account book ID. | |
| 273 | BALANCE_TYPE | NUMBER [20] | Balance type. | |
| 274 | BONUS_AMOUNT | NUMBER [20] | Bonus amount. | |
| 275 | CURRENT_BALANCE | NUMBER [20] | Current fund balance. | |
| 276 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 277 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 278 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 279 | CURRENCY_ID | NUMBER [10] | Currency type ID. | |
| 280 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | other groups of fields are left empty. |
| 281 | ACCT_ID | NUMBER [20] | Account ID. | The 251st to 350th fields record 10 groups of bonus details. The 281st to 290th fields record the fourth group of bonus details. If *N* bonuses are involved in an adjustment, the first *N* groups of bonus details fields are recorded and other groups of |
| 282 | ACCT_BALANCE_ID | NUMBER [20] | Account book ID. | |
| 283 | BALANCE_TYPE | NUMBER [20] | Balance type. | |
| 284 | BONUS_AMOUNT | NUMBER [20] | Bonus amount. | |
| 285 | CURRENT_BALANCE | NUMBER [20] | Current fund balance. | |
| 286 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 287 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 288 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 289 | CURRENCY_ID | NUMBER [10] | Currency type ID. | |
| 290 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | fields are left empty. |
| 291 | ACCT_ID | NUMBER [20] | Account ID. | The 251st to 350th fields record 10 groups of bonus details. The 291st to 300th fields record the fifth group of bonus details. If *N* bonuses are involved in an adjustment, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 292 | ACCT_BALANCE_ID | NUMBER [20] | Account book ID. | |
| 293 | BALANCE_TYPE | NUMBER [20] | Balance type. | |
| 294 | BONUS_AMOUNT | NUMBER [20] | Bonus amount. | |
| 295 | CURRENT_BALANCE | NUMBER [20] | Current fund balance. | |
| 296 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 297 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 298 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 299 | CURRENCY_ID | NUMBER [10] | Currency type ID. | |
| 300 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 301 | ACCT_ID | NUMBER [20] | Account ID. | The 251st to 350th fields record 10 groups of bonus details. The 301st to 310th fields record the sixth group of bonus details. If *N* bonuses are involved in an adjustment, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 302 | ACCT_BALANCE_ID | NUMBER [20] | Account book ID. | |
| 303 | BALANCE_TYPE | NUMBER [20] | Balance type. | |
| 304 | BONUS_AMOUNT | NUMBER [20] | Bonus amount. | |
| 305 | CURRENT_BALANCE | NUMBER [20] | Current fund balance. | |
| 306 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 307 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 308 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 309 | CURRENCY_ID | NUMBER [10] | Currency type ID. | |
| 310 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |
| 311 | ACCT_ID | NUMBER [20] | Account ID. | The 251st |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 312 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | to 350th fields record 10 groups of bonus details. The 311st to 320th fields record the seventh group of bonus details. If *N* bonuses are involved in an adjustment, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 313 | BALANCE_TYPE | NUMBER[20] | Balance type. | |
| 314 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |
| 315 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | |
| 316 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 317 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 318 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 319 | CURRENCY_ID | NUMBER[10] | Currency type ID. | |
| 320 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |
| 321 | ACCT_ID | NUMBER[20] | Account ID. | The 251st to 350th |
| 322 | ACCT_BAL | NUMBER | Account book ID. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | ANCE_ID | [20] | | fields record 10 groups of bonus details. The 321st to 330th fields record the eighth group of bonus details. If *N* bonuses are involved in an adjustment, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 323 | BALANCE_TYPE | NUMBER [20] | Balance type. | |
| 324 | BONUS_AMOUNT | NUMBER [20] | Bonus amount. | |
| 325 | CURRENT_BALANCE | NUMBER [20] | Current fund balance. | |
| 326 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 327 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 328 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 329 | CURRENCY_ID | NUMBER [10] | Currency type ID. | |
| 330 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |
| 331 | ACCT_ID | NUMBER [20] | Account ID. | The 251st to 350th fields record 10 |
| 332 | ACCT_BALANCE_ID | NUMBER [20] | Account book ID. | |
| 333 | BALANCE_TYPE | NUMBER [20] | Balance type. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 334 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | groups of bonus details. The 331st to 340th fields record the ninth group of bonus details. If *N* bonuses are involved in an adjustment, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 335 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | |
| 336 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 337 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 338 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 339 | CURRENCY_ID | NUMBER[10] | Currency type ID. | |
| 340 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |
| 341 | ACCT_ID | NUMBER[20] | Account ID. | The 251st to 350th fields record 10 groups of bonus |
| 342 | ACCT_BALANCE_ID | NUMBER[20] | Account book ID. | |
| 343 | BALANCE_TYPE | NUMBER[20] | Balance type. | |
| 344 | BONUS_AMOUNT | NUMBER[20] | Bonus amount. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 345 | CURRENT_BALANCE | NUMBER[20] | Current fund balance. | details. The 341st to 350th fields record the tenth group of bonus details. If *N* bonuses are involved in an adjustment, the first *N* groups of bonus details fields are recorded and other groups of fields are left empty. |
| 346 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 347 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 348 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 349 | CURRENCY_ID | NUMBER[10] | Currency type ID. | |
| 350 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **4**: Roll over bonuses.<br>• **5**: Add a bonus account book.<br>• **6**: Add bonuses to an existing bonus account book. | |
| 351 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 351st to 460th fields record 10 groups of free unit reward details. The |
| 352 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 353 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 354 | FREE_UNIT | NUMBER | Free unit ID. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | _ID | [20] | | 351st to 361st fields record the first group of free unit reward details. If *N* free unit rewards are involved in an adjustment, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 355 | BONUS_AMOUNT | NUMBER [20] | Rewarded free unit amount. | |
| 356 | CURRENT_AMOUNT | NUMBER [20] | Current free unit amount. | |
| 357 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 358 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 359 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 360 | FU_MEASURE_ID | NUMBER [10] | Free unit measurement unit ID. | |
| 361 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 362 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 351st to 460th fields record 10 groups of free unit reward |
| 363 | FU_OWN_ID | NUMBER [20] | Free unit owner ID. | |
| 364 | FREE_UNIT_TYPE | NUMBER [20] | Free unit type. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 365 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | details. The 362nd to 372nd fields record the second group of free unit reward details. If *N* free unit rewards are involved in an adjustment, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 366 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 367 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 368 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 369 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 370 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 371 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 372 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 373 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 351st to 460th fields record 10 groups of free |
| 374 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 375 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | unit reward details. The 373rd to 383rd fields record the third group of free unit reward details. If *N* free unit rewards are involved in an adjustment, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 376 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 377 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 378 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 379 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 380 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 381 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 382 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 383 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 384 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 351st to 460th fields record |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 385 | FU_OWN_ID | NUMBER [20] | Free unit owner ID. | 10 groups of free unit reward details. The 384th to 394th fields record the fourth group of free unit reward details. If *N* free unit rewards are involved in an adjustment, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 386 | FREE_UNIT_TYPE | NUMBER [20] | Free unit type. | |
| 387 | FREE_UNIT_ID | NUMBER [20] | Free unit ID. | |
| 388 | BONUS_AMOUNT | NUMBER [20] | Rewarded free unit amount. | |
| 389 | CURRENT_AMOUNT | NUMBER [20] | Current free unit amount. | |
| 390 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 391 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 392 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 393 | FU_MEASURE_ID | NUMBER [10] | Free unit measurement unit ID. | |
| 394 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 395 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber | The 351st to |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **G**: subscriber group<br>• **C**: customer | 460th fields record 10 groups of free unit reward details. The 395th to 405th fields record the fifth group of free unit reward details. If *N* free unit rewards are involved in an adjustment, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 396 | FU_OWN_ID | NUMBER [20] | Free unit owner ID. | |
| 397 | FREE_UNIT_TYPE | NUMBER [20] | Free unit type. | |
| 398 | FREE_UNIT_ID | NUMBER [20] | Free unit ID. | |
| 399 | BONUS_AMOUNT | NUMBER [20] | Rewarded free unit amount. | |
| 400 | CURRENT_AMOUNT | NUMBER [20] | Current free unit amount. | |
| 401 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 402 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 403 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 404 | FU_MEASURE_ID | NUMBER [10] | Free unit measurement unit ID. | |
| 405 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 406 | FU_OWN_T | VARCHA | Free unit owner type. The options are as | The |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | YPE | R2[1] | follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | 351st to 460th fields record 10 groups of free unit reward details. The 406th to 416th fields record the sixth group of free unit reward details. If *N* free unit rewards are involved in an adjustment, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 407 | FU_OWN_ID | NUMBER [20] | Free unit owner ID. | |
| 408 | FREE_UNIT _TYPE | NUMBER [20] | Free unit type. | |
| 409 | FREE_UNIT _ID | NUMBER [20] | Free unit ID. | |
| 410 | BONUS_AM OUNT | NUMBER [20] | Rewarded free unit amount. | |
| 411 | CURRENT_ AMOUNT | NUMBER [20] | Current free unit amount. | |
| 412 | PRE_APPLY _TIME | DATE[14] | Original effective time of free units. | |
| 413 | PRE_EXPIR E_TIME | DATE[14] | Original expiration time of free units. | |
| 414 | CUR_EXPIR E_TIME | DATE[14] | Current expiration time of free units. | |
| 415 | FU_MEASU RE_ID | NUMBER [10] | Free unit measurement unit ID. | |
| 416 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 417 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 351st to 460th fields record 10 groups of free unit reward details. The 417th to 427th fields record the seventh group of free unit reward details. If *N* free unit rewards are involved in an adjustment, the first *N* groups of free unit reward details fields are recorded and other groups of fields |
| 418 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 419 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 420 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 421 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 422 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 423 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 424 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 425 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 426 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 427 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | are left empty. |
| 428 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 351st to 460th fields record 10 groups of free unit reward details. The 428th to 438th fields record the eighth group of free unit reward details. If *N* free unit rewards are involved in an adjustment, the first *N* groups of free unit reward details fields are recorded and other groups |
| 429 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 430 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 431 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 432 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 433 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 434 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 435 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 436 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 437 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 438 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | of fields are left empty. |
| 439 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 351st to 460th fields record 10 groups of free unit reward details. The 439th to 449th fields record the ninth group of free unit reward details. If *N* free unit rewards are involved in an adjustment, the first *N* groups of free unit reward details fields are recorded and |
| 440 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 441 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 442 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 443 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 444 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 445 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 446 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 447 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 448 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 449 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | other groups of fields are left empty. |
| 450 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | The 351st to 460th fields record 10 groups of free unit reward details. The 450th to 460th fields record the tenth group of free unit reward details. If *N* free unit rewards are involved in an adjustment, the first *N* groups of free unit reward details fields are |
| 451 | FU_OWN_ID | NUMBER[20] | Free unit owner ID. | |
| 452 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 453 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | |
| 454 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 455 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 456 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 457 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 458 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 459 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 460 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | | recorded and other groups of fields are left empty. |
| 461 | BrandID | NUMBER [10] | Brand ID.<br>In the process of adjusting a specified account, this field can be left empty.<br>This field can be left empty. | The 461st to 475th fields record additional adjustment information. These fields are provided in the baseline version and can be extended based on the site requirements. |
| 462 | MainOfferingID | NUMBER [10] | Primary offering ID.<br>In the process of adjusting a specified account, this field can be left empty.<br>This field can be left empty. | |
| 463 | PayType | VARCHAR2[1] | Payment type of a subscriber. The options are as follows:<br>• **0**: prepaid<br>• **1**: postpaid<br>• **2**: hybrid<br>In the process of adjusting a specified account, this field can be left empty.<br>This field can be left empty. | |
| 464 | StartTimeOfBillCycle | VARCHAR2[14] | Bill cycle start time, in the format *YYYYMMDDHHMMSS*.<br>This field cannot be left empty. | |
| 465 | Account | VARCHAR2[1024] | This field is reserved. | |
| 466 | MainBalanceInfo | VARCHAR2[255] | This field is reserved. | |
| 467 | ChgBalanceInfo | VARCHAR2[1024] | This field is reserved. | |
| 468 | ChgFreeUnitInfo | VARCHAR2[1024] | This field is reserved. | |
| 469 | UserState | VARCHAR2[10] | This field is reserved. | |
| 470 | oldUserState | VARCHAR2[10] | This field is reserved. | |
| 471 | SPID | VARCHA | This field is reserved. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | R2[20] | | |
| 472 | AdditionalInfo | VARCHAR2[256] | This field is reserved. | |
| 473 | Merchant | VARCHAR2[20] | This field is reserved. | |
| 474 | Service | VARCHAR2[20] | This field is reserved. | |

## 4.3.4 Switch Primary Offering CDR

This topic describes fields in Switch Primary Offering CDR.

Table 4-16 describes the fields in Switch Primary Offering CDR.

**Table 4-16** Switch Primary Offering CDR

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 1 | SubscriberNo | Char(32) | Indicates the subscriber number. The calling number with an international number prefix.<br>The number format is as follows: Country code + area number + PSTN<br>The number format is the format of the fixed-line phone number.<br>MSISDN<br>The number format is the format of the mobile phone number. Value range: numerals within 0-9 It is the Primary Identity of the subscriber.<br>Not null<br>Value Range: Digitals within [0,9],*,# For URI format, it should be [a,z],[A,Z],[0,9],@ |
| 2 | OriginalPrimaryOfferingIDAfter | Integer(4) | Indicates the ID number of the permanent Primary Offering ID after the switch.<br>Can be null<br>Value Range: >0 |
| 3 | OriginalPrimaryOfferingIDBefore | Integer(4) | Indicates the ID number of the permanent Primary Offering ID before the switch.<br>Can be null<br>Value Range: >0 |

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| 4 | TempPrimaryOfferingIDAfter | Integer(4) | Reserved<br>Can be null<br>Value Range: >0 |
| 5 | TempPrimaryOfferingIDBefore | Integer(4) | Reserved<br>Can be null<br>Value Range: >0 |
| 6 | TempOfferingIDExpiryDate | Char(14) | Reserved<br>Can be null<br>Value Range: Sting of 14 numerical digits [0-9] |
| 7 | Balance | Integer(8) | Indicates the balance of the subscriber. Main Balance Account ( BalanceType = 2000)<br>Can be null<br>Reserved<br>Value Range: >=0 |
| 8 | OriginNodeType | Char(8) | Record the value of OriginalNodeType, If OriginalNodeType parameter is coming in the WS request.<br>Can be null |
| 9 | OriginTransactionID | Char(32) | Record the value of OriginalTransactionID, If OriginalTransactionID parameter is coming in the WS request.<br>Can be null<br>Value Range: [A-Z, 0-9] |
| 10 | OriginHostName | Char(32) | Record the value of OriginHostName, if OriginHostName parameter is coming in the WS request.<br>Can be null<br>Value Range: [A-Z, 0-9] |
| 11 | OriginTimeStamp | Char(14) | Indicates the external system time stamp at the time of operation.<br>Format: YYYYMMDDhhmmss<br>Not null<br>Value Range: Sting of 14 numerical digits [0-9] |
| 12 | OriginOperatorID | Char(32) | Record the value of OriginOperatorID, If OriginOperatorID parameter is coming in the WS request<br>Can be null |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | Value Range: [A-Z, 0-9] |
| 13 | Status | Integer(8) | Indicates the lifecycle status of the subscriber.<br>• 1: Idle<br>• 2: Active<br>• 3: Barring<br>• 4: Suspend<br>• 8: Pool<br>• 9: Disconnect<br>Can be null<br>Value Range: [A-Z, 0-9] |
| 14 | ExternalData1 | Char(32) | Record the value of ExternalData1, If ExternalData1parameter is coming in the WS request.<br>Can be null<br>Value Range: [A-Z, 0-9] |
| 15 | ExternalData2 | Char(32) | Record the value of ExternalData2, If ExternalData2 parameter is coming in the WS request.<br>Can be null<br>Value Range: [A-Z, 0-9] |
| 16 | OldStatus | Integer(8) | Indicates the old subscriber life cycle status of the subscriber before the operation.<br>Value Range: [A-Z, 0-9]<br>Can be null |
| 17 | OldBalance | Integer(8) | Indicates the main account balance before operation.<br>Can be null<br>Value Range: >=0<br>Reserved |
| 18 | Fee | Integer(8) | Indicates the fee for the operation.<br>Can be null<br>Value Range: >=0 |
| 19 | OperationMode | Integer(8) | Indicates the mode of operation.<br>Can be null<br>Value Range: 0: IVR, 1: USSD, 2: SMS, 3: WebService, 4: GUI, 8 - System |
| 20 | OldTempOfferingIDExpiryDate | Char(14) | Reserved<br>Can be null |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description |
|---|---|---|---|
| | | | Value range: Sting of 14 numerical digits [0-9] |
| 21 | OperationResult | Char(9) | Indicates the status of the operation.<br>Not Null<br>Value Range: 0- Success or BMP Error Codes |
| 22 | TransactionType | Char(32) | Indicates the transaction type that is received from external system.<br>For example: ADMIN WEBSER BONUS<br>Can be null<br>Value Range: [0-9] and |
| 23 | TransactionCode | Char(32) | Indicates the transaction code that is received from external system.<br>Can be null<br>Value Range: [0-9] and |
| 24 | BEID | Integer(4) | Indicates the MVNOID of subscriber<br>Can be null<br>Value Range: >0 |
| 25 | UserNetType | Integer(4) | Indicates the Network type of subscriber.<br>Recode the network type of a product , it can be taken from BC_SUB_IDEN :<br>• 0:Not Specify<br>• 1:GSM<br>• 2:CDMA<br>• 3:ADSL<br>• 4:FIX<br>• 5:Wimax<br>• 6:VOIP<br>• 7:OTTO VOIP<br>Can be null<br>Value Range: >0 |

## 4.3.5 Loan CDR

This topic describes fields in loan CDRs generated on the CBP.

Table 4-17 describes fields in loan CDRs.

**Table 4-17** Loan CDR

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 1 | SUB_ID | NUMBER [20] | Subscriber ID.<br>The default value is **0**.<br>This field cannot be left empty. | The first 19 fields record the first part of basic information in CDR files. The meaning and length of these fields are fixed. |
| 2 | PRI_IDENTITY | VARCHAR2[64] | Subscriber primary identifier.<br>If a primary identifier is an MSISDN or a PSTN, the formats are as follows:<br>• Country code + MSISDN<br>• Country code + Area code + PSTN<br>If a primary identifier is of other types, the value is the number that is transferred. | |
| 3 | OPER_DATE | DATE[14] | Operation time.<br>This field cannot be left empty. | |
| 4 | OPER_TYPE | VARCHAR2[1] | Operation type. The options are as follows:<br>• **L**: loan<br>• **R**: loan payment by recharge<br>• **T**: loan payment by transfer<br>• **A**: loan payment by adjustment<br>• **F**: forcible loan payment<br>• **C**: loan payment cancellation due to recharge reversal<br>When the loan and handling fee payment is canceled due to recharge reversal, the system needs to update the loan information table and record the historical loan log table.<br>This field cannot be left empty. | |
| 5 | LOAN_BALANCE_TYPE | NUMBER [20] | Loan account book type.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 6 | INIT_LOAN_AMT | NUMBER [20] | Initial loan amount.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 7 | INIT_LOAN_POUNDAGE | NUMBER [20] | Initial loan handling fee.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 8 | LOAN_AM | NUMBER | Unpaid loan amount. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | T | [20] | The default value is **0**.<br>This field cannot be left empty. | |
| 9 | LOAN_POUNDAGE | NUMBER [20] | Unpaid loan handling fee.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 10 | REPAY_AMT | NUMBER [20] | Loan payment amount.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 11 | REPAY_POUNDAGE | NUMBER [20] | Payment amount of the loan handling fee.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 12 | ETU_GRACE_DATE | DATE[14] | Loan payment deadline.<br>This field can be left empty. | |
| 13 | FORCE_REPAY_DATE | DATE[14] | Forcible payment date.<br>This field can be left empty. | |
| 14 | TRANS_ID | VARCHAR2[64] | Sequence number of a transaction.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 15 | ENTRY_DATE | DATE[14] | Time when a record is created.<br>This field cannot be left empty. | |
| 16 | PRI_OFFERING | NUMBER [20] | Primary offering.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 17 | LOAN_PENALTY | NUMBER [20] | Loan penalty that is paid currently.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 18 | LOAN_PENALTY_LEFT | NUMBER [20] | Remaining loan penalty.<br>The default value is **0**.<br>This field cannot be left empty. | |
| 19 | LOAN_OCCUR_DATE | DATE[14] | Time when a loan is applied.<br>This field can be left empty. | |
| 20 | ACCT_ID | NUMBER [20] | Account ID. | The 20th to 149th fields record |
| 21 | ACCT_BA | NUMBER | ID of a balance account. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | LANCE_ID | [20] | | 10 groups of balance change information.<br>The 20th to 32nd fields record the first group of balance change information. If *N* balance changes are involved, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 22 | BALANCE_TYPE | NUMBER [20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | |
| 23 | CUR_BALANCE | NUMBER [20] | Current balance. | |
| 24 | CHG_BALANCE | NUMBER [20] | Change amount of the balance. | |
| 25 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 26 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 27 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 28 | BAL_PAY_PLAN_ID | NUMBER [20] | Balance payment plan ID. | |
| 29 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **0**: expend<br>• **1**: perform accounting<br>• **2**: update the income<br>• **3**: increase the income | |
| 30 | CURRENCYE_ID | NUMBER [10] | Currency type ID. | |
| 31 | CONTENT_PROD_ID | NUMBER [20] | Content type ID. | |
| 32 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | |
| 33 | ACCT_ID | NUMBER [20] | Account ID. | The 20th to 149th fields record 10 groups of balance change information. |
| 34 | ACCT_BALANCE_ID | NUMBER [20] | ID of a balance account. | |
| 35 | BALANCE_TYPE | NUMBER [20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | |
| 36 | CUR_BALANCE | NUMBER [20] | Current balance. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 37 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | The 33rd to 45nd fields record the second group of balance change information. If *N* balance changes are involved, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 38 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 39 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 40 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 41 | BAL_PAY_PLAN_ID | NUMBER[20] | Balance payment plan ID. | |
| 42 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: expend<br>• **1**: perform accounting<br>• **2**: update the income<br>• **3**: increase the income | |
| 43 | CURRENCYE_ID | NUMBER[10] | Currency type ID. | |
| 44 | CONTENT_PROD_ID | NUMBER[20] | Content type ID. | |
| 45 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | |
| 46 | ACCT_ID | NUMBER[20] | Account ID. | The 20th to 149th fields record 10 groups of balance change information.<br>The 46th to 58th fields record the third group of balance change |
| 47 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 48 | BALANCE_TYPE | NUMBER[20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | |
| 49 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 50 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 51 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 52 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 53 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | information. If *N* balance changes are involved, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 54 | BAL_PAY_PLAN_ID | NUMBER[20] | Balance payment plan ID. | |
| 55 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: expend<br>• **1**: perform accounting<br>• **2**: update the income<br>• **3**: increase the income | |
| 56 | CURRENCYE_ID | NUMBER[10] | Currency type ID. | |
| 57 | CONTENT_PROD_ID | NUMBER[20] | Content type ID. | |
| 58 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | |
| 59 | ACCT_ID | NUMBER[20] | Account ID. | The 20th to 149th fields record 10 groups of balance change information.<br>The 59th to 71st fields record the fourth group of balance change information. If *N* balance changes are involved, the first *N* groups of |
| 60 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 61 | BALANCE_TYPE | NUMBER[20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | |
| 62 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 63 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 64 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 65 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 66 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 67 | BAL_PAY_PLAN_ID | NUMBER[20] | Balance payment plan ID. | |
| 68 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: expend | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **1**: perform accounting<br>• **2**: update the income<br>• **3**: increase the income | balance change fields are recorded and other groups of fields are left empty. |
| 69 | CURRENCYE_ID | NUMBER[10] | Currency type ID. | |
| 70 | CONTENT_PROD_ID | NUMBER[20] | Content type ID. | |
| 71 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | |
| 72 | ACCT_ID | NUMBER[20] | Account ID. | The 20th to 149th fields record 10 groups of balance change information.<br>The 72nd to 84th fields record the fifth group of balance change information. If *N* balance changes are involved, the first *N* groups of balance change fields are recorded and other groups of fields are left |
| 73 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 74 | BALANCE_TYPE | NUMBER[20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | |
| 75 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 76 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 77 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 78 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 79 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 80 | BAL_PAY_PLAN_ID | NUMBER[20] | Balance payment plan ID. | |
| 81 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: expend<br>• **1**: perform accounting<br>• **2**: update the income<br>• **3**: increase the income | |
| 82 | CURRENCYE_ID | NUMBER[10] | Currency type ID. | |
| 83 | CONTENT_PROD_ID | NUMBER[20] | Content type ID. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 84 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | empty. |
| 85 | ACCT_ID | NUMBER[20] | Account ID. | The 20th to 149th fields record 10 groups of balance change information.<br>The 85th to 97th fields record the sixth group of balance change information. If *N* balance changes are involved, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 86 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 87 | BALANCE_TYPE | NUMBER[20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | |
| 88 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 89 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 90 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 91 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 92 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 93 | BAL_PAY_PLAN_ID | NUMBER[20] | Balance payment plan ID. | |
| 94 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: expend<br>• **1**: perform accounting<br>• **2**: update the income<br>• **3**: increase the income | |
| 95 | CURRENCYE_ID | NUMBER[10] | Currency type ID. | |
| 96 | CONTENT_PROD_ID | NUMBER[20] | Content type ID. | |
| 97 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | |
| 98 | ACCT_ID | NUMBER[20] | Account ID. | The 20th to 149th fields record 10 |
| 99 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 100 | BALANCE_TYPE | NUMBER[20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | groups of balance change information.<br>The 98th to 110th fields record the seventh group of balance change information. If *N* balance changes are involved, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 101 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 102 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 103 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 104 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 105 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 106 | BAL_PAY_PLAN_ID | NUMBER[20] | Balance payment plan ID. | |
| 107 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: expend<br>• **1**: perform accounting<br>• **2**: update the income<br>• **3**: increase the income | |
| 108 | CURRENCYE_ID | NUMBER[10] | Currency type ID. | |
| 109 | CONTENT_PROD_ID | NUMBER[20] | Content type ID. | |
| 110 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | |
| 111 | ACCT_ID | NUMBER[20] | Account ID. | The 20th to 149th fields record 10 groups of balance change information.<br>The 111st to 123rd |
| 112 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 113 | BALANCE_TYPE | NUMBER[20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | |
| 114 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 115 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 116 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | fields record the eighth group of balance change information. If *N* balance changes are involved, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 117 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 118 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 119 | BAL_PAY_PLAN_ID | NUMBER[20] | Balance payment plan ID. | |
| 120 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: expend<br>• **1**: perform accounting<br>• **2**: update the income<br>• **3**: increase the income | |
| 121 | CURRENCYE_ID | NUMBER[10] | Currency type ID. | |
| 122 | CONTENT_PROD_ID | NUMBER[20] | Content type ID. | |
| 123 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | |
| 124 | ACCT_ID | NUMBER[20] | Account ID. | The 20th to 149th fields record 10 groups of balance change information.<br>The 124th to 136th fields record the ninth group of balance change information. If *N* |
| 125 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 126 | BALANCE_TYPE | NUMBER[20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | |
| 127 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 128 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 129 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 130 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 131 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 132 | BAL_PAY_PLAN_ID | NUMBER[20] | Balance payment plan ID. | balance changes are involved, the first *N* groups of balance change fields are recorded and other groups of fields are left empty. |
| 133 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: expend<br>• **1**: perform accounting<br>• **2**: update the income<br>• **3**: increase the income | |
| 134 | CURRENCYE_ID | NUMBER[10] | Currency type ID. | |
| 135 | CONTENT_PROD_ID | NUMBER[20] | Content type ID. | |
| 136 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | |
| 137 | ACCT_ID | NUMBER[20] | Account ID. | The 20th to 149th fields record 10 groups of balance change information.<br>The 137th to 149th fields record the tenth group of balance change information. If *N* balance changes are involved, the first *N* groups of balance change |
| 138 | ACCT_BALANCE_ID | NUMBER[20] | ID of a balance account. | |
| 139 | BALANCE_TYPE | NUMBER[20] | ID of the balance type.<br>Set this field based on the **ACCT_BALANCE_ID** value. | |
| 140 | CUR_BALANCE | NUMBER[20] | Current balance. | |
| 141 | CHG_BALANCE | NUMBER[20] | Change amount of the balance. | |
| 142 | PRE_APPLY_TIME | DATE[14] | Original effective time of the account book. | |
| 143 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of the account book. | |
| 144 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of the account book. | |
| 145 | BAL_PAY_PLAN_ID | NUMBER[20] | Balance payment plan ID. | |
| 146 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **0**: expend<br>• **1**: perform accounting<br>• **2**: update the income | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | | | • **3**: increase the income | fields are recorded and other groups of fields are left empty. |
| 147 | CURRENCYE_ID | NUMBER[10] | Currency type ID. | |
| 148 | CONTENT_PROD_ID | NUMBER[20] | Content type ID. | |
| 149 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | |
| 150 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | The 150th to 299th fields record 10 groups of free unit reward details.<br>The 150th to 164th fields record the first group of free unit reward details. If *N* free unit reward details are involved, the first *N* groups of free unit reward details fields are recorded and other groups of fields are left |
| 151 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 152 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 153 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 154 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 155 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | |
| 156 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 157 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 158 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 159 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 160 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 161 | CONTENT | NUMBER | Content type ID. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | _PROD_ID | [20] | | empty. |
| 162 | EXCHANGE_SRV_AMT | NUMBER [20] | Traffic length. | |
| 163 | SRV_TYPE | NUMBER [10] | Traffic type. | |
| 164 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | |
| 165 | FREE_UNIT_ID | NUMBER [20] | Free unit ID. | The 150th to 299th fields record 10 groups of free unit reward details.<br>The 165th to 179th fields record the second group of free unit reward details. If *N* free unit reward details are involved, the first *N* groups of free unit reward details fields are recorded and other groups |
| 166 | FREE_UNIT_TYPE | NUMBER [20] | Free unit type. | |
| 167 | BONUS_AMOUNT | NUMBER [20] | Rewarded free unit amount. | |
| 168 | CURRENT_AMOUNT | NUMBER [20] | Current free unit amount. | |
| 169 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 170 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | |
| 171 | FU_OWN_ID | NUMBER [20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 172 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 173 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 174 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 175 | FU_MEASURE_ID | NUMBER [10] | Free unit measurement unit ID. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 176 | CONTENT_PROD_ID | NUMBER[20] | Content type ID. | of fields are left empty. |
| 177 | EXCHANGE_SRV_AMT | NUMBER[20] | Traffic length. | |
| 178 | SRV_TYPE | NUMBER[10] | Traffic type. | |
| 179 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | |
| 180 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | The 150th to 299th fields record 10 groups of free unit reward details.<br>The 180th to 194th fields record the third group of free unit reward details. If *N* free unit reward details are involved, the first *N* groups of free unit reward details fields are recorded and other groups |
| 181 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 182 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 183 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 184 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 185 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | |
| 186 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 187 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 188 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 189 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 190 | FU_MEAS | NUMBER | Free unit measurement unit ID. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | URE_ID | [10] | | of fields are left empty. |
| 191 | CONTENT_PROD_ID | NUMBER [20] | Content type ID. | |
| 192 | EXCHANGE_SRV_AMT | NUMBER [20] | Traffic length. | |
| 193 | SRV_TYPE | NUMBER [10] | Traffic type. | |
| 194 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | |
| 195 | FREE_UNIT_ID | NUMBER [20] | Free unit ID. | The 150th to 299th fields record 10 groups of free unit reward details.<br>The 195th to 209th fields record the fourth group of free unit reward details. If *N* free unit reward details are involved, the first *N* groups of free unit reward details fields are recorded |
| 196 | FREE_UNIT_TYPE | NUMBER [20] | Free unit type. | |
| 197 | BONUS_AMOUNT | NUMBER [20] | Rewarded free unit amount. | |
| 198 | CURRENT_AMOUNT | NUMBER [20] | Current free unit amount. | |
| 199 | OPER_TYPE | NUMBER [10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 200 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | |
| 201 | FU_OWN_ID | NUMBER [20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 202 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 203 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 204 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |

 Copyright © Huawei Technologies Co., Ltd. 

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 205 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | and other groups of fields are left empty. |
| 206 | CONTENT_PROD_ID | NUMBER[20] | Content type ID. | |
| 207 | EXCHANGE_SRV_AMT | NUMBER[20] | Traffic length. | |
| 208 | SRV_TYPE | NUMBER[10] | Traffic type. | |
| 209 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | |
| 210 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | The 150th to 299th fields record 10 groups of free unit reward details.<br>The 210th to 224th fields record the fifth group of free unit reward details. If *N* free unit reward details are involved, the first *N* groups of free unit reward details fields are recorded |
| 211 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 212 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 213 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 214 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 215 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | |
| 216 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 217 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 218 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 219 | CUR_EXPI | DATE[14 | Current expiration time of free units. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | RE_TIME | ] | | and other groups of fields are left empty. |
| 220 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 221 | CONTENT_PROD_ID | NUMBER[20] | Content type ID. | |
| 222 | EXCHANGE_SRV_AMT | NUMBER[20] | Traffic length. | |
| 223 | SRV_TYPE | NUMBER[10] | Traffic type. | |
| 224 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | |
| 225 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | The 150th to 299th fields record 10 groups of free unit reward details.<br>The 225th to 239th fields record the sixth group of free unit reward details. If *N* free unit reward details are involved, the first *N* groups of free unit reward details fields are |
| 226 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 227 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 228 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 229 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 230 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | |
| 231 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 232 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 233 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 234 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | recorded and other groups of fields are left empty. |
| 235 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 236 | CONTENT_PROD_ID | NUMBER[20] | Content type ID. | |
| 237 | EXCHANGE_SRV_AMT | NUMBER[20] | Traffic length. | |
| 238 | SRV_TYPE | NUMBER[10] | Traffic type. | |
| 239 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | |
| 240 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | The 150th to 299th fields record 10 groups of free unit reward details.<br>The 240th to 254th fields record the seventh group of free unit reward details. If *N* free unit reward details are involved, the first *N* groups of free unit reward |
| 241 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 242 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 243 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 244 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 245 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | |
| 246 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 247 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |
| 248 | PRE_EXPI | DATE[14 | Original expiration time of free units. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | RE_TIME | ] | | details fields are recorded and other groups of fields are left empty. |
| 249 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 250 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 251 | CONTENT_PROD_ID | NUMBER[20] | Content type ID. | |
| 252 | EXCHANGE_SRV_AMT | NUMBER[20] | Traffic length. | |
| 253 | SRV_TYPE | NUMBER[10] | Traffic type. | |
| 254 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | |
| 255 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | The 150th to 299th fields record 10 groups of free unit reward details.<br>The 255th to 269th fields record the eighth group of free unit reward details. If *N* free unit reward details are involved, the first *N* groups of free |
| 256 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 257 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 258 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 259 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 260 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | |
| 261 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 262 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 263 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | unit reward details fields are recorded and other groups of fields are left empty. |
| 264 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 265 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 266 | CONTENT_PROD_ID | NUMBER[20] | Content type ID. | |
| 267 | EXCHANGE_SRV_AMT | NUMBER[20] | Traffic length. | |
| 268 | SRV_TYPE | NUMBER[10] | Traffic type. | |
| 269 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | |
| 270 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | The 150th to 299th fields record 10 groups of free unit reward details.<br>The 270th to 284th fields record the ninth group of free unit reward details. If *N* free unit reward details are involved, the first *N* groups of free |
| 271 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 272 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 273 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 274 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 275 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | |
| 276 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |
| 277 | PRE_APPL | DATE[14 | Original effective time of free units. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| | Y_TIME | ] | | unit reward details fields are recorded and other groups of fields are left empty. |
| 278 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 279 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 280 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 281 | CONTENT_PROD_ID | NUMBER[20] | Content type ID. | |
| 282 | EXCHANGE_SRV_AMT | NUMBER[20] | Traffic length. | |
| 283 | SRV_TYPE | NUMBER[10] | Traffic type. | |
| 284 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | |
| 285 | FREE_UNIT_ID | NUMBER[20] | Free unit ID. | The 150th to 299th fields record 10 groups of free unit reward details.<br>The 285th to 299th fields record the tenth group of free unit reward details. If *N* free unit reward details are involved, the first |
| 286 | FREE_UNIT_TYPE | NUMBER[20] | Free unit type. | |
| 287 | BONUS_AMOUNT | NUMBER[20] | Rewarded free unit amount. | |
| 288 | CURRENT_AMOUNT | NUMBER[20] | Current free unit amount. | |
| 289 | OPER_TYPE | NUMBER[10] | Operation type. The options are as follows:<br>• **3**: Roll over free units.<br>• **4**: Add a free unit instance.<br>• **5**: Add free units to an existing free unit instance. | |
| 290 | FU_OWN_TYPE | VARCHAR2[1] | Free unit owner type. The options are as follows:<br>• **S**: subscriber<br>• **G**: subscriber group<br>• **C**: customer | |
| 291 | FU_OWN_ID | NUMBER[20] | Free unit owner ID.<br>Set this field based on the **FU_OWN_TYPE** value. | |

| SN | Field Name | Field Type | Description | Field Category |
|---|---|---|---|---|
| 292 | PRE_APPLY_TIME | DATE[14] | Original effective time of free units. | *N* groups of free unit reward details fields are recorded and other groups of fields are left empty. |
| 293 | PRE_EXPIRE_TIME | DATE[14] | Original expiration time of free units. | |
| 294 | CUR_EXPIRE_TIME | DATE[14] | Current expiration time of free units. | |
| 295 | FU_MEASURE_ID | NUMBER[10] | Free unit measurement unit ID. | |
| 296 | CONTENT_PROD_ID | NUMBER[20] | Content type ID. | |
| 297 | EXCHANGE_SRV_AMT | NUMBER[20] | Traffic length. | |
| 298 | SRV_TYPE | NUMBER[10] | Traffic type. | |
| 299 | RESERVED_FLAG | VARCHAR2[4] | Reserved. | |
| 300 | ADDITIONAL_INFO | VARCHAR2[2048] | Additional information.<br>Format: *owner_cust_id*,*billcycleid*<br>Fields must be separated with a comma (,). | |

# 4.4 Daily Dump Files

This section describes the dump files contents for loan.

## 4.4.1 Loan Daily Dump

The CBS provides dump files every day for the RA to audit the loan of the CBS.

The format of the exported file is as follows:

- File name: cbs_rb_loaninfo_#flow.LastDay#_#flow.data_source#_#flow.be_id#_#fileIndexFormat#.unl
- Fields in the file are separated by ",", and no separator is added at the end of each record.

Table 4-18 describes the fields in loan daily dump files.

**Table 4-18** loan daily dump

| Columns | DATA Type | Description |
|---|---|---|
| MSISDN | Number | Mobile number.<br>8-20 digits |
| Sub_ID | String | Unique ID of the customer in CBS<br>10-24 digits |
| LoanTransID | String | Unique transactions ID generated by CBS internally.<br>10-24 digits |
| Loan_Occur_Date | DATA | When Loan is given to the customer.<br>Date and time in format YYYYMMDDHHMMSS |
| initial_loanAmt | Number | Initial Loan given end customer.<br>1 to 10 digits |
| initial_loanPoundage | Number | Initial service charges to be paid by the end customer.<br>1-10 digits |
| PaidAmount | Number | Amount paid (Loanamt+ Loan Poundage)<br>1-10 digits |
| RemainingAmount | Number | Amount to be paid (Loanamt+ Loan Poundage)<br>1-10 digits |
| GraceDate | DATA | Final to clear the loan.<br>Date and time in format YYYYMMDDHHMMSS |
| LoanStatus | Char | Loan status.<br>• O: Open<br>• C: Closed |

 Copyright © Huawei Technologies Co., Ltd. 