

Fine-Structure Constant: Unit Conventions Why $\alpha = 1$ can
be set Supplement to Document 011

Contents

.1	Introduction and Reference to Document 011	1
	Delimitation from Document 011	1
	Why Two Documents?	2
.2	Different Unit Conventions for α	2
	Overview of Systems	2
.3	Heaviside-Lorentz Units in Detail	2
	What are Heaviside-Lorentz Units?	2
	Why epsilon 0 = 1	3
	Fine-Structure Constant in Heaviside-Lorentz	3
.4	Two Variants of Heaviside-Lorentz	3
	Variant A	3
	Variant B: Keep ϵ_0 , $\alpha \approx 1/137$	4
	Which variant is used?	4
.5	Reconstruction of SI Values from T0	5
	The Central Principle	5
	Example: Fine-Structure Constant	5
	Example: Gravitational Constant	5
	Why does this work?	6
	Comparison Table	6
	Important Conclusion	6
.6	Why can $\alpha = 1$ be set?	6
	Fundamental Insight	6
	Step-by-Step Justification	6
	Analogy: Temperature Scales	7
.7	Consequences of Redefining the Coulomb	7
	What does it mean to redefine elementary charge?	7
	Effects on Electromagnetic Quantities	8
	Electric Current (Ampere)	8
	Electric Voltage (Volt)	8
	Capacitance (Farad)	8
	Are these changes "real"?	8
.8	Practical Impacts on Everyday Calculations	8
	Motivation	8
	Example 1: Ohm's Law	8
	In SI Units (Standard)	8
	In Heaviside-Lorentz with $\alpha = 1$	9
	Example 2: Power of a Light Bulb	9
	In SI Units	9
	In Heaviside-Lorentz with $\alpha = 1$	9
	Example 3: Charging a Capacitor	10
	In SI Units	10

	In Heaviside-Lorentz with $\alpha = 1$	10
	Example 4: RC Time Constant	10
	In SI Units	10
	In Heaviside-Lorentz with $\alpha = 1$	11
	Summary of Practical Calculations	11
	Important Insights	11
	Why does nobody use $\alpha = 1$ in practice?	11
.9	Practical Aspects of Different Systems	12
	Advantages and Disadvantages: SI Units	12
	Advantages and Disadvantages: Heaviside-Lorentz with $\alpha = 1$	12
	Advantages and Disadvantages: Natural Units with $\alpha \approx 1/137$	12
.10	Historical Development	13
	Gauss Units (cgs)	13
	SI Units (MKSA)	13
	Heaviside-Lorentz	13
	Natural Units	13
.11	Fine's Inequality vs. Fine-Structure Constant	13
	Frequent Confusion	13
	Fine's Inequality	13
	Fine-Structure Constant	14
	No Conceptual Connection	14
.12	Summary	14
	Core Statements	14
	For Further Details See Document 011	14
0.1	Conversion Table: SI $\leftrightarrow$ Heaviside-Lorentz	15
0.2	Sample Calculation: Coulomb's Law	15
	In SI Units	15
	In HL Units ($\hbar = c = \epsilon_0 = 1$)	15

Correction notes

Corrections from the calculation check (30 Sept. 2026). The following places are corrected or annotated in the text; each carries a dated note with the previous value:

- G_{SI} formula: $\frac{\xi^2}{4m_e} \times C_{dim} \times C_{conv} \rightarrow \frac{\xi^2}{4m_e} \times C_{conv} \times K_{frak}$ – with C_{dim} but without the compensating factor E_{char} , G would be too small by a factor of $E_{char} = 28.8$.
- Heaviside-Lorentz units: $\hbar = c = 4\pi\epsilon_0 = 1$, $\alpha = e^2$, $e = 1 \rightarrow \hbar = c = \epsilon_0 = 1$, $\alpha = e^2/(4\pi)$, $e = \sqrt{4\pi} \approx 3.545$ (definition, Coulomb/Maxwell, variants A/B, appendix table).
- $e_{HL} = \sqrt{4\pi\epsilon_0\hbar c}$: $5.29 \times 10^{-19} \rightarrow 1.877 \times 10^{-18} \text{ C}$ ($= \sqrt{137} e$).
- α deviation with $E_0 = 7.398 \text{ MeV}$: $0.03 \% \rightarrow 0.0005 \%$.
- Conversion examples 1–4: numerical values converted in the direction of the defined units (e.g. R_{new} : $0.73 \rightarrow 13\,700$, U_{new} : $17.1 \rightarrow 2341$); the back-conversion $17.1 \times 0.085 = 200 \text{ V}$ was wrong ($= 1.45$).
- Coulomb example: r : $0.197 \times 10^6 \rightarrow 5.07 \times 10^{-4} \text{ eV}^{-1}$, 1 eV^2 : $9 \times 10^5 \rightarrow 8.12 \times 10^{-13} \text{ N}$, $F = e^2/r^2 \rightarrow e^2/(4\pi r^2) = \alpha/r^2$; $2.3 \times 10^{-8} \text{ N}$ follows only with $\alpha = 1/137$.
- $E_0 = \sqrt{m_e m_\mu}$: $7.398 \rightarrow 7.348 \text{ MeV}$ (bare; 7.398 MeV is the corrected value); practical example household/USB: $1.96/0.43 \rightarrow 2692/58.5 \text{ V}_{new}$; Gaussian system: $\epsilon_0 = 1 \rightarrow 4\pi\epsilon_0 = 1$.
- (2 Oct. 2026) Notation f : scaling factor f of the units — not a frequency; note in the text (Doc. 190, R147).

Abstract

This document addresses aspects of the fine-structure constant not discussed in detail in Document 011. The focus is on providing a comprehensive justification for why and how $\alpha = 1$ can be set (Heaviside-Lorentz convention), the physical consequences of different unit systems, and the historical and practical implications of redefining electromagnetic units.

For T0-specific derivations (characteristic energy E_0 , geometric parameter ξ , T0 formula $\alpha = \xi(E_0/1\text{MeV})^2$) see Document 011.

.1 Introduction and Reference to Document 011

Delimitation from Document 011

Document 011 covers in detail:

- T0 derivation: $\alpha = \xi(E_0/1\text{MeV})^2$
- Characteristic energy: $E_0 = \sqrt{m_e \cdot m_\mu} = 7.348 \text{ MeV}$ (bare), corrected $E_0 = 7.348/\sqrt{K_{frak}} = 7.398 \text{ MeV}$ (*Corrected on 30 Sept. 2026: previously $\sqrt{m_e \cdot m_\mu} = 7.398 \text{ MeV} - \sqrt{0.511 \times 105.658} = 7.348 \text{ MeV}$; 7.398 MeV is the value divided by $\sqrt{K_{frak}}$*)
- Geometric parameter: $\xi = \frac{4}{3} \times 10^{-4}$
- Alternative formulations: with μ_0 , with r_e/λ_C , etc.
- Historical context (Sommerfeld)
- Natural units and energy as fundamental field

- Detailed dimensional analysis of all formulations
This document (044) focuses on:
 - **Why** $\alpha = 1$ can be set (detailed justification)
 - **How** different unit conventions work
 - Consequences of redefining the Coulomb
 - Heaviside-Lorentz vs. Gauss vs. SI units
 - Practical aspects and historical development
 - Fine's inequality vs. fine-structure constant (name confusion)

Why Two Documents?

Document 011: T0 theory and physical derivations

Document 044: Unit systems and conventions

Both complement each other, with minimal overlap.

.2 Different Unit Conventions for α

Overview of Systems

The fine-structure constant can be expressed in different unit systems:

System	Formula	Value
SI Standard	$\alpha = \frac{e^2}{4\pi\epsilon_0\hbar c}$	$\approx \frac{1}{137}$
Heaviside-Lorentz	$\alpha = \frac{e^2}{4\pi}$ (with $\hbar = c = \epsilon_0 = 1$)	1 or $\frac{1}{137}$
Gauss (cgs)	$\alpha = \frac{e^2}{\hbar c}$	$\approx \frac{1}{137}$

Table 1: Unit systems for α

(Corrected on 30 Sept. 2026: previously Heaviside-Lorentz with $\hbar = c = 4\pi\epsilon_0 = 1$ – Heaviside-Lorentz is rationalised and sets $\epsilon_0 = 1$, so $\alpha = e^2/(4\pi)$; $4\pi\epsilon_0 = 1$ with $\alpha = e^2$ is the Gaussian convention.)

Important: The numerical value depends on the convention, the *physical* predictions do not.

.3 Heaviside-Lorentz Units in Detail

What are Heaviside-Lorentz Units?

The Heaviside-Lorentz system is a variant of natural units, specifically for electrodynamics:

$$\boxed{\hbar = c = \epsilon_0 = 1} \quad (1)$$

Consequences:

- Electromagnetic equations become more symmetric
- The factor 4π disappears from many formulas
- Elementary charge is redefined

Why $\varepsilon_0 = 1$?

In SI units, 4π appears in many electromagnetic formulas:

$$\vec{E} = \frac{1}{4\pi\varepsilon_0} \frac{q}{r^2} \hat{r} \quad (\text{Coulomb's law}) \quad (2)$$

$$\nabla \cdot \vec{E} = \frac{\rho}{\varepsilon_0} \quad (\text{Maxwell's equation}) \quad (3)$$

With $\varepsilon_0 = 1$, these become:

$$\vec{E} = \frac{q}{4\pi r^2} \hat{r} \quad (4)$$

$$\nabla \cdot \vec{E} = \rho \quad (5)$$

The factor 4π remains only in Coulomb's law (sphere surface $4\pi r^2$); Maxwell's equations become free of 4π .

(Corrected on 30 Sept. 2026: previously $\hbar = c = 4\pi\varepsilon_0 = 1$ with $\vec{E} = q/r^2 \hat{r}$, $\nabla \cdot \vec{E} = 4\pi\rho$ and the statement that the factor 4π moves from Coulomb's law to Poisson's equation – that is the Gaussian convention; Heaviside-Lorentz sets $\varepsilon_0 = 1$, giving $\vec{E} = q/(4\pi r^2) \hat{r}$ and $\nabla \cdot \vec{E} = \rho$.)

Fine-Structure Constant in Heaviside-Lorentz

Starting point (SI):

$$\alpha = \frac{e^2}{4\pi\varepsilon_0 \hbar c} \quad (6)$$

With $\hbar = c = \varepsilon_0 = 1$:

$$\alpha = \frac{e^2}{4\pi \cdot 1 \cdot 1 \cdot 1} = \frac{e^2}{4\pi} \quad (7)$$

(Corrected on 30 Sept. 2026: previously $\alpha = e^2/(1 \cdot 1 \cdot 1) = e^2$ – with $\varepsilon_0 = 1$ the factor 4π stays in the denominator.)

Now the crucial question: What value does e have in this system?

.4 Two Variants of Heaviside-Lorentz

Variant A: Normalize e so that $\alpha = 1$

Approach: We define the unit of charge such that $\alpha = 1$.

Since $\alpha = e^2/(4\pi)$ in HL units:

$$e^2 = 4\pi \quad \Rightarrow \quad e = \sqrt{4\pi} \approx 3.545 \quad (8)$$

Physical meaning:

- Elementary charge becomes a *dimensionless unit*
- Electromagnetic coupling is "normalized"
- Charge is measured in units of $\sqrt{\hbar c}$

(Corrected on 30 Sept. 2026: previously $e^2 = 1 \Rightarrow e = 1$ – from $\alpha = e^2/(4\pi) = 1$ it follows that $e = \sqrt{4\pi} \approx 3.545$, cf. A267.)

What changes?

The elementary charge gets a new numerical value:

$$e_{\text{HL}} = \sqrt{4\pi\varepsilon_0 \hbar c} \quad (\text{expressed in SI units}) \quad (9)$$

Numerically:

$$e_{\text{HL}} = \sqrt{4\pi \times 8.854 \times 10^{-12} \times 1.055 \times 10^{-34} \times 3 \times 10^8} \quad (10)$$

$$\approx 1.877 \times 10^{-18} \text{ C} \quad (11)$$

This is $\sqrt{137.036} \times e_{\text{SI}}$ – the charge for which $\alpha = 1$. In the HL charge unit $\sqrt{\epsilon_0 \hbar c} \approx 5.29 \times 10^{-19} \text{ C}$ it has the numerical value $\sqrt{4\pi}$.

(Corrected on 30 Sept. 2026: previously $e_{\text{HL}} \approx 5.29 \times 10^{-19} - \sqrt{4\pi \times 8.854 \times 10^{-12} \times 1.055 \times 10^{-34} \times 3 \times 10^8} = \sqrt{3.52 \times 10^{-36}} = 1.877 \times 10^{-18} \text{ C}$; 5.29×10^{-19} is $\sqrt{\epsilon_0 \hbar c}$ without the 4π and does not match $\sqrt{137} e$.)

Variant B: Keep e , $\alpha \approx 1/137$

Approach: The elementary charge retains its "natural" value.

In this case:

$$\alpha = \frac{e^2}{4\pi} \approx \frac{1}{137} \quad (12)$$

because e in these units has the value $\sqrt{4\pi/137} \approx 0.303$.

(Corrected on 30 Sept. 2026: previously $\alpha = e^2$ and $e \approx 1/\sqrt{137}$ – in HL $\alpha = e^2/(4\pi)$, so $e = \sqrt{4\pi\alpha} = 0.303$; $e = 1/\sqrt{137}$ holds in the Gaussian convention.)

Physical meaning:

- Charge retains physical meaning
- α remains $\approx 1/137$
- Only the mathematical form simplifies

Which variant is used?

In practice:

- **T0 theory:** Sets all constants = 1 ($c = \hbar = \alpha = G = 1$)
- **Theoretical high-energy physics:** Often $\hbar = c = 1$, sometimes also $\alpha = 1$
- **Numerical calculations:** Often $\hbar = c = 1$, but $\alpha \approx 1/137$
- **Experimental physics:** Almost always SI units (all constants have numerical values)

T0 convention:

- In T0 calculations: $c = \hbar = \alpha = G = 1$ (maximum simplification)
- Only parameter: $\xi = \frac{4}{3} \times 10^{-4}$ (integer structural choices are motivated settings; SI anchors such as m_e serve for conversion)
- When comparing with experiments: SI values ($c = 3 \times 10^8 \text{ m/s}$, $\alpha \approx 1/137$, etc.)
- Both describe the same physics.

.5 Reconstruction of SI Values from T0

The Central Principle

Basic idea: Although T0 sets all constants to 1, the SI values can be reconstructed.

T0 Reconstruction

In T0 calculations:

- All constants = 1: $c = \hbar = \alpha = G = 1$
- Only parameter: $\xi = \frac{4}{3} \times 10^{-4}$ (plus structural choices as settings)
- Formulas maximally simplified

Reconstruction of SI values:

- Fine-structure constant: $\alpha_{\text{SI}} = \xi(E_0/1\text{MeV})^2 \approx 1/137$
- Gravitational constant: $G_{\text{SI}} = \frac{\xi^2}{4m_e} \times \text{factors}$
- Further constants: reconstructable from ξ and energy scales (see Doc. 011 and 012)

Example: Fine-Structure Constant

In T0 units:

$$\alpha = 1 \quad (13)$$

Reconstruction of SI value:

$$\alpha_{\text{SI}} = \xi \cdot \left(\frac{E_0}{1\text{MeV}} \right)^2 \quad (14)$$

With $\xi = \frac{4}{3} \times 10^{-4}$ and $E_0 = 7.398 \text{ MeV}$:

$$\alpha_{\text{SI}} = 1.3333 \times 10^{-4} \times (7.398)^2 \quad (15)$$

$$= 1.3333 \times 10^{-4} \times 54.73 \quad (16)$$

$$= 7.297 \times 10^{-3} \quad (17)$$

$$= \frac{1}{137.04} \quad (18)$$

Experimental: $\alpha_{\text{exp}} = \frac{1}{137.036}$

Deviation from the experimental value: 0.0005 %

(Corrected on 30 Sept. 2026: previously 0.03 % – $1/(1.3333 \times 10^{-4} \times 54.730) = 137.035$ against 137.036 is 0.0005 %; even the rounded value 137.04 deviates by only 0.003 %.)

Example: Gravitational Constant

In T0 units:

$$G = 1 \quad (19)$$

Reconstruction of SI value:

$$G_{\text{SI}} = \frac{\xi^2}{4m_e} \times C_{\text{conv}} \times K_{\text{frak}} \quad (20)$$

(Corrected on 30 Sept. 2026: previously $\frac{\xi^2}{4m_e} \times C_{\text{dim}} \times C_{\text{conv}} - C_{\text{dim}} = 1/E_{\text{char}} = 3.472 \times 10^{-2}$ is cancelled again by the factor $E_{\text{char}} = 28.8$ in the step chain of Doc. 012; in the formula alone the product would give 2.35×10^{-12} instead of 6.674×10^{-11} .)

where:

- C_{dim} = Dimension conversion (natural units $\rightarrow$ SI)
 - C_{conv} = Conversion factors (eV $\rightarrow$ J, etc.)
- Detailed derivation see Document 012 (Gravitation).

Why does this work?

Key: ξ is dimensionless and is taken as universal in the T0 framework.

1. In T0: ξ determines all coupling strengths
2. In SI: ξ together with characteristic energies (E_0 , masses) reconstructs all constants
3. Physical predictions: identical in both systems
4. Only the mathematical representation differs

Comparison Table

Constant	T0	SI	Reconstruction
c	1	3×10^8 m/s	Convention
$\hbar$	1	1.055×10^{-34} J·s	Convention
α	1	$\approx 1/137$	$\xi(E_0/1\text{MeV})^2$
G	1	6.67×10^{-11} m ³ /(kg·s ²)	$\xi^2/(4m_e) \times \text{factors}$
ξ	$\frac{4}{3} \times 10^{-4}$	$\frac{4}{3} \times 10^{-4}$	same

Table 2: T0 vs. SI - Reconstruction of constants

Important Conclusion

- **T0 is not new physics**, but a reparametrization
- Instead of many constants (c , $\hbar$, α , G , ...) only **one parameter** ξ
- All SI values reconstructable from ξ and energy scales
- Advantage: Formulas simpler, physical relationships clearer
- Disadvantage: Conversion to SI needed for experiments

.6 Why can $\alpha = 1$ be set?

Fundamental Insight

Core Statement

The fine-structure constant α is a **dimensionless number**. Its numerical value is **convention-dependent**, not fundamental.
One can set $\alpha = 1$ by redefining the **unit of charge** accordingly.

Step-by-Step Justification

Step 1: What is a convention?

SI units are historically evolved definitions:

- 1 meter = originally 1/10,000,000 of the Earth's meridian
- 1 second = originally 1/86,400 of a solar day
- 1 Coulomb = defined via Ampere and force between currents

None of these is "fundamental".

Step 2: α in SI

In SI units:

$$\alpha = \frac{e^2}{4\pi\epsilon_0\hbar c} \approx \frac{1}{137} \quad (21)$$

The value $1/137$ follows from:

- How we defined the Coulomb (historically)
- How we defined ϵ_0 (via μ_0 and c)

Step 3: Redefinition

We can say: "From now on, the elementary charge is no longer 1.602×10^{-19} C, but $e = \sqrt{4\pi\epsilon_0\hbar c}$."

Then automatically:

$$\alpha = \frac{(\sqrt{4\pi\epsilon_0\hbar c})^2}{4\pi\epsilon_0\hbar c} = 1 \quad (22)$$

Step 4: Physical Consequences

- **No physical prediction changes.**
- Only the *numbers* in formulas change
- All ratios remain the same
- All experiments yield the same results

Analogy: Temperature Scales

Celsius: Water freezes at 0°C

Fahrenheit: Water freezes at 32°F

Kelvin: Water freezes at 273.15 K

None of these scales is more "correct" than the others; they are conventions.

Similarly, $\alpha = 1/137$ (SI) vs. $\alpha = 1$ (HL) is a choice of convention.

.7 Consequences of Redefining the Coulomb

What does it mean to redefine elementary charge?

If e is redefined such that $\alpha = 1$:

Old definition (SI):

$$e = 1.602 \times 10^{-19} \text{ C} \quad (23)$$

New definition (HL with $\alpha = 1$):

$$e = \sqrt{4\pi} \approx 3.545 \quad (\text{dimensionless in natural units}) \quad (24)$$

or expressed in SI units:

$$e_{\text{new}} = \sqrt{4\pi\epsilon_0\hbar c} \approx 1.877 \times 10^{-18} \text{ C} = \sqrt{137.036} e \quad (25)$$

The charge unit is rescaled by the same factor: $1 \text{ C}_{\text{new}} = (e_{\text{new}}/e) \cdot 1 \text{ C} = \sqrt{137} \times 1 \text{ C}_{\text{old}}$. Numerical values transform inversely to the units: a unit larger by a factor f gives a numerical value smaller by f .

(Note of 2 Oct. 2026 on notation: here f is the scaling factor between the old and the new unit, not a frequency and not the base winding number $f = 1/\xi$. Cf. Doc. 190, R147.)

(Corrected on 30 Sept. 2026: previously $e = 1$ and $e_{\text{new}} \approx 5.29 \times 10^{-19}$ as well as $1 \text{ A}_{\text{new}} = e_{\text{new}}/1 \text{ s}$ – in HL, $\alpha = e^2/(4\pi) = 1$ gives $e = \sqrt{4\pi}$; $\sqrt{4\pi\epsilon_0\hbar c} = 1.877 \times 10^{-18} \text{ C}$. The factors $\sqrt{137}$, $1/\sqrt{137}$, 137 apply to the rescaled unit C_{new} , not to the elementary charge e_{new} itself.)

Effects on Electromagnetic Quantities

Electric Current (Ampere)

Since $1 \text{ A} = 1 \text{ C/s}$:

$$1 \text{ A}_{\text{new}} = \frac{1 \text{ C}_{\text{new}}}{1 \text{ s}} = \sqrt{137} \times 1 \text{ A}_{\text{old}} \quad (26)$$

Electric Voltage (Volt)

$1 \text{ V} = 1 \text{ J/C}$:

$$1 \text{ V}_{\text{new}} = \frac{1 \text{ J}}{1 \text{ C}_{\text{new}}} = \frac{1}{\sqrt{137}} \times 1 \text{ V}_{\text{old}} \quad (27)$$

Capacitance (Farad)

$$1 \text{ F}_{\text{new}} = \frac{1 \text{ C}_{\text{new}}}{1 \text{ V}_{\text{new}}} = 137 \times 1 \text{ F}_{\text{old}} \quad (28)$$

Are these changes "real"?

No. They are conversion factors, like Celsius $\rightarrow$ Fahrenheit.

All physical ratios remain identical:

- Capacitance of a capacitor / distance: same
- Force between charges / distance²: same
- All experiments: same results

Only the *numerical values* we calculate with change.

.8 Practical Impacts on Everyday Calculations

Motivation

Question: If we set $\alpha = 1$, what does that mean for ordinary electrical calculations with volts, amperes, resistance, capacitance?

Answer: All formulas change, but the *physical results* remain identical.

Example 1: Ohm's Law

In SI Units (Standard)

$$U = R \cdot I \quad (29)$$

Numerical example:

- Resistance: $R = 100 \, \Omega$
- Current: $I = 2 \text{ A}$
- Voltage: $U = 100 \times 2 = 200 \text{ V}$

In Heaviside-Lorentz with $\alpha = 1$

The formula remains $U = R \cdot I$, but the *numerical values* change.

Unit conversion:

$$1 \text{ A}_{\text{new}} = \sqrt{137} \times 1 \text{ A}_{\text{old}} \approx 11.7 \text{ A}_{\text{old}} \quad (30)$$

$$1 \text{ V}_{\text{new}} = \frac{1}{\sqrt{137}} \times 1 \text{ V}_{\text{old}} \approx 0.085 \text{ V}_{\text{old}} \quad (31)$$

$$1 \text{ } \Omega_{\text{new}} = \frac{1}{137} \times 1 \text{ } \Omega_{\text{old}} \quad (32)$$

Same circuit in new units:

$$R_{\text{new}} = 100 \times 137 = 13\,700 \text{ } \Omega_{\text{new}} \quad (33)$$

$$I_{\text{new}} = \frac{2}{\sqrt{137}} \approx 0.171 \text{ A}_{\text{new}} \quad (34)$$

$$U_{\text{new}} = 13\,700 \times 0.171 = 2341 \text{ V}_{\text{new}} \quad (35)$$

Conversion back to SI:

$$U = 2341 \times 0.0854 \text{ V}_{\text{old}} = 200 \text{ V} \quad \checkmark \quad (36)$$

The result is identical.

(Corrected on 30 Sept. 2026: previously $R_{\text{new}} = 100/137 = 0.73$, $I_{\text{new}} = 2\sqrt{137} = 23.4$, $U_{\text{new}} = 17.1$ and back-conversion $17.1 \times 0.085 = 200 \text{ V}$ – the numerical values were converted opposite to the units defined above ($1 \text{ } \Omega_{\text{new}} = \Omega_{\text{old}}/137$ means $100 \text{ } \Omega_{\text{old}} = 13\,700 \text{ } \Omega_{\text{new}}$), and 17.1×0.085 gives 1.45, not 200. Likewise in Examples 2–4.)

Example 2: Power of a Light Bulb**In SI Units**

$$P = U \cdot I = \frac{U^2}{R} \quad (37)$$

Light bulb: 60 W at 230 V

$$R = \frac{U^2}{P} = \frac{(230)^2}{60} = 882 \text{ } \Omega \quad (38)$$

$$I = \frac{P}{U} = \frac{60}{230} = 0.26 \text{ A} \quad (39)$$

In Heaviside-Lorentz with $\alpha = 1$

Power: $1 \text{ W}_{\text{new}} = 1 \text{ W}_{\text{old}}$ (energy/time does not change in HL)

$$U_{\text{new}} = 230 \times \sqrt{137} = 2692 \text{ V}_{\text{new}} \quad (40)$$

$$R_{\text{new}} = 882 \times 137 = 1.21 \times 10^5 \text{ } \Omega_{\text{new}} \quad (41)$$

$$I_{\text{new}} = \frac{P}{U_{\text{new}}} = \frac{60}{2692} = 0.0223 \text{ A}_{\text{new}} \quad (42)$$

Verification:

$$P = U_{\text{new}} \cdot I_{\text{new}} = 2692 \times 0.0223 = 60 \text{ W} \quad \checkmark \quad (43)$$

(Corrected on 30 Sept. 2026: previously $U_{\text{new}} = 230/\sqrt{137} = 19.6$, $R_{\text{new}} = 882/137 = 6.44$, $I_{\text{new}} = 3.06$ – conversion in the direction of the defined units, see Example 1.)

Example 3: Charging a Capacitor

In SI Units

$$Q = C \cdot U \quad (44)$$

Capacitor: $C = 100 \mu\text{F}$ at $U = 12 \text{ V}$

$$Q = 100 \times 10^{-6} \times 12 = 1.2 \times 10^{-3} \text{ C} \quad (45)$$

Stored energy:

$$E = \frac{1}{2}CU^2 = \frac{1}{2} \times 100 \times 10^{-6} \times 144 = 7.2 \times 10^{-3} \text{ J} \quad (46)$$

In Heaviside-Lorentz with $\alpha = 1$

Conversion:

$$1 \text{ F}_{\text{new}} = 137 \times 1 \text{ F}_{\text{old}} \quad (47)$$

$$1 \text{ C}_{\text{new}} = \sqrt{137} \times 1 \text{ C}_{\text{old}} \quad (48)$$

$$C_{\text{new}} = \frac{100 \times 10^{-6}}{137} = 7.30 \times 10^{-7} \text{ F}_{\text{new}} \quad (49)$$

$$U_{\text{new}} = 12 \times \sqrt{137} = 140.5 \text{ V}_{\text{new}} \quad (50)$$

$$Q_{\text{new}} = 7.30 \times 10^{-7} \times 140.5 = 1.025 \times 10^{-4} \text{ C}_{\text{new}} \quad (51)$$

Conversion back:

$$Q = 1.025 \times 10^{-4} \times \sqrt{137} = 1.2 \times 10^{-3} \text{ C}_{\text{old}} \quad \checkmark \quad (52)$$

Energy:

$$E_{\text{new}} = \frac{1}{2} \times 7.30 \times 10^{-7} \times (140.5)^2 = 7.2 \times 10^{-3} \text{ J} \quad \checkmark \quad (53)$$

The energy is the same in all systems.

(Corrected on 30 Sept. 2026: previously $C_{\text{new}} = 0.0137$, $U_{\text{new}} = 1.025$, $Q_{\text{new}} = 0.014$ and back-conversion with $1/\sqrt{137}$ – conversion in the direction of the defined units, see Example 1.)

Example 4: RC Time Constant

In SI Units

$$\tau = R \cdot C \quad (54)$$

Circuit: $R = 1 \text{ k}\Omega$, $C = 10 \mu\text{F}$

$$\tau = 1000 \times 10 \times 10^{-6} = 0.01 \text{ s} = 10 \text{ ms} \quad (55)$$

In Heaviside-Lorentz with $\alpha = 1$

$$R_{\text{new}} = 1000 \times 137 = 1.37 \times 10^5 \Omega_{\text{new}} \quad (56)$$

$$C_{\text{new}} = \frac{10 \times 10^{-6}}{137} = 7.30 \times 10^{-8} \text{ F}_{\text{new}} \quad (57)$$

$$\tau_{\text{new}} = 1.37 \times 10^5 \times 7.30 \times 10^{-8} = 0.01 \text{ s} = 10 \text{ ms} \quad \checkmark \quad (58)$$

(Corrected on 30 Sept. 2026: previously $R_{\text{new}} = 1000/137 = 7.3$ and $C_{\text{new}} = 137 \times 10^{-5} = 1.37 \times 10^{-3}$ – conversion in the direction of the defined units, see Example 1; τ is unchanged.)

Time remains the same: physical timescales do not change.

Summary of Practical Calculations

Quantity	SI	HL Factor	HL ($\alpha = 1$)
Charge (Q)	C	$\sqrt{137}$	$\sqrt{137} \text{ C}$
Current (I)	A	$\sqrt{137}$	$\sqrt{137} \text{ A}$
Voltage (U)	V	$1/\sqrt{137}$	$\text{V}/\sqrt{137}$
Resistance (R)	Ω	$1/137$	$\Omega/137$
Capacitance (C)	F	137	137 F
Power (P)	W	1	W (unchanged)
Energy (E)	J	1	J (unchanged)
Time (τ)	s	1	s (unchanged)

Table 3: Conversion factors SI $\rightarrow$ HL with $\alpha = 1$ (factors for the units; numerical values are divided by the factor)

Important Insights**Core Statement****What changes:**

- Numerical values for charge, current, voltage, resistance, capacitance

What does NOT change:

- Energy
- Power
- Time
- All physical ratios
- All experimental results

Conclusion: It is a conversion, comparable to meters $\leftrightarrow$ feet.

Why does nobody use $\alpha = 1$ in practice?**Reasons:**

1. **Measuring devices:** All voltmeters, ammeters, etc. are calibrated in SI
2. **Standards:** Worldwide accepted SI definitions

3. **Intuition:** Engineers know typical values in SI

- Household: 230 V, not $2692 V_{\text{new}}$
- USB: 5 V, not $58.5 V_{\text{new}}$

(Corrected on 30 Sept. 2026: previously 1.96 and $0.43 V_{\text{new}}$ – even in the old direction $230/\sqrt{137} = 19.65$; in the direction corrected above, $230 \times \sqrt{137} = 2692$ and $5 \times \sqrt{137} = 58.5 V_{\text{new}}$.)

4. **Conversion is laborious:** $\sqrt{137}$ factors everywhere

5. **No advantage for practitioners:** Simplification only visible in theoretical formulas

But: In theoretical calculations (QED, Feynman diagrams), $\alpha = 1$ can be helpful.

.9 Practical Aspects of Different Systems

Advantages and Disadvantages: SI Units

Advantages:

- Worldwide standardized
- Directly usable for experiments
- All measuring devices calibrated in SI
- Clear separation of length/time/mass/charge

Disadvantages:

- Many constants in formulas ($4\pi\epsilon_0, \hbar, c$)
- Physical relationships obscured
- Dimensions unwieldy

Advantages and Disadvantages: Heaviside-Lorentz with $\alpha = 1$

Advantages:

- Maximally simplified formulas
- Electromagnetic symmetry visible
- Theoretical calculations simpler
- QED Feynman diagrams easier to read

Disadvantages:

- No direct connection to experiments
- Conversion to SI laborious
- Unfamiliar for practitioners
- Physical "size" of e unclear

Advantages and Disadvantages: Natural Units with $\alpha \approx 1/137$

Advantages:

- Simplified formulas ($\hbar = c = 1$)
- α retains physical meaning
- Good compromise theory/practice
- Numerically: $\alpha \ll 1 \rightarrow$ perturbation theory

Disadvantages:

- Still need conversion to SI
- Factor 4π remains in some formulas
This is the usual convention in present-day particle physics.

.10 Historical Development

Gauss Units (cgs)**19th century:** Gauss system (centimeter-gram-second)

$$\alpha = \frac{e^2}{\hbar c} \quad (59)$$

No $4\pi\epsilon_0$, because $4\pi\epsilon_0 = 1$ by definition in cgs. (Corrected on 30 Sept. 2026: previously $\epsilon_0 = 1$ – with $\epsilon_0 = 1$ one would get $\alpha = e^2/(4\pi\hbar c)$; only $4\pi\epsilon_0 = 1$ gives $\alpha = e^2/(\hbar c)$.)

SI Units (MKSA)**20th century:** SI system (meter-kilogram-second-ampere)

$$\alpha = \frac{e^2}{4\pi\epsilon_0\hbar c} \quad (60)$$

The $4\pi\epsilon_0$ appears because the SI ampere is defined via force.

Heaviside-Lorentz**Theoretical physics:** Heaviside-Lorentz simplifies Maxwell's equations

$$\nabla \times \vec{E} = -\frac{\partial \vec{B}}{\partial t}, \quad \nabla \times \vec{B} = \vec{j} + \frac{\partial \vec{E}}{\partial t} \quad (61)$$

The equations are symmetric (in SI, μ_0 and ϵ_0 appear asymmetrically)

Natural Units**Modern high-energy physics:** $\hbar = c = 1$, but different conventions for α

.11 Fine's Inequality vs. Fine-Structure Constant

Frequent Confusion**Note:** *Fine's inequality* and the *fine-structure constant* are different concepts.**Fine's Inequality****What it is:**

- A form of Bell's inequality
- Test for local hidden variables
- Quantum entanglement vs. classical correlations

Mathematically:

$$|C(\alpha, \beta) - C(\alpha, \beta')| + |C(\alpha', \beta) + C(\alpha', \beta')| \leq 2 \quad (62)$$

where C are correlation functions.

Physically: Shows non-locality of quantum mechanics

Fine-Structure Constant**What it is:**

- Fundamental physical constant
- Strength of the electromagnetic interaction
- Dimensionless, $\alpha \approx 1/137$

Mathematically:

$$\alpha = \frac{e^2}{4\pi\epsilon_0\hbar c} \quad (63)$$

Physically: Determines EM coupling strength

No Conceptual Connection

The similarity in name is coincidental; the two concepts are not related.

.12 Summary**Core Statements**

1. α is dimensionless $\rightarrow$ numerical value is convention-dependent
2. One **can** set $\alpha = 1$ by redefining the unit of charge
3. **T0 theory:** Sets all constants = 1: $c = \hbar = \alpha = G = 1$
4. Only parameter in T0: $\xi = \frac{4}{3} \times 10^{-4}$ (integer structural choices are settings, SI anchors serve for conversion)
5. **No** physical prediction changes
6. Only numerical values in formulas differ
7. When comparing with experiments: SI values ($\alpha \approx 1/137$, $c = 3 \times 10^8$ m/s, etc.)

For Further Details See Document 011

- T0 derivation of α
- Characteristic energy E_0
- Geometric parameter ξ
- Experimental verification
- Detailed dimensional analysis
- Historical context (Sommerfeld)

Quantity	SI	HL ($\alpha = 1$)
Elementary charge	$e = 1.602 \times 10^{-19} \text{ C}$	$e = \sqrt{4\pi} \approx 3.545$
Fine-structure constant	$\alpha \approx 1/137$	$\alpha = 1$
ϵ_0	$8.854 \times 10^{-12} \text{ F/m}$	1
$\hbar$	$1.055 \times 10^{-34} \text{ J}\cdot\text{s}$	1
c	$3 \times 10^8 \text{ m/s}$	1

Table 4: Conversion table SI to HL

0.1 Conversion Table: SI $\leftrightarrow$ Heaviside-Lorentz

(Corrected on 30 Sept. 2026: previously $e = 1$ and $4\pi\epsilon_0 = 1$ in the HL column – Heaviside-Lorentz sets $\epsilon_0 = 1$, so $e = \sqrt{4\pi}$ at $\alpha = 1$.)

0.2 Sample Calculation: Coulomb's Law

In SI Units

$$F = \frac{1}{4\pi\epsilon_0} \frac{e^2}{r^2} \quad (64)$$

Numerically for $r = 1 \text{ \AA} = 10^{-10} \text{ m}$:

$$F = \frac{1}{4\pi \times 8.854 \times 10^{-12}} \frac{(1.602 \times 10^{-19})^2}{(10^{-10})^2} \quad (65)$$

$$\approx 2.3 \times 10^{-8} \text{ N} \quad (66)$$

In HL Units ($\hbar = c = \epsilon_0 = 1$)

$$F = \frac{e^2}{4\pi r^2} = \frac{\alpha}{r^2} \quad (67)$$

With r in natural units: $r = 1 \text{ \AA} = 5.07 \times 10^{-4} \text{ eV}^{-1}$ (with $\hbar c = 1.973 \times 10^{-7} \text{ eV m}$)

$$F = \frac{\alpha}{(5.07 \times 10^{-4})^2} = \frac{3.89 \times 10^6}{137.036} \approx 2.84 \times 10^4 \text{ eV}^2 \quad (68)$$

Conversion to SI: $1 \text{ eV}^2 = (1 \text{ eV})^2 / (\hbar c) \approx 8.12 \times 10^{-13} \text{ N}$

$$F \approx 2.3 \times 10^{-8} \text{ N} \quad (69)$$

The result is identical; only the intermediate steps look different.

(Corrected on 30 Sept. 2026: previously $F = e^2/r^2 = 1/r^2$, $r = 0.197 \times 10^6 \text{ eV}^{-1}$, $F \approx 2.6 \times 10^{-14} \text{ eV}^2$ and $1 \text{ eV}^2 \approx 9 \times 10^5 \text{ N}$ – $r = 10^{-10} \text{ m} / (1.973 \times 10^{-7} \text{ eV m}) = 5.07 \times 10^{-4} \text{ eV}^{-1}$, $1 \text{ eV}^2 = (1.602 \times 10^{-19} \text{ J})^2 / (3.16 \times 10^{-26} \text{ J m}) = 8.12 \times 10^{-13} \text{ N}$. The SI result $2.3 \times 10^{-8} \text{ N}$ follows only with the numerical value $\alpha = 1/137.036$ in the numerator; with $\alpha = 1$ one would get $3.2 \times 10^{-6} \text{ N}$. The force depends on the physical value of α , not on the choice of charge unit.)