

Final ASA Config Script

```
hostname ASA-01
interface GigabitEthernet1/1
  nameif outside
  security-level 0
  ip address 203.0.113.1 255.255.255.252
```

```
no shutdown
```

```
interface GigabitEthernet1/2
  no nameif
  no shutdown
```

```
interface GigabitEthernet1/2.10
  vlan 10
  nameif OT
  security-level 90
  ip address 10.50.10.1 255.255.255.0
  no shutdown
```

```
interface GigabitEthernet1/2.20
  vlan 20
  nameif IT
  security-level 70
  ip address 10.50.20.1 255.255.255.0
  no shutdown
```

```
interface GigabitEthernet1/2.30
  vlan 30
  nameif MGMT
  security-level 95
  ip address 10.50.30.1 255.255.255.0
  no shutdown
```

```
interface GigabitEthernet1/2.40
vlan 40
nameif DMZ
security-level 50
ip address 10.50.40.1 255.255.255.192
no shutdown
```

```
interface GigabitEthernet1/2.50
vlan 50
nameif GUEST
security-level 10
ip address 10.50.50.1 255.255.255.192
no shutdown
```

```
route outside 0.0.0.0 0.0.0.0 203.0.113.2
```

```
object network OBJ_OT_NET
subnet 10.50.10.0 255.255.255.0
object network OBJ_IT_NET
subnet 10.50.20.0 255.255.255.0
object network OBJ_MGMT_NET
subnet 10.50.30.0 255.255.255.0
object network OBJ_DMZ_NET
subnet 10.50.40.0 255.255.255.192
object network OBJ_GUEST_NET
subnet 10.50.50.0 255.255.255.192
```

```
object network OBJ_DC
host 10.50.20.3
object network OBJ_WEBSERVER
host 10.50.40.2
object network OBJ_SIEM
host 10.50.30.3
object network OBJ_PAT_IP
host 203.0.113.10
object network OBJ_WEBSERVER_PUBLIC
host 203.0.113.20
```

object-group service SVC_AD
 service-object tcp destination eq 53
 service-object udp destination eq 53
 service-object tcp destination eq 88
 service-object udp destination eq 88
 service-object tcp destination eq 389
 service-object udp destination eq 389
 service-object tcp destination eq 445
 service-object udp destination eq 123

object-group service SVC_WEB
 service-object tcp destination eq 443

object-group service SVC_SYSLOG
 service-object tcp destination eq 6514

object-group service SVC_ADMIN
 service-object tcp destination eq 22
 service-object tcp destination eq 3389

nat (OT,IT) source static OBJ_OT_NET OBJ_OT_NET destination static OBJ_IT_NET
OBJ_IT_NET
nat (OT,MGMT) source static OBJ_OT_NET OBJ_OT_NET destination static OBJ_MGMT_NET
OBJ_MGMT_NET
nat (IT,IT) source static OBJ_IT_NET OBJ_IT_NET destination static OBJ_IT_NET OBJ_IT_NET
nat (IT,MGMT) source static OBJ_IT_NET OBJ_IT_NET destination static OBJ_MGMT_NET
OBJ_MGMT_NET
nat (DMZ,MGMT) source static OBJ_DMZ_NET OBJ_DMZ_NET destination static
OBJ_MGMT_NET OBJ_MGMT_NET

nat (IT,outside) source dynamic OBJ_IT_NET OBJ_PAT_IP
nat (MGMT,outside) source dynamic OBJ_MGMT_NET OBJ_PAT_IP
nat (DMZ,outside) source dynamic OBJ_DMZ_NET OBJ_PAT_IP
nat (GUEST,outside) source dynamic OBJ_GUEST_NET OBJ_PAT_IP

nat (DMZ,outside) source static OBJ_WEBSERVER OBJ_WEBSERVER_PUBLIC

```
access-list ACL_OT_IN extended permit tcp 10.50.10.0 255.255.255.0 host 10.50.20.3 eq
53
access-list ACL_OT_IN extended permit udp 10.50.10.0 255.255.255.0 host 10.50.20.3 eq
53
access-list ACL_OT_IN extended permit tcp 10.50.10.0 255.255.255.0 host 10.50.20.3 eq
88
access-list ACL_OT_IN extended permit udp 10.50.10.0 255.255.255.0 host 10.50.20.3 eq
88
access-list ACL_OT_IN extended permit tcp 10.50.10.0 255.255.255.0 host 10.50.20.3 eq
389
access-list ACL_OT_IN extended permit udp 10.50.10.0 255.255.255.0 host 10.50.20.3 eq
389
access-list ACL_OT_IN extended permit tcp 10.50.10.0 255.255.255.0 host 10.50.20.3 eq
445
access-list ACL_OT_IN extended permit udp 10.50.10.0 255.255.255.0 host 10.50.20.3 eq
123
access-list ACL_OT_IN extended permit tcp 10.50.10.0 255.255.255.0 10.50.30.0
255.255.255.0 eq 6514
access-list ACL_OT_IN extended deny ip any any log
access-group ACL_OT_IN in interface OT
```

```
access-list ACL_IT_IN extended permit tcp 10.50.20.0 255.255.255.0 host 10.50.20.3 eq 53
access-list ACL_IT_IN extended permit udp 10.50.20.0 255.255.255.0 host 10.50.20.3 eq 53
access-list ACL_IT_IN extended permit tcp 10.50.20.0 255.255.255.0 host 10.50.20.3 eq 88
access-list ACL_IT_IN extended permit udp 10.50.20.0 255.255.255.0 host 10.50.20.3 eq 88
access-list ACL_IT_IN extended permit tcp 10.50.20.0 255.255.255.0 host 10.50.20.3 eq 389
access-list ACL_IT_IN extended permit udp 10.50.20.0 255.255.255.0 host 10.50.20.3 eq 389
access-list ACL_IT_IN extended permit tcp 10.50.20.0 255.255.255.0 host 10.50.20.3 eq 445
access-list ACL_IT_IN extended permit udp 10.50.20.0 255.255.255.0 host 10.50.20.3 eq 123
access-list ACL_IT_IN extended permit tcp 10.50.20.0 255.255.255.0 10.50.30.0
255.255.255.0 eq 6514
access-list ACL_IT_IN extended permit tcp 10.50.20.0 255.255.255.0 any eq 443
access-list ACL_IT_IN extended permit udp 10.50.20.0 255.255.255.0 any eq 53
access-list ACL_IT_IN extended deny ip any any log
access-group ACL_IT_IN in interface IT
```

```
access-list ACL_MGMT_IN extended permit tcp 10.50.30.0 255.255.255.0 10.50.10.0
255.255.255.0 eq 22
```

```
access-list ACL_MGMT_IN extended permit tcp 10.50.30.0 255.255.255.0 10.50.10.0
255.255.255.0 eq 3389
access-list ACL_MGMT_IN extended permit tcp 10.50.30.0 255.255.255.0 10.50.20.0
255.255.255.0 eq 22
access-list ACL_MGMT_IN extended permit tcp 10.50.30.0 255.255.255.0 10.50.20.0
255.255.255.0 eq 3389
access-list ACL_MGMT_IN extended permit tcp 10.50.30.0 255.255.255.0 host 10.50.40.10
eq 22
access-list ACL_MGMT_IN extended permit udp 10.50.30.0 255.255.255.0 host
10.50.40.10 eq 161
access-list ACL_MGMT_IN extended permit tcp 10.50.30.0 255.255.255.0 any eq 443
access-list ACL_MGMT_IN extended permit udp 10.50.30.0 255.255.255.0 any eq 53
access-list ACL_MGMT_IN extended deny ip any any log
access-group ACL_MGMT_IN in interface MGMT
```

```
access-list ACL_DMZ_IN extended permit tcp 10.50.40.0 255.255.255.192 10.50.30.0
255.255.255.0 eq 6514
access-list ACL_DMZ_IN extended deny ip any any log
access-group ACL_DMZ_IN in interface DMZ
```

```
access-list ACL_GUEST_IN extended permit udp any host 10.50.50.1 eq 67
access-list ACL_GUEST_IN extended permit tcp 10.50.50.0 255.255.255.192 any eq 443
access-list ACL_GUEST_IN extended deny ip any any log
access-group ACL_GUEST_IN in interface GUEST
```

```
access-list ACL_OUTSIDE_IN extended permit tcp any host 203.0.113.20 eq 443
access-list ACL_OUTSIDE_IN extended deny ip any any log
access-group ACL_OUTSIDE_IN in interface outside
```

```
banner motd ^
```

```
AUTHORIZED ACCESS ONLY. All activity is monitored and logged.
```

```
Unauthorized access is prohibited and will be prosecuted.
```

```
^
```

```
write memory
```