Partial Differential Equations in Finance

Your Name

May 22, 2025

Overview of Topics

- Charting theory and nature of boundary and initial conditions
- Explicit solutions, including original Black-Scholes formula
- Special problems arising when there are free boundaries

Key Questions in Financial PDEs

- Physical interpretation of the equations?
- ▶ Mathematical properties of the solution?
- Techniques for obtaining explicit solutions?

PDEs in finance:

- Fundamental equations (e.g., Black-Scholes)
- Linear vs. nonlinear problems

Considerations for PDEs in Finance

- 1. Does the equation make sense as a well-posed problem?
 - ► Appropriate boundary or initial/final conditions?
 - Nature of the mathematical problem?
 - Smooth or discontinuous solutions?
- 2. Can we develop analytical tools to solve the equation?
- 3. How should we solve the equation numerically if necessary?

First Order Linear PDE

Consider the equation:

$$\alpha(s,t)\frac{\partial u}{\partial s} + \beta(s,t)\frac{\partial u}{\partial t} = \gamma(s,t)u(t)$$

Linearity Property

If u_1, u_2 are solutions, then $c_1u_1 + c_2u_2$ is also a solution for constants c_1, c_2 .

Proof.

Substitute $u = c_1u_1 + c_2u_2$ into the PDE and use linearity of derivatives.

Constant Coefficient Case

When α, β are constants and $\gamma \equiv 0$:

$$\alpha_0 \frac{\partial u}{\partial s} + \beta_0 \frac{\partial u}{\partial t} = 0 \quad (4.2)$$

Define the vector $\vec{v} = (\alpha_0, \beta_0)$ with $\beta_0 \alpha_0 \neq 0$. The directional derivative:

$$\nabla_{\vec{v}} u = \langle \alpha_0, \beta_0 \rangle \cdot \langle \frac{\partial u}{\partial s}, \frac{\partial u}{\partial t} \rangle$$

Thus, (4.2)
$$\Leftrightarrow \nabla_{\vec{v}} u \equiv 0$$

Characteristic Coordinates

Introduce new coordinates:

$$\xi = \beta_0 s + \alpha_0 t, \quad \zeta = \beta_0 s - \alpha_0 t$$

The Jacobian determinant:

$$\begin{vmatrix} \beta_0 & \alpha_0 \\ \beta_0 & -\alpha_0 \end{vmatrix} = -2\alpha_0\beta_0 \neq 0$$

Computing $\frac{\partial u}{\partial \xi}$:

$$\frac{\partial u}{\partial \xi} = \beta_0 \frac{\partial u}{\partial s} + \alpha_0 \frac{\partial u}{\partial t} \equiv 0$$

Therefore, u depends only on ζ : $u = F(\zeta)$

Characteristics and Information Propagation

- $\xi = \beta_0 s \alpha_0 t$ is called a **characteristic**
- Characteristics represent directions in which information propagates
- Analogous to constants of integration in ODEs

Important Note

Without boundary conditions, the solution remains arbitrary (like the constant ${\it C}$ in ODEs)

General Second-Order Linear PDE

Consider the general form in two variables:

$$a(x,t)u_{xx}+2b(x,t)u_{xt}+c(x,t)u_{tt}+d(x,t)u_{x}+e(x,t)u_{t}+f(x,t)u=g(x,t)u_{xt}+g(x,t)u_{$$

where $a,b,c,d,e,f,g:\mathbb{R}\times\mathbb{R}\to\mathbb{R}$ are coefficient functions.

Principal Part

The highest-order terms form the principal part:

$$L_p(u) = au_{xx} + 2bu_{xt} + cu_{tt}$$

Classification of PDEs

Define the discriminant:

$$\Delta(L) = b^2 - ac : (x, t) \mapsto b(x, t)^2 - a(x, t)c(x, t)$$

The PDE is classified as:

- ▶ **Hyperbolic** if $\Delta(L) > 0$ (e.g., wave equation)
- ▶ **Parabolic** if $\Delta(L) = 0$ (e.g., heat equation)
- ▶ **Elliptic** if $\Delta(L)$ < 0 (e.g., Laplace equation)

Coordinate Transformations

Definition

A transformation $(\xi, \eta) = (\xi(x, t), \eta(x, t))$ is called a change of coordinates if the Jacobian is non-zero:

$$J := \xi_x \eta_t - \xi_t \eta_x \neq 0$$

Theorem

The type of a linear second-order PDE in two variables is invariant under a change of coordinates.

Proof of Invariance

Under transformation (ξ, η) , the principal part becomes:

$$Au_{\xi\xi} + 2Bu_{\xi\eta} + Cu_{\eta\eta}$$

where:

$$A = a\xi_x^2 + 2b\xi_x\xi_t + c\xi_t^2$$

$$B = a\xi_x\eta_x + b(\xi_x\eta_t + \xi_t\eta_x) + c\xi_t\eta_t$$

$$C = a\eta_x^2 + 2b\eta_x\eta_t + c\eta_t^2$$

The new discriminant satisfies:

$$\Delta_{new} = AC - B^2 = J^2(b^2 - ac) = J^2\Delta_{original}$$

Canonical Forms

- **Hyperbolic**: $u_{\xi\xi} u_{\eta\eta} = \text{lower order terms (wave equation)}$
- **Parabolic**: $u_{\xi\xi} = \text{lower order terms (heat equation)}$
- **Elliptic**: $u_{\xi\xi} + u_{\eta\eta} = \text{lower order terms (Laplace equation)}$

Examples

- Wave equation: $u_{tt} = c^2(u_{xx} + u_{yy})$
- ▶ Heat equation: $u_t = k(u_{xx} + u_{yy})$
- ► Laplace equation: $u_{xx} + u_{yy} = 0$

Simplification Through Coordinates

A proper linear change of coordinates can transform:

- Hyperbolic equations to $u_{\xi\eta}=0$
- ▶ Parabolic equations to $u_{\xi\xi} = 0$
- ▶ Elliptic equations to $u_{\xi\xi} + u_{\eta\eta} = 0$

Important Note

The classification determines:

- Nature of characteristics
- Appropriate boundary conditions
- Solution techniques