NAME I SYNOPSIS I DESCRIPTION I RETURN VALUE I ERRORS I CONFORMING TO I NOTES I BUGS I EXAMPLE I SEE ALSO I COLOPHON

Search online pages

SEND(2)

Linux Programmer's Manual

SEND(2)

NAME top

send, sendto, sendmsg - send a message on a socket

# SYNOPSIS

## DESCRIPTION top

The system calls **send()**, **sendto()**, and **sendmsg()** are used to transmit a message to another socket.

The **send**() call may be used only when the socket is in a *connected* state (so that the intended recipient is known). The only difference between **send**() and write(2) is the presence of *flags*. With a zero *flags* argument, **send**() is equivalent to write(2). Also, the following call

```
send(sockfd, buf, len, flags);
```

is equivalent to

```
sendto(sockfd, buf, len, flags, NULL, 0);
```

The argument sockfd is the file descriptor of the sending socket.

If sendto() is used on a connection-mode (SOCK\_STREAM, SOCK\_SEQPACKET) socket, the arguments <code>dest\_addr</code> and <code>addrlen</code> are ignored (and the error EISCONN may be returned when they are not NULL and 0), and the error ENOTCONN is returned when the socket was not actually connected. Otherwise, the address of the target is given by <code>dest\_addr</code> with <code>addrlen</code> specifying its size. For <code>sendmsg()</code>, the address of the target is given by <code>msg.msg\_name</code>, with <code>msg.msg\_namelen</code> specifying its size.

For **send**() and **sendto**(), the message is found in *buf* and has length *len*. For **sendmsg**(), the message is pointed to by the elements of the array *msg.msg\_iov*. The **sendmsg**() call also allows sending ancillary data (also known as control information).

If the message is too long to pass atomically through the underlying protocol, the error **EMSGSIZE** is returned, and the message is not transmitted.

No indication of failure to deliver is implicit in a **send()**. Locally detected errors are indicated by a return value of -1.

When the message does not fit into the send buffer of the socket, send() normally blocks, unless the socket has been placed in nonblocking I/O mode. In nonblocking mode it would fail with the error EAGAIN or EWOULDBLOCK in this case. The select(2) call may be used to determine when it is possible to send more data.

## The flags argument

The flags argument is the bitwise OR of zero or more of the following flags.

### MSG CONFIRM (since Linux 2.3.15)

Tell the link layer that forward progress happened: you got a successful reply from the other side. If the link layer doesn't get this it will regularly reprobe the neighbor (e.g., via a unicast ARP). Only valid on SOCK\_DGRAM and SOCK\_RAW sockets and currently implemented only for IPv4 and IPv6. See arp(7) for details.

## MSG DONTROUTE

Don't use a gateway to send out the packet, send to hosts only on directly connected networks. This is usually used only by diagnostic or routing programs. This is defined only for protocol families that route; packet sockets don't.

## MSG DONTWAIT (since Linux 2.2)

Enables nonblocking operation; if the operation would block, EAGAIN or EWOULDBLOCK is returned. This provides similar behavior to setting the O\_NONBLOCK flag (via the fcntl(2) F\_SETFL operation), but differs in that MSG\_DONTWAIT is a percall option, whereas O\_NONBLOCK is a setting on the open file description (see open(2)), which will affect all threads in the calling process and as well as other processes that hold file descriptors referring to the same open file description.

## MSG EOR (since Linux 2.2)

Terminates a record (when this notion is supported, as for sockets of type SOCK\_SEQPACKET).

# MSG\_MORE (since Linux 2.4.4)

The caller has more data to send. This flag is used with TCP sockets to obtain the same effect as the TCP CORK socket

option (see tcp(7)), with the difference that this flag can be set on a per-call basis.

Since Linux 2.6, this flag is also supported for UDP sockets, and informs the kernel to package all of the data sent in calls with this flag set into a single datagram which is transmitted only when a call is performed that does not specify this flag. (See also the UDP\_CORK socket option described in udp(7).)

## MSG\_NOSIGNAL (since Linux 2.2)

Don't generate a **SIGPIPE** signal if the peer on a streamoriented socket has closed the connection. The **EPIPE** error is still returned. This provides similar behavior to using sigaction(2) to ignore **SIGPIPE**, but, whereas **MSG\_NOSIGNAL** is a per-call feature, ignoring **SIGPIPE** sets a process attribute that affects all threads in the process.

## MSG\_OOB

Sends out-of-band data on sockets that support this notion (e.g., of type SOCK\_STREAM); the underlying protocol must also support out-of-band data.

### sendmsg()

The definition of the msghdr structure employed by sendmsg() is as follows:

```
struct msghdr {
                           /* optional address */
   void
             *msg name;
             msg_namelen; /* size of address */
   socklen t
   struct iovec *msg iov;
                           /* scatter/gather array */
            size t
   void
            msg controllen; /* ancillary data buffer len */
   size_t
                           /* flags (unused) */
   int
              msq flags;
};
```

The msg\_name field is used on an unconnected socket to specify the target address for a datagram. It points to a buffer containing the address; the msg\_namelen field should be set to the size of the address. For a connected socket, these fields should be specified as NULL and 0, respectively.

The msg\_iov and msg\_iovlen fields specify scatter-gather locations, as for writev(2).

You may send control information using the msg\_control and msg\_controllen members. The maximum control buffer length the kernel can process is limited per socket by the value in /proc/sys/net/core/optmem max; see socket(7).

The msg\_flags field is ignored.

## RETURN VALUE top

On success, these calls return the number of bytes sent. On error, -1 is returned, and *errno* is set appropriately.

## ERRORS top

These are some standard errors generated by the socket layer. Additional errors may be generated and returned from the underlying protocol modules; see their respective manual pages.

EACCES (For UNIX domain sockets, which are identified by pathname)
Write permission is denied on the destination socket file, or
search permission is denied for one of the directories the
path prefix. (See path\_resolution(7).)

(For UDP sockets) An attempt was made to send to a network/broadcast address as though it was a unicast address.

#### EAGAIN or EWOULDBLOCK

The socket is marked nonblocking and the requested operation would block. POSIX.1-2001 allows either error to be returned for this case, and does not require these constants to have the same value, so a portable application should check for both possibilities.

EAGAIN (Internet domain datagram sockets) The socket referred to by sockfd had not previously been bound to an address and, upon attempting to bind it to an ephemeral port, it was determined that all port numbers in the ephemeral port range are currently in use. See the discussion of /proc/sys/net/ipv4/ip local port range in ip(7).

EBADF sockfd is not a valid open file descriptor.

#### **ECONNRESET**

Connection reset by peer.

## **EDESTADDRREQ**

The socket is not connection-mode, and no peer address is set.

EFAULT An invalid user space address was specified for an argument.

**EINTR** A signal occurred before any data was transmitted; see signal(7).

**EINVAL** Invalid argument passed.

#### **EISCONN**

The connection-mode socket was connected already but a recipient was specified. (Now either this error is returned, or the recipient specification is ignored.)

#### **EMSGSIZE**

The socket type requires that message be sent atomically, and the size of the message to be sent made this impossible.

#### **ENOBUFS**

The output queue for a network interface was full. This generally indicates that the interface has stopped sending, but may be caused by transient congestion. (Normally, this does not occur in Linux. Packets are just silently dropped when a device queue overflows.)

**ENOMEM** No memory available.

#### **ENOTCONN**

The socket is not connected, and no target has been given.

#### **ENOTSOCK**

The file descriptor sockfd does not refer to a socket.

#### **EOPNOTSUPP**

Some bit in the *flags* argument is inappropriate for the socket type.

EPIPE The local end has been shut down on a connection oriented socket. In this case, the process will also receive a SIGPIPE unless MSG NOSIGNAL is set.

## CONFORMING TO top

4.4BSD, SVr4, POSIX.1-2001. These interfaces first appeared in 4.2BSD.

POSIX.1-2001 describes only the MSG\_OOB and MSG\_EOR flags. POSIX.1-2008 adds a specification of MSG\_NOSIGNAL. The MSG\_CONFIRM flag is a Linux extension.

## NOTES top

According to POSIX.1-2001, the *msg\_controllen* field of the *msghdr* structure should be typed as *socklen\_t*, but glibc currently types it as *size t*.

See sendmmsg(2) for information about a Linux-specific system call
that can be used to transmit multiple datagrams in a single call.

## BUGS top

Linux may return EPIPE instead of ENOTCONN.

## EXAMPLE top

An example of the use of **sendto**() is shown in getaddrinfo(3).

## SEE ALSO top

```
fcntl(2), getsockopt(2), recv(2), select(2), sendfile(2),
sendmmsg(2), shutdown(2), socket(2), write(2), cmsg(3), ip(7),
socket(7), tcp(7), udp(7)
```

## COLOPHON top

This page is part of release 4.08 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

Linux 2016-03-15 SEND(2)

## Copyright and license for this manual page

HTML rendering created 2016-10-08 by Michael Kerrisk, author of *The Linux Programming Interface*, maintainer of the Linux *man-pages* project.

For details of in-depth **Linux/UNIX system programming training courses** that I teach, look here.

Hosting by jambit GmbH.



