How-To Library

Informatica

Split an Informatica domain before you migrate to Cloud Data Integration for PowerCenter (CDI-PC)

© Copyright Informatica LLC 2023. Informatica and the Informatica logo are trademarks or registered trademarks of Informatica LLC in the United States and many jurisdictions throughout the world. A current list of Informatica trademarks is available on the web at https://www.informatica.com/trademarks.html.

Abstract

You can migrate an Informatica domain with PowerCenter services to Cloud Data Integration for PowerCenter (CDI-PC). This article describes how to split an Informatica domain that contains PowerCenter services and other services to ensure that you can migrate the domain to CDI-PC.

Supported Versions

- Cloud Data Integration for PowerCenter .

Table of Contents

Overview. . . . 2
Before you begin. . . . 3
Verify system and database requirements. . . . 3
Plan port numbers. . . . 3
Copy the odbc.ini file. . . . 5
Start the domain. . . . 5
Enable the services in the domain. . . . 5
Back up repository services. . . . 5
Optional. Export domain objects. . . . 6
Disable domain services. . . . 8
Shut down the domain. . . . 8
Back up the domain. . . . 9
Split the domain. . . . 11
Copy the Informatica installation directory. . . . 12
Configure environment variables. . . . 12
Copy the domain backup file to the target location. . . . 13
Copy node configuration files from the source domain to the target domain. . . . 13
Restore the domain on the target location. . . . 13
Define the domain details. . . . 16
Start the target domain. . . . 21
Update service details. . . . 21
Restore the repository service backups. . . . 25
Delete services from the source domain. . . . 27
Enable services in both domains. . . . 27

Overview

You can migrate Informatica domain versions 10.4.0 through 10.5.3 to CDI-PC.

The domain must include PowerCenter services that are supported for migration. If your domain includes services such as a Model Repository Service, Data Integration Service, Content Management Service, or other services, you can

split the domain to create an Informatica domain that you can migrate to CDI-PC. The split creates a copy of your domain where you can continue to use the services that you don't migrate.

You can migrate an Informatica domain with the following services:

- PowerCenter Integration Service
- PowerCenter Repository Service
- Web Services Hub
- PowerCenter Listener Service
- PowerCenter Logger Service
- SAP BW Service

Split your Informatica domain if the domain contains any other services.

This document describes how to split a source domain such that you create a copy of the domain with all services that the source domain includes. You then remove services that you can't migrate from the source domain to ensure that the domain is ready to migrate.

The document uses the following terms to refer to domains:

- Source domain. The Informatica domain that you want to migrate.
- Target domain. The copy of the source domain that you create.

In this document, we create the target domain on the same host.

Before you begin

Before you split the domain, you need to perform tasks such as verifying system requirements, resolving possible port conflicts, and preparing databases for the target domain. You also need to back up the domain and repository services that you want to migrate.

Verify system and database requirements

You can use one host machine for both the domains. Verify that the host machine meets twice the number of resources required for processor, memory, disk space, and database space.

For example, if you require 2 CPUs with multiple cores, 12 GB RAM, and 20 GB of disk space for a node, you will require at least 4 CPUs with multiple cores, 24 GB RAM, and 40 GB of disk space for both nodes a single host machine.

For more information about system requirements, see the *Informatica Installation and Configuration Guide* and the Product Availability Matrix on Informatica Network: https://network.informatica.com/community/informatica-network/product-availability-matrices.

The domain configuration repository must point to a different database on the target domain. If you plan to keep the PowerCenter services on the target domain, the PowerCenter repository services must point to different databases than the source domain. Prepare and plan for the additional databases that you might need.

Plan port numbers

When you split the domain, you need to ensure that no port conflicts occur. Port conflicts can occur between application services and between different Informatica nodes.

When you run infasetup to update the gateway and worker nodes, you need to update static port numbers to avoid port conflicts. After you split the domain, you configure application service properties to assign unique port numbers to the static ports.

Before you split the domain, you need to identify values of static ports used in the source domain, and identify available ports to assign in the target domain.

Use the following guidelines to determine the port numbers:

- The port number that you specify for the domain and for each component in the domain must be unique.
- The port number for the domain and domain components cannot be within the range of the port numbers that you specify for the application service processes.
- The highest number in the range of port numbers that you specify for the application service processes must be at least three numbers higher than the lowest port number. For example, if the minimum port number in the range is 6400, the maximum port number must be at least 6403.
- The port numbers that you specify cannot be lower than 1025 or higher than 65535.

Use the following table as a template to record existing static port numbers and the port numbers that you will use to update service properties:

Service Name	Ports Property	Source Domain Port	Target Domain Port
Analyst Service	Note the port values on the Processes tab: - HTTP Port - HTTPS Port		
Content Management Service	Note the port values on the Processes tab: - HTTP Port - HTTPS Port		
Data Integration Service	Note the port values on the Processes tab: - HTTP Port - HTTPS Port		
Search Service	Note the port value on the Properties tab: - Port Number		
Scheduler Service	Note the port values on the Processes tab: - HTTP Port - HTTPS Port		

Use the following table as a template to record the existing static port numbers and the port numbers that you will use when you define nodes:

Domain Port	Source Domain Port	Target Domain Port
Node port		
Service Manager port		
Service Manager shutdown port		
Informatica Administrator port		
Informatica Administrator shutdown port		
Minimum port for service processes		
Maximum port for service processes		

Copy the odbc.ini file

Each domain requires a separate odbc.ini file.

Copy the existing odbc.ini file and update it as needed. When you split the domain, you set up environment variables to access the file.

Start the domain

Ensure that the Informatica domain is available before you back up the repositories.

If the domain is not started, run infaservice.sh to start the Informatica daemon. By default, infaservice.sh is installed in the following directory: `<Informatica installation directory>/tomcat/bin`

1. Go to the directory where infaservice.sh is located.
2. At the command prompt, enter the following command to start the daemon: `infaservice.sh startup`

Enable the services in the domain

The repository services must be running when you create a backup of the repository content.

To enable the PowerCenter Repository Service, select the service in the Administrator tool. If the service is in disabled state, on the **Manage** tab **Actions** menu, click **Enable the Service**.

Back up repository services

Back up the PowerCenter Repository services that you want to migrate to CDI-PC. Run the pmrep BackUp command to back up the repository. You can also back up the service from the Administrator tool.

The BackUp command backs up the repository to the file specified with the -o option. You must provide the backup file name. Use this command when the repository is running. You must be connected to a repository to use this command.

The BackUp command uses the following syntax:

```
backup
-o <output_file_name>
[-d <description>]
[-f (overwrite existing output file)]
[-b (skip workflow and session logs)]
[-j (skip deploy group history)]
[-q (skip MX data)]
[-v (skip task statistics)]
```

The following table describes *pmrep* BackUp options and arguments:

Option	Argument	Description
-o	output_file_name	Required. Name and path of the file for the repository backup. When you view the list of repository backup files in the Administrator tool, you can see only files with an extension of .rep.
-d	description	Optional. Creates a description of the backup file based on the string that follows the option. The backup process truncates any character beyond 2,000.

Option	Argument	Description
-f	-	Optional. Overwrites an existing file with the same name.
-b	-	Optional. Skips tables related to workflow and session logs during backup.
-j	-	Optional. Skips deployment group history during backup.
-q	-	Optional. Skips tables related to MX data during backup.
-v	-	Optional. Skips task statistics during backup.

To restore the backup file, use the Administrator tool, or use the *pmrep* Restore command.

To back up the PowerCenter Repository Service repository, select the service in the Administrator tool. On the **Domain Actions** menu, click **Repository Contents** > **Backup**.

Optional. Export domain objects

You can choose to export the domain objects. When you export domain objects, you export native users, native groups, roles, connections, and cluster configurations from the Informatica domain to an XML file.

If you don't want to export all objects in the domain, use an infacmd export control file to filter the objects that you want to export.

You can use the ExportDomainObjects and ImportDomainObjects commands to migrate objects between two different domains of the same version.

When you export a group, you export all subgroups and users in the group.

You can't export the Administrator user, the Administrator group, users in the Administrator group, the Everyone group, or the LDAP users or groups. To replicate LDAP users and groups in an Informatica domain, import the LDAP users and groups directly from the LDAP directory service.

If the command fails with a Java memory error, increase the system memory available for infacmd. To increase the system memory, set the -Xmx value in the ICMD_JAVA_OPTS environment variable.

The infacmd isp ExportDomainObjects command uses the following syntax:

```
ExportDomainObjects

<-DomainName|-dn> domain_name

<-UserName|-un> user_name

<-Password|-pd> password

[<-SecurityDomain|-sdn> security_domain]

[<-Gateway|-hp> gateway_host1:port gateway_host2:port...]

[<-ResilienceTimeout|-re> timeout_period_in_seconds]

<-ExportFile|-fp> export_file_name

[<-ExportControlFile|-cp> export_control_file_name]

[<-RetainPassword|-rp> retain_password]

[<-Force|-f>]
```

The following table describes infacmd isp ExportDomainObjects options and arguments:

Option	Argument	Description
-DomainName -dn	domain_name	Required. Name of the Informatica domain. You can set the domain name with the -dn option or the environment variable INFA_DEFAULT_DOMAIN. If you set a domain name with both methods, the -dn option takes precedence.
-UserName -un	user_name	Required if the domain uses Native or LDAP authentication. User name to connect to the domain. You can set the user name with the -un option or the environment variable INFA_DEFAULT_DOMAIN_USER. If you set a user name with both methods, the -un option takes precedence. Optional if the domain uses Kerberos authentication. To run the command with single sign-on, do not set the user name. If you set the user name, the command runs without single sign-on.
-Password -pd	password	Required if you specify the user name. Password for the user name. You can set a password with the -pd option or the environment variable INFA_DEFAULT_DOMAIN_PASSWORD. If you set a password with both methods, the password set with the -pd option takes precedence. For a user account in the domain that uses native authentication, if you enable password complexity, use the following guidelines when you create or change a password: - The length of the password must be at least eight characters. - It must be a combination of an alphabet character, a numeric character and a non-alphanumeric character, such as: `! \ " # $ % & ' ( ) * + , - . / : ; < = > ? @ [ ] ^ _ ` { | } ~` When you use special characters in a password, the shell sometimes interprets them differently. For example, $ is interpreted as a variable. In this case, use an escape character to escape the special character.
-SecurityDomain -sdn	security_domain	Required if the domain uses LDAP authentication. Optional if the domain uses native authentication or Kerberos authentication. Name of the security domain to which the domain user belongs. You can set a security domain with the -sdn option or the environment variable INFA_DEFAULT_SECURITY_DOMAIN. If you set a security domain name with both methods, the -sdn option takes precedence. The security domain name is case sensitive. If the domain uses native or LDAP authentication, the default is Native. If the domain uses Kerberos authentication, the default is the LDAP security domain created during installation. The name of the security domain is the same as the user realm specified during installation.

Option	Argument	Description
-Gateway -hp	gateway_host1:port gateway_host2:port ...	Required if the gateway connectivity information in the domains.infa file is out of date. The host names and port numbers for the gateway nodes in the domain.
-ResilienceTimeout -re	timeout_period_in_seconds	Optional. Amount of time in seconds that infacmd attempts to establish or re-establish a connection to the domain. If you omit this option, infacmd uses the timeout value specified in the INFA_CLIENT_RESILIENCE_TIMEOUT environment variable. If no value is specified in the environment variable, the default of 180 seconds is used.
-ExportFile -fp	export_file_name	Required. Path and file name of the export file. If you do not specify the file path, infacmd creates the file in the directory where you run infacmd.
-ExportControlFile -cp	export_control_file	Optional.Name and path for the export control file that filters the objects that are exported.
-RetainPassword -rp	retain_password	Optional. Set to true to retain encrypted passwords for users and connections in the exported file. When set to false, user and connection passwords are exported as empty strings. Default is false.
-Force -f	-	Optional. Overwrites the export file if a file with the same name already exists. If you omit this option, the command prompts you for a confirmation before it overwrites the file.

Disable domain services

Disable the services in the domain before you shut down the domain. Shutting down the domain does not disable the services.

Disable domain services from the Administrator tool.

To disable a service, perform the following steps:

1. Log in to the Administrator tool.
2. Click the **Services and Nodes** view on the **Manage** tab.
3. In the **Domain Navigator**, select the service that you want to disable.
4. On the **Manage** tab **Actions** menu, click **Disable Service**.

Repeat the steps to disable all services in the domain.

Shut down the domain

Shut down the domain before you back up the domain.

Note: Before you shut down the domain, disable all application services.

To shut down the domain, stop the Informatica service process on the node.

To stop Informatica service, use the *infaservice* command. By default, the *infaservice* executable file is installed in the following directory:

```
<Informatica installation directory>/tomcat/bin
```

Enter the following command to stop the daemon:

```
infaservice shutdown
```

You can also stop the Informatica service from the Administrator tool.

Back up the domain

To create a backup of the domain, the domain must be shut down.

Perform the following steps to back up the domain:

- Run the infasetup BackupDomain command to back up the domain configuration database tables to a file.
- Back up the metadata configuration files.

Informatica infasetup includes command line programs to back up and restore the domain. infasetup is located in the following directory:

```
<Informatica installation directory>/isp/bin
```

To back up the domain with infasetup, use the following syntax:

```
BackupDomain
<<-DatabaseAddress|-da> database_hostname:database_port|

<-DatabaseConnectionString|-cs> database_connection_string>

<-DatabaseUserName|-du> database_user_name

<-DatabasePassword|-dp> database_password

<-DatabaseType|-dt> database_type

[<-DatabaseServiceName|-ds> database_service_name]

<-BackupFile|-bf> backup_file_name

[<-Force|-f>]

<-DomainName|-dn> domain_name

[<-Tablespace|-ts> tablespace_name (used for IBM DB2 only)]

[<-SchemaName|-sc> schema_name (used for Microsoft SQL Server only)]

[<-DatabaseTlsEnabled|-dbtls> database_tls_enabled]

[<-DatabaseTruststorePassword|-dbtp> database_truststore_password]

[<-TrustedConnection|-tc> trusted_connection (used for Microsoft SQL Server only)]

[<-EncryptionKeyLocation|-kl> encryption_key_location]
```

The following table describes *infasetup* BackupDomain options and arguments:

Option	Argument	Description
-DatabaseAddress -da	database_hostname:database_port	Required if you do not use -DatabaseConnectionString (-cs) option. Name and port number of the machine hosting the domain configuration database.
-DatabaseConnectionString -cs	database_connection_string	Connection string used to connect to the domain configuration database. Required if you do not use -DatabaseAddress (-da) and -DatabaseServiceName (-ds) options. Specify the database host, database port, and the database service name as part of the connection string. Enclose the connection string in double quotes.
-DatabaseUserName -du	database_user_name	Required if you do not use -TrustedConnection (-tc) option. Account for the database containing the domain configuration information.
-DatabasePassword -dp	database_password	Domain configuration database password corresponding to the database user. If you omit this option, *infasetup* uses the password specified in the INFA_DEFAULT_DATABASE_PASSWORD environment variable. If no value is specified in the environment variable, you must enter a password using this option.
-DatabaseType -dt	database_type	Required. Type of database that stores the domain configuration metadata. Database types include: - db2 - oracle - mssqlserver - sybase
-DatabaseServiceName -ds	database_service_name	Required if you do not use -DatabaseConnectionString (-cs) option. The database service name. Required for Oracle, IBM DB2, and Microsoft SQL Server databases. Enter the SID for Oracle, the service name for IBM DB2, or the database name for Microsoft SQL Server.
-BackupFile -bf	backup_file_name	Required. Name and path for the backup file. If you do not specify a file path, *infasetup* creates the backup file in the current directory.
-Force -f	-	Optional. Overwrites the backup file if a file with the same name already exists.
-DomainName -dn	domain_name	Required. Name of the domain.
-Tablespace -ts	tablespace_name	Required for an IBM DB2 database. Name of the tablespace where the domain configuration database tables reside.
-SchemaName -sc	schema_name	Optional. Name of the Microsoft SQL Server schema. Enter a schema name if you are not using the default schema.

Option	Argument	Description
-DatabaseTlsEnabled -dbtls	database_tls_enabled	Optional. Indicates whether the Informatica domain database is secure with TLS or SSL. Set this option to True for the secure database. Default is false. If you specify the -dbtls option without a value, the Informatica domain uses secure communication to the Informatica domain database.
-DatabaseTruststorePassword -dbtp	database_truststore_password	Optional. Password for the database truststore file for the secure database.
-TrustedConnection -tc	-	Optional. Connect to the Microsoft SQL Server database through a trusted connection. Trusted authentication uses the Windows security credentials of the current user to connect to Microsoft SQL Server.
-EncryptionKeyLocation -kl	encryption_key_location	Optional. Directory that contains the current encryption key. You must specify the key location if the encryption key does not exist in the isp/config/nodemeta.xml file. The name of the encryption file is sitekey.
-DatabaseTruststoreLocation -dbtl	database_truststore_location	Path and file name of the truststore file for the secure domain repository database. Required if you configure a secure domain repository database for the domain.

The following table describes the metadata files and the locations where you can find them:

Metadata File	Description
nodemeta.xml	Contains metadata for a node. Stored in the <Informatica installation directory>/isp/config directory on the node.
domains.infa	Contains connectivity information for the gateway nodes. Stored in one of the following locations: - The Informatica installation directory on the client and server machines. - The location configured through the INFA_DOMAINS_FILE environment variable.

Split the domain

Perform the following tasks to split the domain:

1. Copy the installation directory to another location on the host machine.
2. Configure environment variables for the new domain.
3. Copy the domain backup file to the target domain.
4. Copy the sitekey and other node configuration files from the source to the target location.
5. Restore the domain on the target location.
6. Update the target domain details.
7. Start the target domain.
8. Update service database details.
9. Restore the repository service database backups.

10. Delete services from the source domain.
11. Enable services on the source and target domains.

Copy the Informatica installation directory

To begin the split process, copy the Informatica installation directory to the location where you want to create the target domain.

Before you copy the installation directory, verify that you have read permissions on the following directories:

```
<Informatica installation directory>/isp/config
<Informatica installation directory>/services/shared/security
```

Copy the Informatica installation directory to the required location on the host machine. Perform this task for all nodes in the domain.

You will restore the domain on one gateway node host, and define the new worker nodes.

Configure environment variables

Each domain requires a different set of environment variables. Create a script to set environment variables for the target domain.

Run `printenv` or `setenv` to identify environment variables on the host machine. Create a script to set environment variables that the Informatica services require, such as Informatica environment variables and library paths.

Important: You must run the script before you start Informatica services or run infacmd and infasetup commands.

The following table describes environment variables required for the Informatica domain:

Environment Variable	Description
INFA_DOMAINS_FILE	The location of the domains.infa file.
INFA_HOME	The Informatica installation directory. If you use a softlink to specify the location of infaservice.sh, set the appropriate INFA_HOME environment variable location to start or stop Informatica services in each domain.
INFA_JAVA_OPTS	The maximum heap size.
INFA_TRUSTSTORE	Required for a secure domain. The directory that contains the truststore files for the SSL certificates. The directory must contain truststore files named infa_truststore.jks and infa_truststore.pem.
INFA_TRUSTSTORE_PASSWORD	Required for a secure domain. The encrypted password for the infa_truststore.jks that contains the SSL certificate. Use pmpasswd to encrypt the password.
ODBCHOME	The path to the ODBC drivers.
ODBCINI	The path to the odbc.ini file for the target domain.
LD_LIBRARY_PATH	The path to databases.

For more information about environment variables required by Informatica services, see the *Informatica Installation and Configuration Guide*.

Copy the domain backup file to the target location

To create a copy of the domain in the target location, the domain files must be present and accessible on the target location.

Copy the backup file that you created in "Back up the domain" on page 9 to a location that is accessible on the target location.

Copy node configuration files from the source domain to the target domain

Copy the required node configuration files such as the encryption key file and nodemeta.xml to the target location on the same host.

Run the infasetup CopyNodeConfigurationFiles command to copy the files.

The CopyNodeConfigurationFiles command uses the following syntax:

```
CopyNodeConfigurationFiles
<-PreviousInfaHome|-ph>
[<-KeysDirectory|-kd>]
```

The following table describes infasetup CopyNodeConfigurationFiles options and arguments:

Option	Description
-PreviousInfaHome -ph	Informatica installation directory of the source domain.
-KeysDirectory -kd	Path to the encryption key folder of the source domain.

Example: `./infasetup.sh copyNodeConfigurationFiles -ph /data/home/installer/Informatica/10.5.1_split/ -kd /data/home/installer/Informatica/10.5.1_split1/isp/config/keys`

Restore the domain on the target location

Restore the backup of the source domain on the target location. When you restore the backup, you restore the configuration metadata on the target to create a copy of the source domain on the target.

The infasetup RestoreDomain command restores the configuration metadata for the domain from a backup .mrep file.

The domain must be shut down before you run this command.

If you restore the domain into a database other than the original backup database, you must restore the ISP_RUN_LOG table contents to get the previous workflow and session logs.

If the command fails with a Java memory error, increase the system memory available for infasetup. To increase the system memory, set the -Xmx value in the INFA_JAVA_CMD_OPTS environment variable.

The RestoreDomain command uses the following syntax:

```
RestoreDomain

<<-DatabaseAddress|-da> database_hostname:database_port|

<-DatabaseConnectionString|-cs> database_connection_string>

[<-DatabaseUserName|-du> database_user_name]

[<-DatabasePassword|-dp> database_password]

<-DatabaseType|-dt> database_type
```

```
[<-DatabaseServiceName|-ds> database_service_name]

<-BackupFile|-bf> backup_file_name

[<-Force|-f>]

[<-ClearNodeAssociation|-ca>]

[<-Tablespace|-ts> tablespace_name]

[<-SchemaName|-sc> schema_name (used for MSSQLServer and PostgreSQL only)]

[<-DatabaseTlsEnabled|-dbtls> database_tls_enabled]

[<-DatabaseTruststorePassword|-dbtp> database_truststore_password]

[<-TrustedConnection|-tc> trusted_connection (used for MSSQLServer only)]

[<-EncryptionKeyLocation|-kl> encryption_key_location]

[<-DatabaseTruststoreLocation|-dbtl> database_truststore_location]
```

The following table describes *infasetup* RestoreDomain options and arguments:

Option	Argument	Description
-DatabaseAddress -da	database_hostname:database_port	Required if you do not use -DatabaseConnectionString (-cs) option. Name and port number of the machine hosting the domain configuration database.
-DatabaseConnectionString -cs	database_connection_string	Connection string used to connect to the domain configuration database. Required if you do not use -DatabaseAddress (-da) and -DatabaseServiceName (-ds) options. Specify the database host, database port, and the database service name as part of the connection string. Enclose the connection string in double quotes.
-DatabaseUserName -du	database_user_name	Required if you do not use -TrustedConnection (-tc) option. Account for the database containing the domain configuration information.
-DatabasePassword -dp	database_password	Domain configuration database password corresponding to the database user. If you omit this option, *infasetup* uses the password specified in the INFA_DEFAULT_DATABASE_PASSWORD environment variable. If no value is specified in the environment variable, you must enter a password using this option.
-DatabaseType -dt	database_type	Required. Type of database that stores the domain configuration metadata. Database types include: - db2 - oracle - mssqlserver - sybase - postgresql

Option	Argument	Description
-DatabaseServiceName -ds	database_service_name	Required if you do not use -DatabaseConnectionString (-cs) option. The database service name. Required for Oracle, IBM DB2, and Microsoft SQL Server databases. Enter the SID for Oracle, the service name for IBM DB2, or the database name for Microsoft SQL Server.
-BackupFile -bf	backup_file_name	Required. Name and path for the backup file. If you do not specify a file path, *infasetup* creates the backup file in the current directory.
-Force -f	-	Optional. Overwrites the database if a database with the same name already exists. Do not include any characters after this option.
-ClearNodeAssociation -ca	-	Optional. Clears node associations when restoring the domain. For example, a backed up domain contains node “Node1” on machine “MyHost:9090.” If you specify this option, the connection between the node name “Node1” and the address “MyHost:9090” is broken when you restore the domain. You can then associate another node with “MyHost:9090.” If you do not specify this option, “Node1” retains its connection to “MyHost:9090.” If you restore the domain and associate another node with “MyHost:9090,” the node does not start.
-Tablespace -ts	tablespace_name	Required for an IBM DB2 database. Name of the tablespace where the domain configuration database tables reside.
-SchemaName -sc	schema_name	Optional. Name of the Microsoft SQL Server or PostgreSQL schema. Enter a schema name if you are not using the default schema.
-DatabaseTlsEnabled -dbtls	database_tls_enabled	Optional. Indicates whether the Informatica domain database is secure with TLS or SSL. Set this option to True for the secure database. Default is false. If you specify the -dbtls option without a value, the Informatica domain uses secure communication to the Informatica domain database.
-DatabaseTruststorePassword -dbtp	database_truststore_password	Optional. Password for the database truststore file for the secure database.
-TrustedConnection -tc	-	Optional. Connect to the Microsoft SQL Server database through a trusted connection. Trusted authentication uses the Windows security credentials of the current user to connect to Microsoft SQL Server.

Option	Argument	Description
-EncryptionKeyLocation -kl	encryption_key_location	Optional. Directory that contains the current encryption key. You must specify the key location if the encryption key does not exist in the isp/config/keys/sitekey file. The name of the encryption file is sitekey.
-DatabaseTruststoreLocation -dbtl	database_truststore_location	Optional. Path and file name of the truststore file for the secure database. Required if you configure a secure domain repository database for the domain.

Define the domain details

After you restore the source domain configuration to the target domain, define the domain details to reflect any changes that you need to make, such as the domain configuration databases, port numbers, or backup directories.

The infasetup DefineGatewayNode command updates connectivity information for a gateway node on the current machine. The node must be shut down before you run the command. After you run the command, the target domain points to the updated Domain Configuration repository.

The DefineGatewayNode command uses the following syntax:

```
DefineGatewayNode
<-DatabaseAddress|-da> database_hostname:database_port|<-DatabaseConnectionString|-cs>
database_connection_string>
[<-DatabaseUserName|-du> database_user_name]
[<-DatabasePassword|-dp> database_password]
<-DatabaseType|-dt> database_type ORACLE|DB2|MSSQLSERVER|SYBASE|POSTGRESQL
[<-DatabaseServiceName|-ds> database_service_name]
<-DomainName|-dn> domain_name
<-NodeName|-nn> node_name
<-NodeAddress|-na> node_host:port
[<-ServiceManagerPort|-sp> service_manager_port]
[<-EnableTLS|-tls> enable_tls]
[<-NodeKeystore|-nk> node_keystore_directory]
[<-NodeKeystorePass|-nkp> node_keystore_password]
[<-NodeTruststore|-nt> node_truststore_directory]
[<-NodeTruststorePass|-ntp> node_truststore_password]
[<-CipherWhiteList|-cwl> comma_separated_white_list_jsse_cipher_names]
[<-CipherBlackList|-cbl> comma_separated_black_list_jsse_cipher_names]
[<-CipherWhiteListFile|-cwlf>
absolute_filename_containing_comma_separated_white_list_jsse_cipher_names]
[<-CipherBlackListFile|-cblf>
absolute_filename_containing_comma_separated_black_list_jsse_cipher_names]
[<-EnableKerberos|-krb> enable_kerberos]
[<-ServiceRealmName|-srn> realm_name_of_node_spn]
[<-UserRealmName|-urn> realm_name_of_user_spn]
[<-KeysDirectory|-kd> Infa_keys_directory_location]
[<-EnableSaml|-saml> enable_saml]
[<-SamlTrustStoreDir|-std> saml_truststore_directory]
[<-SamlTrustStorePassword|-stp> saml_truststore_password]
[<-SamlKeyStoreDir|-skd> saml_keystore_directory]
[<-SamlKeyStorePassword|-skp> saml_keystore_password]
[<-AdminconsolePort|-ap> admin_tool_port]
[<-HttpsPort|-hs> admin_tool_https_port]
[<-KeystoreFile|-kf> admin_tool_keystore_file_location]
[<-KeystorePass|-kp> admin_tool_keystore_password]
[<-MinProcessPort|-mi> minimum_port]
[<-MaxProcessPort|-ma> maximum_port]
<-LogServiceDirectory|-ld> log_service_directory
[<-SystemLogDirectory|-sld> system_log_directory]
[<-ServerPort|-sv> server_shutdown_port]
[<-AdminconsoleShutdownPort|-asp> admin_tool_shutdown_port]
[<-BackupDirectory|-bd> backup_directory]
```

```
[<-ErrorLogLevel|-el> FATAL_ERROR_WARNING_INFO_TRACE_DEBUG]
<-ResourceFile|-rf> resource_file
[<-Tablespace|-ts> tablespace_name]
[<-SchemaName|-sc> schema_name (used for MSSQLServer and PostgreSQL only)]
[<-DatabaseTlsEnabled|-dbtls> database_tls_enabled]
[<-DatabaseTruststorePassword|-dbtp> database_truststore_password]
[<-TrustedConnection|-tc> trusted_connection (used for MSSQLServer only)]
[<-DatabaseTruststoreLocation|-dbtl> database_truststore_location]
```

The following table describes *infasetup* DefineGatewayNode options and arguments:

Option	Description
-DatabaseAddress -da	Required if you do not use -DatabaseConnectionString (-cs) option. Name and port number of the machine hosting the domain configuration database.
-DatabaseConnectionString -cs	Connection string used to connect to the domain configuration database. Required if you do not use -DatabaseAddress (-da) and -DatabaseServiceName (-ds) options. Specify the database host, database port, and the database service name as part of the connection string. Enclose the connection string in double quotes.
-DatabaseUserName -du	Required if you do not use -TrustedConnection (-tc) option. Account for the database containing the domain configuration information.
-DatabasePassword -dp	Domain configuration database password corresponding to the database user. If you omit this option, *infasetup* uses the password specified in the INFA_DEFAULT_DATABASE_PASSWORD environment variable. If no value is specified in the environment variable, you must enter a password using this option.
-DatabaseType -dt	Required. Type of database that stores the domain configuration metadata. Database types include: - db2 - oracle - mssqlserver - sybase - postgresql
-DatabaseServiceName -ds	Required if you do not use -DatabaseConnectionString (-cs) option. The database service name. Required for Oracle, IBM DB2, and Microsoft SQL Server databases. Enter the SID for Oracle, the service name for IBM DB2, or the database name for Microsoft SQL Server.
-DomainName -dn	Required. Name of the domain.
-NodeName -nn	Optional. Name of the node. Node names must be between 1 and 79 characters and cannot contain spaces or the following characters: \ / * ? < > " |
-NodeAddress -na	Optional. Host name and port number for the machine hosting the node. Choose an available port number.
-ServiceManagerPort -sp	Optional. Port number used by the Service Manager to listen for incoming connection requests.

Option	Description
-EnableTLS -tls	Optional. Configures secure communication among the services in the Informatica domain. If you use the default SSL certificates provided by Informatica, you do not need to specify the keystore and truststore options. If you do not use the default SSL certificate, you must specify the keystore and truststore options. Valid values are true or false. Default is false. If you specify the -tls option without a value, the Informatica domain uses secure communication among the services. To enable secure communication for the associated services or web applications, such as Administrator tool, Analyst tool, or Web Services Hub, configure the secure communication separately within the applications.
-NodeKeystore -nk	Optional if you use the default SSL certificates from Informatica. Required if you use your SSL certificates. Directory that contains the keystore files. The Informatica domain requires the SSL certificates in PEM format and in Java Keystore (JKS) files. The directory must contain keystore files in PEM and JKS formats. The keystore files must be named infa_keystore.jks and infa_keystore.pem. If the keystore file that you receive from the certificate authority (CA) has a different name, you must rename it to infa_keystore.jks and infa_keystore.pem. You must use the same keystore file for all the nodes in the domain.
-NodeKeystorePass -nkp	Optional if you use the default SSL certificates from Informatica. Required if you use your SSL certificates. Password for the keystore infa_keystore.jks file.
-NodeTruststore -nt	Optional if you use the default SSL certificates from Informatica. Required if you use your SSL certificates. Directory that contains the truststore files. The Informatica domain requires the SSL certificates in PEM format and in Java Keystore (JKS) files. The directory must contain truststore files in PEM and JKS formats. The truststore files must be named infa_truststore.jks and infa_truststore.pem. If the truststore file that you receive from the certificate authority (CA) has a different name, you must rename it to infa_truststore.jks and infa_truststore.pem.
-NodeTruststorePass -ntp	Optional if you use the default SSL certificates from Informatica. Required if you use your SSL certificates. Password for the infa_truststore.jks file.
-CipherWhiteList -cwl	Optional. Comma-separated list of JSSE cipher suites that you want to add to the effective list. **Note:** The list must contain at least one valid JRE or OpenSSL cipher suite.
-CipherBlackList -cbl	Optional. Comma-separated list of JSSE cipher suites that you want to remove from the effective list. **Note:** The effective list must contain at least one valid JRE or OpenSSL cipher suite.
-CipherWhiteListFile -cwlf	Optional. Absolute file name of the plain text file that contains a comma-separated list of cipher suites that you want to add to the effective list. **Note:** The list must contain at least one valid JRE or OpenSSL cipher suite.
-CipherBlackListFile -cblf	Optional. Absolute file name of the plain text file that contains a comma-separated list of cipher suites that you want to remove from the effective list. **Note:** The effective list must contain at least one valid JRE or OpenSSL cipher suite.

Option	Description
-EnableKerberos -krb	Optional. Configures the Informatica domain to use Kerberos authentication. Valid values are true or false. If true, the domain uses Kerberos authentication, and you cannot later change the authentication mode. After you enable Kerberos authentication, you cannot disable it. Default is false. If you specify the -krb option without a value, the Informatica domain uses Kerberos authentication.
-ServiceRealmName -srn	Optional. Name of the Kerberos realm that the domain uses to authenticate users. The realm name must be in uppercase and is case-sensitive. To configure Kerberos cross realm authentication, specify the name of each Kerberos realm that the domain uses to authenticate users, separated by a comma. For example: COMPANY.COM,EAST.COMPANY.COM,WEST.COMPANY.COM Use an asterisk as a wildcard character before a realm name to include all realms that include the name. For example, specify the following value to include all realms that include the EAST.COMPANY.COM name: *EAST.COMPANY.COM
-UserRealmName -urn	Optional. Name of the Kerberos realm that the domain uses to authenticate users. The realm name must be in uppercase and is case-sensitive. To configure Kerberos cross realm authentication, specify the name of each Kerberos realm that the domain uses to authenticate users, separated by a comma. For example: COMPANY.COM,EAST.COMPANY.COM,WEST.COMPANY.COM Use an asterisk as a wildcard character before a realm name to include all realms that include the name. For example, specify the following value to include all realms that include the EAST.COMPANY.COM name: *EAST.COMPANY.COM
-KeysDirectory -kd	Optional. Directory where all keytab files and the encryption key for the Informatica domain are stored. Default is `<InformaticaInstallationDir>/isp/config/keys`.
-EnableSaml -saml	Optional. Enables or disables SAML authentication in the Informatica domain. Set this value to true to enable SAML authentication in the Informatica domain. Default is false.
-SamlTrustStoreDir -std	Optional. The directory containing the custom truststore file required to use SAML authentication on the gateway node. Specify the directory only, not the full path to the file. The default Informatica truststore is used if no truststore is specified.
-SamlTrustStorePassword -stp	Required if you use a custom truststore for SAML authentication. The password for the custom truststore.
-SamlKeyStoreDir -skd	Optional. The directory containing the custom keystore file required to use SAML authentication on the gateway node. Specify the directory only, not the full path to the file.
-SamlKeyStorePassword -skp	Required if you use a custom keystore for SAML authentication. Password to the SAML keystore. *

Option	Description
-AdminconsolePort -ap	Optional. Port to access Informatica Administrator.
-HttpsPort -hs	Optional. Port number that the node uses for communication between the Administrator tool and the Service Manager. Set this port number if you want to configure HTTPS for a node. To disable HTTPS support for a node, set this port number to zero.
-KeystoreFile -kf	Optional. Keystore file that contains the keys and certificates required if you use the SSL security protocol.
-KeystorePass -kp	Optional. A plain-text password for the keystore file. You can set a password with the -kp option or the environment variable INFA_PASSWORD. If you set a password with both methods, the password set with the -kp option takes precedence.
-MinProcessPort -mi	Optional. Minimum port number for application service processes that run on the node. Default is 11000.
-MaxProcessPort -ma	Optional. Maximum port number for application service processes that run on the node. Default is 11999.
-LogServiceDirectory -ld	Required. Shared directory path used by the Log Manager to store log event files. Verify that -ld does not match or contain the specified -sld value.
-SystemLogDirectory -sld	Optional. Directory path to store system log files. Verify that -ld does not match or contain the specified -sld value. Default is <INFA_home>/logs.
-ServerPort -sv	Optional. TCP/IP port number used by the Service Manager. The Service Manager listens for shutdown commands from PowerCenter components on this port. Set this port number if you have multiple nodes on one machine or if the default port number is in use. Default is 8005.
-AdminconsoleShutdownPort -asp	Optional. Port number that controls shutdown for Informatica Administrator.
-BackupDirectory -bd	Optional. Directory to store repository backup files. The directory must be accessible by the node.
-ErrorLogLevel -el	Optional. Severity level for log events in the domain log. Default is info.
-ResourceFile -rf	Required. File that contains the list of available resources for the node. Use the file nodeoptions.xml, located in the following directory: `<INFA_HOME>\isp\bin`.
-Tablespace -ts	Required for an IBM DB2 database. Name of the tablespace where the domain configuration database tables reside.
-SchemaName -sc	Optional. Name of the Microsoft SQL Server schema. Enter a schema name if you are not using the default schema.

Option	Description
-DatabaseTlsEnabled -dbtls	Optional. Indicates whether the Informatica domain database is secure with TLS or SSL. Set this option to True for the secure database. Default is false. If you specify the -dbtls option without a value, the Informatica domain uses secure communication to the Informatica domain database.
-DatabaseTruststorePassword -dbtp	Optional. Password for the database truststore file for the secure database.
-TrustedConnection -tc	Optional. Connect to the Microsoft SQL Server database through a trusted connection. Trusted authentication uses the Windows security credentials of the current user to connect to Microsoft SQL Server.
-DatabaseTruststoreLocation -dbtl	Path and file name of the truststore file for the secure domain repository database. Required if you configure a secure domain repository database for the domain.
* Note: If you currently run scripts that use this command to enable a custom keystore for SAML authentication, you must update them to include this option.	

Start the target domain

Start the target domain after you restore the domain configuration and update the domain details.

Run infaservice.sh to start the Informatica daemon for the target domain. By default, infaservice.sh is installed in the following directory: `<Informatica installation directory>/tomcat/bin`

Note: Disable the services on the source domain before you start the target domain.

1. Go to the directory where infaservice.sh is located.
2. At the command prompt, enter the following command to start the daemon: `infaservice.sh startup`

If you don't want to retain PowerCenter services on the target domain, you can choose to delete those services. For information about how to delete a service, see "Delete services from the source domain" on page 27. You can perform the steps on the target domain to delete services that you don't want to retain.

Update service details

After you start the target domain, update the service details. If you retain PowerCenter services on the target domain, ensure that the PowerCenter repository services point to the new database. You can run an infacmd isp command or log in to the Administrator tool to update the details.

To update the details from the Administrator tool, log in to the Administrator tool and select the required PowerCenter Repository Service. Edit the database properties to update the database details. Restart the service to update the changes.

You can run the infacmd isp UpdateRepositoryService command to update the service details.

The infacmd isp UpdateRepositoryService command uses the following syntax:

```
UpdateRepositoryService

<-DomainName|-dn> domain_name

<-UserName|-un> user_name

<-Password|-pd> password
```

```
[<-SecurityDomain|-sdn> security_domain]

[<-Gateway|-hp> gateway_host1:port gateway_host2:port...]

[<-ResilienceTimeout|-re> timeout_period_in_seconds]

<-ServiceName|-sn> service_name

[<-NodeName|-nn> node_name]

[<-BackupNodes|-bn> node1 node2 ...]

[<-ServiceOptions|-so> option_name=value ...]
```

The following table describes infacmd isp UpdateRepositoryService options and arguments:

Option	Argument	Description
-DomainName -dn	domain_name	Required. Name of the Informatica domain. You can set the domain name with the -dn option or the environment variable INFA_DEFAULT_DOMAIN. If you set a domain name with both methods, the -dn option takes precedence.
-UserName -un	user_name	Required if the domain uses Native or LDAP authentication. User name to connect to the domain. You can set the user name with the -un option or the environment variable INFA_DEFAULT_DOMAIN_USER. If you set a user name with both methods, the -un option takes precedence. Optional if the domain uses Kerberos authentication. To run the command with single sign-on, do not set the user name. If you set the user name, the command runs without single sign-on.
-Password -pd	password	Required if you specify the user name. Password for the user name. The password is case sensitive. You can set a password with the -pd option or the environment variable INFA_DEFAULT_DOMAIN_PASSWORD. If you set a password with both methods, the password set with the -pd option takes precedence.
-SecurityDomain -sdn	security_domain	Required if the domain uses LDAP authentication. Optional if the domain uses native authentication or Kerberos authentication. Name of the security domain to which the domain user belongs. You can set a security domain with the -sdn option or the environment variable INFA_DEFAULT_SECURITY_DOMAIN. If you set a security domain name with both methods, the -sdn option takes precedence. The security domain name is case sensitive. If the domain uses native or LDAP authentication, the default is Native. If the domain uses Kerberos authentication, the default is the LDAP security domain created during installation. The name of the security domain is the same as the user realm specified during installation.
-Gateway -hp	gateway_host1:port gateway_host2:port ...	Required if the gateway connectivity information in the domains.infa file is out of date. The host names and port numbers for the gateway nodes in the domain.

Option	Argument	Description
-ResilienceTimeout -re	timeout_period_in_seconds	Optional. Amount of time in seconds that infacmd attempts to establish or re-establish a connection to the domain. If you omit this option, infacmd uses the timeout value specified in the INFA_CLIENT_RESILIENCE_TIMEOUT environment variable. If no value is specified in the environment variable, the default of 180 seconds is used.
-ServiceName -sn	service_name	Required. Name of the PowerCenter Repository Service you want to update. To enter a name that contains a space or other non-alphanumeric character, enclose the name in quotation marks.
-NodeName -nn	node_name	Optional. Name of the node where the PowerCenter Repository Service process runs. If the PowerCenter environment is configured for high availability, this option specifies the name of the primary node.
-BackupNodes -bn	node1 node2 ...	Optional. Nodes on which the service can run if the primary node is unavailable. You can configure backup nodes if you have high availability.
-ServiceOptions -so	option_name=value	Required. Service properties that define how the PowerCenter Repository Service runs.

Enter Repository Service options in the following format:

```
infacmd CreateRepositoryService ... -so option_name=value option_name=value ...
```

To enter multiple options, separate them with a space. To enter a value that contains a space or other non-alphanumeric character, enclose the value in quotation marks.

The following table describes Repository Service options:

Option	Description
AllowWritesWithRACaching	Optional. Uses PowerCenter Client tools to modify metadata in the repository when repagent caching is enabled. Default is Yes.
CheckinCommentsRequired	Optional. Requires users to add comments when checking in repository objects. Default is Yes. To apply changes, restart the PowerCenter Repository Service.
CodePage	Required. Code page description for the database. To enter a code page description that contains a space or other non-alphanumeric character, enclose the name in quotation marks.
ConnectString	Required. Database connection string specified during PowerCenter Repository Service setup. To apply changes, restart the PowerCenter Repository Service.
DBPassword	Required. Repository database password corresponding to the database user. You can set a password with the -so option or the environment variable INFA_DEFAULT_DATABASE_PASSWORD. If you set a password with both methods, the password set with the -so option takes precedence. To apply changes, restart the PowerCenter Repository Service.

Option	Description
DBPoolExpiryThreshold	Optional. The minimum number of idle database connections allowed by the PowerCenter Repository Service. For example, if there are 20 idle connections, and you set this threshold to 5, the PowerCenter Repository Service closes no more than 15 connections. Minimum is 3. Default is 5.
DBPoolExpiryTimeout	Optional. The interval, in seconds, at which the PowerCenter Repository Service checks for idle database connections. If a connection is idle for a period of time greater than this value, the PowerCenter Repository Service can close the connection. Minimum is 300. Maximum is 2,592,000 (30 days). Default is 3,600 (1 hour).
DBUser	Required. Account for the database containing the repository. To apply changes, restart the PowerCenter Repository Service.
DatabaseArrayOperationSize	Optional. Number of rows to fetch each time an array database operation is issued, such as insert or fetch. Default is 100. To apply changes, restart the PowerCenter Repository Service.
DatabaseConnectionTimeout	Optional. Amount of time in seconds that the PowerCenter Repository Service attempts to establish a connection to the database management system. Default is 180.
DatabasePoolSize	Optional. Maximum number of connections to the repository database that the PowerCenter Repository Service can establish. Minimum is 20. Default is 500.
DatabaseType	Required. Type of database that stores the repository metadata. To apply changes, restart the PowerCenter Repository Service.
EnableRepAgentCaching	Optional. Enables the repository agent caching feature. Default is Yes.
ErrorSeverityLevel	Optional. Minimum level of error messages written to the PowerCenter Repository Service log: - Fatal - Error Warning - Info - Trace - Debug Default is Info.
HeartBeatInterval	Optional. Interval at which the PowerCenter Repository Service verifies its connections with clients of the service. Default is 60 seconds.
MaxResilienceTimeout	Optional. Maximum amount of time in seconds that the service holds on to resources for resilience purposes. Default is 180.
MaximumConnections	Optional. Maximum number of connections the repository accepts from repository clients. Default is 200.
MaximumLocks	Optional. Maximum number of locks the repository places on metadata objects. Default is 50,000.

Option	Description
OperatingMode	Optional. Mode in which the PowerCenter Repository Service is running: - Normal - Exclusive Default is Normal. To apply changes, restart the PowerCenter Repository Service.
OptimizeDatabaseSchema	Optional. Optimizes the repository database schema when you create repository contents or back up and restore an IBM DB2 or Microsoft SQL Server repository. When enabled, the PowerCenter Repository Service tries to create repository tables that contain Varchar columns with a precision of 2000 instead of CLOB columns. Use Varchar columns to increase repository performance. When you use Varchar columns, you reduce disk input and output, and the database can cache the columns. To use this option, verify the page size requirements for the following repository databases: - IBM DB2. Database page size 4 KB or greater. At least one temporary tablespace with page size 16 KB or greater. - Microsoft SQL Server. Database page size 8 KB or greater. Default is disabled.
PreserveMXData	Optional. Preserves MX data for prior versions of mappings. Default is disabled.
RACacheCapacity	Optional. Number of objects that the cache can contain when repository agent caching is enabled. Default is 10,000.
SecurityAuditTrail	Optional. Tracks changes made to users, groups, privileges, and permissions. Default is No.
ServiceResilienceTimeout	Optional. Amount of time in seconds that the service tries to establish or reestablish a connection to another service. Default is 180. To apply changes, restart the PowerCenter Repository Service.
TableOwnerName	Optional. Name of the owner of the repository tables for an IBM DB2 repository.
TablespaceName	Optional. Tablespace name for IBM DB2 repositories. To apply changes, restart the PowerCenter Repository Service.
TrustedConnection	Optional. Uses Windows authentication to access the Microsoft SQL Server database. Default is No. To apply changes, restart the PowerCenter Repository Service.

Restore the repository service backups

To restore the data from the source domain, restore the service backups after you update the service to point to the required database. You can restore the service backup from the Administrator tool or run a pmrep command to restore the backup.

To update the details from the Administrator tool, perform the following steps:

1. Log in to the Administrator tool.
2. On the Services and Nodes view, select the required PowerCenter Repository Service.
3. From the Actions menu, click **Repository Contents** > **Restore**.
4. Select a backup file to restore.
5. Choose whether to restore the repository as new. When you restore a repository as new, the PowerCenter Repository Service restores the repository with a new repository ID and deletes the log event files.

6. Optionally, choose to skip restoring the workflow and session logs, deployment group history, and Metadata Exchange (MX) data to improve performance.
7. Click **OK**. The activity log indicates whether the restore operation succeeded or failed.
   When you restore a global repository, the repository becomes a standalone repository. After restoring the repository, you need to promote it to a global repository.

You can run the pmrep Restore command to restore the repository service backup file to a database. The target database must be empty.

The *pmrep* Restore command uses the following syntax:

```
restore
-u <domain_user_name>
[-s <domain_user_security_domain>]
[-p <domain_password> |
 -P <domain_password_environment_variable>]
-i <input_file_name>
[-g (create global repository)]
[-y (enable object versioning)]
[-b (skip workflow and session logs)]
[-j (skip deployment group history)]
[-q (skip MX data)]
[-f (skip task statistics)]
[-a (as new repository)]
[-e (exit if domain name in the binary file is different from current domain name)]
```

The following table describes *pmrep* Restore options and arguments:

Option	Argument	Description
-u	domain_user_name	Required. User name.
-s	domain_user_security_domain	Required if you use LDAP authentication. Name of the security domain that the user belongs to. Default is Native.
-p	domain_password	Optional. Password. You can use the -p or -P option, but not both. If you do not use the -p or -P option, *pmrep* prompts you for the password.
-P	domain_password_ environment_variable	Optional. Password environment variable. You can use the -p or -P option, but not both. If you do not use the -p or -P option, *pmrep* prompts you for the password.
-i	input_file_name	Required. Name of the repository backup file. Use a file name and path local to the Repository Service.
-g	-	Optional. Promotes the repository to a global repository.
-y	-	Optional. Enables object versioning for the repository.

Option	Argument	Description
-b	-	Optional. Skips tables related to workflow and session logs during restore.
-j	-	Optional. Skips deployment group history during restore.
-q	-	Optional. Skips tables related to MX data during restore.
-f	-	Optional. Skips task statistics during restore.
-a	-	Optional. Creates new internal folder IDs for folders in the restored repository. This enables you to copy folders and deployment groups between the original repository and the restored repository. If you do not use -a, you cannot copy folders and deployment groups between the original and restored repositories.
-e	-	Optional. Exits if domain name in the binary file is different from current domain name

Delete services from the source domain

To ensure that the source domain is ready to migrate to CDI-PC, delete services that you can't migrate from the source domain. You can continue to use those services in the target domain.

Perform the following steps to delete services that you don't need on the source domain:

1. Log in to the Administrator tool.
2. Click the **Services and Nodes** view on the **Manage** tab.
3. In the Domain Navigator, select the service that you want to delete.
4. On the Domain Navigator **Actions** menu, click **Delete**.
5. Click **Yes** to confirm the delete.

Enable services in both domains

After you restore the repository service backups in the target domain and delete services that you don't want to keep in the source domain, enable the services in both domains.

Perform the following steps for each service in both domains:

1. Log in to the Administrator tool.
2. Click the **Services and Nodes** view on the **Manage** tab.
3. In the Domain Navigator, select the service that you want to enable.
4. On the **Manage** tab **Actions** menu, click **Enable the Service**.

The source domain now includes PowerCenter services that you can migrate to CDI-PC. The target domain contains all services that the original source domain contained, and you can continue to use the domain.

Author

Sadhana Kamath