

Informatica® Cloud Data Integration

JDBC V2 Connector

Informatica Cloud Data Integration JDBC V2 Connector
October 2025

© Copyright Informatica LLC 1993, 2026

This software and documentation are provided only under a separate license agreement containing restrictions on use and disclosure. No part of this document may be reproduced or transmitted in any form, by any means (electronic, photocopying, recording or otherwise) without prior consent of Informatica LLC.

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation is subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License.

Informatica, the Informatica logo, Informatica Cloud, and PowerCenter are trademarks or registered trademarks of Informatica LLC in the United States and many jurisdictions throughout the world. A current list of Informatica trademarks is available on the web at https://www.informatica.com/trademarks.html. Other company and product names may be trade names or trademarks of their respective owners.

Portions of this software and/or documentation are subject to copyright held by third parties. Required third party notices are included with the product.

See patents at https://www.informatica.com/legal/patents.html.

DISCLAIMER: Informatica LLC provides this documentation "as is" without warranty of any kind, either express or implied, including, but not limited to, the implied warranties of noninfringement, merchantability, or use for a particular purpose. Informatica LLC does not warrant that this software or documentation is error free. The information provided in this software or documentation may include technical inaccuracies or typographical errors. The information in this software and documentation is subject to change at any time without notice.

NOTICES

This Informatica product (the "Software") includes certain drivers (the "DataDirect Drivers") from DataDirect Technologies, an operating company of Progress Software Corporation ("DataDirect") which are subject to the following terms and conditions:

1. THE DATADIRECT DRIVERS ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT.
2. IN NO EVENT WILL DATADIRECT OR ITS THIRD PARTY SUPPLIERS BE LIABLE TO THE END-USER CUSTOMER FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, CONSEQUENTIAL OR OTHER DAMAGES ARISING OUT OF THE USE OF THE ODBC DRIVERS, WHETHER OR NOT INFORMED OF THE POSSIBILITIES OF DAMAGES IN ADVANCE. THESE LIMITATIONS APPLY TO ALL CAUSES OF ACTION, INCLUDING, WITHOUT LIMITATION, BREACH OF CONTRACT, BREACH OF WARRANTY, NEGLIGENCE, STRICT LIABILITY, MISREPRESENTATION AND OTHER TORTS.

The information in this documentation is subject to change without notice. If you find any problems in this documentation, report them to us at infa_documentation@informatica.com.

Informatica products are warranted according to the terms and conditions of the agreements under which they are provided. INFORMATICA PROVIDES THE INFORMATION IN THIS DOCUMENT "AS IS" WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING WITHOUT ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND ANY WARRANTY OR CONDITION OF NON-INFRINGEMENT.

Publication Date: 2026-10-01

Table of Contents

Preface 5

Informatica Resources 5

- Informatica Documentation 5
- IDMC web site 5
- IDMC Communities 5
- IDMC Marketplace 6
- Data Integration connector documentation 6
- Informatica Knowledge Base 6
- IDMC Trust Center 6
- IDMC Pulse Dashboard 6
- Informatica Global Customer Support 6

Chapter 1: Introduction to JDBC V2 Connector 7

JDBC V2 Connector assets 7

Chapter 2: Connections for JDBC V2 8

Prerequisites 8

- Install the Type 4 JDBC driver 8

Connect to JDBC V2 9

- Before you begin 9
- Connection details 9

Connect to SSL-enabled databases for mappings in advanced mode 11

Configure the serverless runtime environment 12

Configure the elastic runtime environment 13

Proxy server settings 14

Chapter 3: Mappings in JDBC V2 Connector 15

JDBC V2 sources in mappings 15

- Joining multiple objects 17

JDBC V2 targets in mappings 18

- Create a target table at runtime 19

JDBC V2 lookups in mappings 21

Mappings in advanced mode example 22

Partitioning for mappings in advanced mode 23

- JDBC V2 data types supported for partitioning 24

Rules and guidelines for JDBC V2 objects in mappings 24

Rules and guidelines for JDBC V2 objects in mappings configured in advanced mode 26

Chapter 4: Migrating a mapping 28

Use the same object path for the migrated mapping 28

Use a different object path for the migrated mapping. 28
Migration options. 29
Rules and guidelines for migrating a mapping. 30

Appendix A: JDBC V2 data type reference. 31

JDBC V2 and transformation data types for Create New at Runtime option. 32
Rules and guidelines for data types. 34

Index. 35

Preface

Use *JDBC V2 Connector* to learn how to use the JDBC V2 connection to read from or write to Aurora PostgreSQL and other databases that support the Type 4 JDBC driver by using Data Integration. Learn to create a connection, develop and run mappings, mapping tasks, dynamic mapping tasks, and data transfer tasks in Data Integration.

Informatica Resources

Informatica provides you with a range of product resources through the Informatica Network and other online portals. Use the resources to get the most from your Informatica products and solutions and to learn from other Informatica users and subject matter experts.

Informatica Documentation

Use the Informatica Documentation Portal to explore an extensive library of documentation for current and recent product releases. To explore the Documentation Portal, visit https://docs.informatica.com.

If you have questions, comments, or ideas about the product documentation, contact the Informatica Documentation team at infa_documentation@informatica.com.

IDMC web site

You can access the Informatica® Intelligent Data Management Cloud™ (IDMC) web site at http://www.informatica.com/cloud.

IDMC Communities

Use the IDMC Community to discuss and resolve technical issues. You can also find technical tips, documentation updates, and answers to frequently asked questions.

Access the IDMC Community at:

https://network.informatica.com/community/informatica-network/products/cloud-integration

Developers can learn more and share tips at the Cloud Developer community:

https://network.informatica.com/community/informatica-network/products/cloud-integration/cloud-developers

IDMC Marketplace

Visit the Informatica Marketplace to try and buy Data Integration Connectors, templates, and mapplets:

https://marketplace.informatica.com/

Data Integration connector documentation

You can access documentation for Data Integration Connectors at the Documentation Portal. To explore the Documentation Portal, visit https://docs.informatica.com.

Informatica Knowledge Base

Use the Informatica Knowledge Base to find product resources such as how-to articles, best practices, video tutorials, and answers to frequently asked questions.

To search the Knowledge Base, visit https://search.informatica.com. If you have questions, comments, or ideas about the Knowledge Base, contact the Informatica Knowledge Base team at KB_Feedback@informatica.com.

IDMC Trust Center

The IDMC Trust Center provides information about Informatica security, compliance, and privacy practices.

You can access the trust center at https://trust.informatica.com/.

IDMC Pulse Dashboard

The IDMC Pulse Dashboard provides system status and upgrade information for all PODs and services across IDMC.

Follow the services you use and subscribe to alerts to receive notifications about upgrades, maintenance, production incidents, and upcoming releases. The IDMC Pulse Dashboard displays the production status of all the IDMC products. All maintenance updates are posted to this page, and during an outage, it will have the most current information. To ensure you are notified of updates and outages, you can subscribe to receive updates for a single service or all IDMC services. Subscribing to all services is the best way to be certain you never miss an update.

For more information, see the Service Status and Communications guide.

Informatica Global Customer Support

You can contact a Global Support Center through the Informatica Network or by telephone.

To find online support resources on the Informatica Network, click **Contact Support** in the IDMC Help menu to go to the **Cloud Support** page. The **Cloud Support** page includes system status information and community discussions. Log in to Informatica Network and click **Need Help** to find additional resources and to contact Informatica Global Customer Support through email.

The telephone numbers for Informatica Global Customer Support are available from the Informatica web site at https://www.informatica.com/services-and-training/support-services/contact-us.html.

CHAPTER 1

Introduction to JDBC V2 Connector

You can use JDBC V2 Connector to connect to databases that support the JDBC Type 4 driver with Data Integration, such as PostgreSQL and Azure SQL.

When you use JDBC V2 Connector, you can create a JDBC V2 connection and use the connection in Data Integration mappings and tasks. You can switch mappings to advanced mode to include transformations and functions that enable advanced functionality.

In advanced mode, the mapping can run on Amazon Web Services, Google Cloud Platform, the Microsoft Azure environment, Azure Kubernetes Service (AKS), or Elastic Kubernetes Service (EKS).

Note: JDBC V2 Connector provides generic connectivity to databases through the JDBC protocol. You can use this connector to connect to JDBC-compliant databases when Informatica does not provide specific database connectors or when you do not have access to the database connectors available for Cloud Data Integration. Informatica does not guarantee that the functionality or performance of JDBC V2 Connector will be equivalent to that of the available database connectors. You can connect to any JDBC-compliant databases you choose, but these databases might not have been evaluated for compatibility with this connector.

JDBC V2 Connector assets

Create assets in Data Integration to integrate data using JDBC V2 Connector.

When you use JDBC V2 Connector, you can include the following Data Integration assets:

- Data transfer task
- Dynamic mapping task
- Mapping
- Mapping task

Note: Dynamic mapping task applies only to mappings in advanced mode.

For more information about configuring assets and transformations, see *Mappings*, *Transformations*, and *Tasks* in the Data Integration documentation.

CHAPTER 2

Connections for JDBC V2

Create a JDBC V2 connection to access data from any database that supports the Type 4 JDBC driver, such as PostgreSQL and Azure SQL.

You can use a JDBC V2 connection to specify sources, targets and lookups in a mappings and mapping tasks.

Prerequisites

Before you create a JDBC V2 connection to read from or write to databases that support the JDBC Type 4 driver, complete the prerequisites.

Install the Type 4 JDBC driver

To read from or write to JDBC V2 objects, you need to install the Type 4 JDBC driver on the Secure Agent machine.

1. Download the latest Type 4 JDBC driver version that your database supports from the third-party vendor site.
   If you want to use JDBC V2 Connector to connect to Aurora PostgreSQL, download the Aurora PostgreSQL driver. Informatica has certified Aurora PostgreSQL driver 42.2.6 for JDBC V2 Connector.
2. Install the Type 4 JDBC driver for the database on the Secure Agent machine and perform the following tasks:
   a. Navigate to the following directory on the Secure Agent machine:
      `<Secure Agent installation directory>/ext/connectors/thirdparty/`
   b. Create a folder and add the driver based on the type of mapping that you want to configure.
      For mappings, add the driver in the following folder:

      `informatica.jdbc_v2/common`

      For mappings in advanced mode, add the driver in the following folders:

      `informatica.jdbc_v2/common`

      `informatica.jdbc_v2/spark`
3. Restart the Secure Agent.
   If you update the driver on the Secure Agent machine while the mapping in advanced mode runs, you need to restart the Secure Agent.

Connect to JDBC V2

Let's configure the JDBC V2 connection properties to connect to JDBC-compliant databases.

Before you begin

Before you get started, you'll need to install the Type 4 JDBC driver on the Secure Agent machine to establish a JDBC V2 connection.

Check out "Prerequisites" on page 8 to learn more about the configuration prerequisites.

Connection details

The following table describes the basic connection properties:

Property	Description
Connection Name	Name of the connection. Each connection name must be unique within the organization. Connection names can contain alphanumeric characters, spaces, and the following special characters: _ . + -, Maximum length is 255 characters.
Description	Description of the connection. Maximum length is 4000 characters.
Use Secret Vault	Stores sensitive credentials for this connection in the secrets manager that is configured for your organization. This property appears only if secrets manager is set up for your organization. When you enable the secret vault in the connection, you can select the credentials that the Secure Agent retrieves from the secrets manager. If you don't enable this option, the credentials are stored in the repository or on a local Secure Agent, depending on how your organization is configured. **Note:** If you're using this connection to apply data access policies through pushdown or proxy services, you cannot use the Secret Vault configuration option. For information about how to configure and use a secrets manager, see "Secrets manager configuration" in the Administrator help.
Runtime Environment	The name of the runtime environment where you want to run tasks. Select a Secure Agent, serverless, or elastic runtime environment. For more information about how to configure a serverless environment, see "Configure the serverless runtime environment" on page 12. For more information about how to configure an elastic environment, see "Configure the elastic runtime environment" on page 13.
JDBC Driver Class Name	Name of the JDBC driver class. For example, to connect to Aurora PostgreSQL, specify the following driver class name: org.postgresql.Driver For more information about which driver class to use with specific databases, see the corresponding third-party vendor documentation.

Property	Description
Connection String	Connection string to connect to the database. Use the following format to specify the connection string: `jdbc:<subprotocol>:<subname>` For example, the connection string for the Aurora PostgreSQL database type is `jdbc:postgresql://<host>:<port>[/dbname]`. For more information about the connection string to use with specific drivers, see the corresponding third-party vendor documentation. You can also connect to SSL-enabled Aurora PostgreSQL databases in mappings in advanced mode. For more information, see "Connect to SSL-enabled databases for mappings in advanced mode" on page 11.
User Name	The user name to connect to the database.
Password	The password to connect to the database.

Advanced settings

The following table describes the advanced connection properties:

Property	Description
Database Type	The database type to which you want to connect. Select one of the following database types: - PostgreSQL. Connect to the Aurora PostgreSQL database hosted in the Amazon Web Services or the Microsoft Azure environment. - Azure SQL Database. Connect to Azure SQL Database hosted in the Microsoft Azure environment. - Others. Connect to any database that supports the Type 4 JDBC driver, such as Salesforce Data Cloud. Default is Others.
Schema Name	The schema name used for the JDBC object. If you don't specify the schema name, all the schemas available in the database are listed. To read from or write to Oracle public synonyms, enter PUBLIC.
Connection Environment SQL	The SQL statement to set up the database environment when you connect to a PostgreSQL database. The database environment applies for the entire session that uses this connection. For example, you can enter this statement to set the time zone: `SET timezone to 'America/New_York';`
Additional Security Properties	Masks sensitive and confidential data of the connection string that you don't want to display in the session log. Specify the part of the connection string that you want to mask. When you create a connection, the string you enter in this field appends to the string that you specified in the **Connection String** field.

Property	Description
Enable Auto Commit	Specifies whether the driver supports connections to automatically commit data to the database when you run an SQL statement. When disabled, the driver does not support connections to automatically commit data even if the auto-commit mode is enabled in the JDBC driver. Default is disabled. This property does not apply to mappings in advanced mode.
Support Mixed-Case Identifiers	Indicates whether the database supports case-sensitive identifiers. When enabled, the Secure Agent encloses all identifiers within the character selected for the SQL Identifier Character property. Default is disabled.
SQL Identifier Character	Type of character that the database uses to enclose delimited identifiers in SQL queries. The available characters depend on the database type. Select **None** if the database uses regular identifiers. When the Secure Agent generates SQL queries, it does not place delimited characters around any identifiers. Select a character from the list based on what delimiter the database uses for identifiers. When the Secure Agent generates SQL queries, it encloses delimited identifiers within this character.

Connect to SSL-enabled databases for mappings in advanced mode

You can use JDBC V2 connection in mappings in advanced mode to connect to an SSL-enabled JDBC-complaint database. To run mappings in advanced mode with SSL-enabled JDBC-complaint databases, you need to download the SSL certificates to the Secure Agent machine, and then perform certain prerequisite tasks.

1. Specify the JDBC URL in the JDBC V2 connection properties.
   To connect to an SSL-enabled Aurora PostgreSQL database, specify the following JDBC URL:

   `jdbc:postgresql://<host>:<port>/dbname?sslmode=verify-ca&sslrootcert=<Location of the SSL certificate on the Secure Agent machine>`, where the values for sslmode supports `verify-ca` and `verify-ca`.

   For example, `jdbc:postgresql://aurorapostgres-appsdk.abc.ap-south-1.rds.amazonaws.com:5432/JDBC_V2?sslmode=verify-full&sslrootcert=/data/home/qamercury/cloud_td/Aurora_cert/rds-combined-ca-bundle.pem`.
2. After you specify the JDBC URL in the JDBC V2 connection properties, in the advanced session properties of the mapping task, select **advanced.custom.property** as the session property name.
3. In the session property value, specify the following value:
   Spark.NeedUserCredentialFileForAdapter=true&:Spark.UserCredentialDirOnDIS=<Location of the SSL certificate on the Secure Agent machine>
   - Spark.NeedUserCredentialFileForAdapter. When you set this property to true, the Secure Agent copies the SSL certificate from the Secure Agent machine to the advanced cluster.

- Spark.UserCredentialDirOnDIS. When you set this property to the location of the SSL certificates, the Secure Agent uses the specified location to get the SSL certificate.
  This property is optional. If you do not specify this property, the Secure Agent considers the following default location: `/infa/user/credentials`

Configure the serverless runtime environment

You can use a serverless runtime environment hosted on AWS or Azure to connect to JDBC-compliant databases.

Before you configure a JDBC V2 connection using the serverless runtime environment, perform the following tasks:

- Add the JDBC driver JAR files in the Amazon S3 bucket or Azure container in your AWS or Azure account.
- Configure the .yml serverless configuration file.

Add the JDBC driver JAR files in the Amazon S3 bucket or Azure container in your AWS or Azure account

Perform the following steps to configure a JDBC V2 connection in a serverless runtime environment:

1. Create the following structure for the serverless agent configuration on AWS or Azure:
   `<Supplementary file location>/serverless_agent_config`
2. Add the JDBC driver files in the Amazon S3 bucket or Azure container in the following location in your AWS or Azure account:
   `<Supplementary file location>/serverless_agent_config/common`
3. For mappings in advanced mode, additionally add the JDBC driver files in the following location in the Amazon S3 bucket or Azure container:
   `<Supplementary file location>/serverless_agent_config/spark`

Configure the .yml serverless configuration file

Perform the following steps to configure the .yml serverless configuration file in the serverless runtime environment:

1. Copy the following code snippet to a text editor based on the mappings that you want to run in a serverless environment:
   - For mappings that do not apply in advanced mode, add the following code snippet:

```
version: 1
agent:
  dataIntegrationServer:
    autoDeploy:
      jdbcv2:
        common:
          - fileCopy:
              sourcePath: common/<Driver_filename>
          - fileCopy:
              sourcePath: common/<Driver_filename>
```

   - For mappings in advanced mode, add the following code snippet:

```
version: 1
agent:
  elasticServer:
    autoApply:
      jdbcv2:
```

```
common:
  - fileCopy:
      sourcePath: common/<Driver_filename>
  - fileCopy:
      sourcePath: common/<Driver_filename>
spark:
  - fileCopy:
      sourcePath: spark/<Driver_filename>
  - fileCopy:
      sourcePath: spark/<Driver_filename>
```

where the source path is the directory path of the driver files on AWS or Azure.

2. Ensure that the syntax and indentations are valid, and then save the file as `serverlessUserAgentConfig.yml` in the following AWS or Azure location: `<Supplementary file location>/serverless_agent_config`
   When the .yml file runs, the JDBC driver files are copied from the AWS or Azure location to the serverless agent directory.

For more information about the serverless runtime environment, see *Serverless Runtime Environments* in the Administrator help.

Configure the elastic runtime environment

You can configure custom binary files in an elastic runtime environment to ensure that the runtime environment can access and execute these files during mapping runs.

Before you configure custom binary files, make sure that you deploy the elastic runtime environment on AWS to create a Kubernetes cluster that can process data within Informatica Intelligent Cloud Services.

For more information about deploying an elastic runtime environment, see Deploy an elastic runtime environment.

After you deploy the elastic runtime environment, place the custom binary files on the mounted disk and copy the exact path of the binary files to use in the POST request.

Perform the following steps within Informatica Intelligent Cloud Services for the elastic runtime environment to manage the custom binary files:

1. Log in to your organization and obtain the session ID and runtime environment ID.
2. Make a POST call to the REST API, passing the session ID, runtime environment ID, and the binary file path copied earlier from the mounted disk.
   For more about information about making the POST calls, see Supplementary files in the REST API Reference guide.

   The following is an example of the POST request:

```
POST <base URL>/api/v3/RuntimeEnvironment/<runtime environment ID>/ElasticConfig
Content-Type: application/json
Accept: application/json
INFA-SESSION-ID: <SessionId>
{
  "rteId": "rte-12345",
  "specification": {
    "agent": {
      "dataIntegrationServer": {
        "jdbcv2": {
          "common": [{"sourcePath": "/<path to binaries>/common1.jar"}],
          "spark": [{"sourcePath": "/<path to binaries>/spark1.jar"}]
        }
```

The POST call triggers a restart of the Data Integration Server.

3. Verify that the elastic runtime environment is up and running by checking the status of the Data Integration Server in Administrator.
4. Test a connection or run a mapping to confirm that the elastic runtime environment can access and use the custom binary files.

For more information about the elastic runtime environment, see *Elastic Runtime Environments* in the Administrator help.

Proxy server settings

If your organization uses an outgoing proxy server to connect to the Internet, the Secure Agent connects to Informatica® Intelligent Data Management Cloud™ (IDMC) through the proxy server.

You can configure the Secure Agent to use the SOCKS proxy server on Windows and Linux. You can use the unauthenticated or authenticated SOCKS proxy server. The proxy settings apply to connections used in mappings and in mappings in advanced mode.

To configure proxy settings for the Secure Agent, contact Informatica Global Customer Support.

CHAPTER 3

Mappings in JDBC V2 Connector

Use the Mapping Designer in Data Integration to define and configure a mapping for JDBC V2 sources and targets.

Add the Source and Target transformations in the mapping canvas and configure the JDBC V2 source and target properties. In advanced mode, the Mapping Designer updates the mapping canvas to include transformations and functions that enable advanced functionality. You can also use Monitor to monitor the jobs.

When you run a JDBC V2 mapping task based on either a mapping or a mapping in advanced mode and it completes, you can view the number of processed and failed rows for each source and target in the job details page.

JDBC V2 sources in mappings

When you configure a mapping to use a JDBC V2 source, you can configure the source properties.

Specify the name and description of the JDBC V2 source. Configure the source and advanced source properties for the JDBC V2 object.

You can parameterize the source and advanced source properties for the JDBC source object in a mapping. You can also parameterize the JDBC V2 source connection and source object with values specified in a parameter file when you configure a mapping in advanced mode.

The following table describes the JDBC V2 source properties that you can configure in a Source transformation:

Property	Description
Connection Name	Name of the source connection.
Source Type	Source type. Select one of the following source types: - **Single Object**. Select to specify a single JDBC V2 object. - **Multiple Objects**. Select to specify multiple JDBC V2 objects. Use the advanced relationship option to define the relationship for the objects that you want to join. - **Parameter**. Select to specify a parameter name. You can configure the source object in a mapping task associated with a mapping that uses this Source transformation. - **Query**. Select to define a valid and supported SQL query in the Source transformation.
Object	Source object for the mapping.

Property	Description
Filter	A simple filter or an advanced filter condition to remove rows at the source. You can improve efficiency by filtering early in the data flow. Specify a simple filter by including a field name, operator, and value. Configure an advanced filter to define a more complex filter condition that can include multiple conditions using the AND or OR logical operators. You can choose from the following filter conditions: - **Not parameterized**. Use a basic filter to specify the object, field, operator, and value to select specific records. - **Completely parameterized**. Use a parameter to represent the field mapping. - **Advanced**. Use an advanced filter to define a more complex filter condition.
Sort	Not applicable.

The following table describes the JDBC advanced source properties that you can configure in a Source transformation:

Advanced Source Property	Description
Pre SQL	The SQL query that the Secure Agent runs before reading data from the source.
Post SQL[1]	The SQL query that the Secure Agent runs after reading data from the source.
Fetch Size	The number of rows that the Secure Agent fetches from the database in a single call.
Table Name	Overrides the table name used in the metadata import with the table name that you specify.
Schema Name	Overrides the schema name of the source object. If you specify the schema name both in the connection and the source properties, the Secure Agent uses the schema name specified in the source properties.
SQL Override	The SQL statement to override the default query and the object name that is used to read data from the JDBC V2 source.
Tracing Level	Determines the amount of details that logs contain. You can select one of the following tracing levels: - **Terse**. The Secure Agent logs initialization information, error messages, and notification of rejected data. - **Normal**. The Secure Agent logs initialization and status information, errors encountered, and skipped rows due to transformation row errors. Summarizes session results, but not at the level of individual rows. - **Verbose Initialization**. In addition to normal tracing, the Secure Agent logs additional initialization details, names of index and data files used, and detailed transformation statistics. - **Verbose Data**. In addition to verbose initialization tracing, the Secure Agent logs each row that passes into the mapping. Also notes where the Secure Agent truncates string data to fit the precision of a column and provides detailed transformation statistics. When you configure the tracing level to verbose data, the Secure Agent writes row data for all rows in a block when it processes a transformation.

[1]Doesn't apply to mappings in advanced mode.


Joining multiple objects

When you create a Source transformation, you can select multiple JDBC V2 objects as the source type and then configure an advanced relationship to combine the tables. Ensure that the source tables do not contain the same name.

1. In the Source transformation, click the **Source Type** as **Multiple Objects**.
2. From the **Actions** menu, select **Add Source Object**, and then select the source object that you want to add from the displayed list:
3. Click **Related Objects Actions** menu, and then select **Advanced Relationship** to define the relationship between the tables:

   Note: The **Add Related Objects** option is not applicable.

   The following image shows an example of an advanced relationship condition defined between the JDBC V2 tables:



   If you join tables that are from different schemas, you must manually add the schema names.

   The following image shows an example of an advanced relationship condition defined between two JDBC V2 tables where the schema names are different:



JDBC V2 targets in mappings

When you configure a mapping to use a JDBC V2 target, you can configure the target properties.

Specify the name and description of the JDBC target. Configure the target and advanced target properties for the JDBC object in a Target transformation.

You can parameterize the target and advanced target properties for the JDBC target object in a mapping. You can also parameterize the JDBC V2 target connection and target object with values specified in a parameter file when you configure a mapping in advanced mode.

The following table describes the target properties that you can configure in a Target transformation:

Property	Description
Connection	Name of the target connection.
Target Type	Type of target object. Select one of the following target types: - Single. Select to specify a single JDBC object. - Parameter. Select to specify a parameter name. You can configure the target object in a mapping task associated with a mapping that uses this Target transformation.
Object	Name of the target object. You can select an existing object.
Create New at Runtime	Creates a target table at runtime using the object name and path you specify. You can create a target table at runtime only for PostgreSQL or Azure SQL Database. Ensure that you have selected PostgreSQL or Azure SQL Database in the JDBC V2 connection advanced properties based on the database that you want to connect. To create a target table at runtime, provide the following parameters: - **Object name**. Specify the name for the target table. - **Path**. Specify the target table name and schema in the following format: `<Schema-Name>/<TableType>`, where the mandatory value for TableType is *TABLE*.
Operation	Type of the target operation. Select Insert, Update, Upsert, Delete, or Data Driven.
Update columns	The temporary key column that identifies rows in the target table to update, upsert, or delete data.
Data Driven Condition	Flags rows for an insert, update, delete, or reject operation based on the data driven expression you specify. Appears only when the operation type is **Data Driven**. **Note:** To configure a data driven expression in a mapping, you need to specify the expression that uses the IIF function.

The following table describes the JDBC advanced target properties that you can configure in a Target transformation:

Advanced Target Property	Description
Pre SQL	The SQL statement to run before writing data to the target.
Post SQL	The SQL statement to run after writing data to the target.

Advanced Target Property	Description
Truncate Target	Truncates the target table before inserting records to the target.
Reject Truncated/ Overflow Rows	Writes truncated and overflow data to the reject file. If you select Reject Truncated/Overflow Rows, the Data Integration Service sends all truncated rows and any overflow rows to the reject file.
Table Name	Overrides the table name used in the metadata import with the table name that you specify.
Schema Name	Overrides the schema name of the target object. If you specify the schema name both in the connection and the target properties, the Secure Agent considers the schema name specified in the target properties.
Update Mode	Determines the mode how the Secure Agent writes data to the target. Select one of the following modes: - Update As Update. Updates all rows flagged for update if the entries exist. - Update Else Insert. Updates all rows flagged for update if the entries exist in the target. If the entries do not exist, the agent then inserts the entries.
Forward Rejected Rows	Determines whether the transformation passes rejected rows to the next transformation or drops rejected rows. By default, the agent forwards rejected rows to the next transformation.


Create a target table at runtime

You can use an existing target or create a target in a mapping. If you choose to create the target, the agent creates the target when you run the task.

To specify the target properties, perform the following tasks:

1. Select the Target transformation in the mapping.
2. On the **Incoming Fields** tab, configure field rules to specify the fields to include in the target.
3. To specify the target, click the **Target** tab.
4. Select the target connection.
5. For the target type, choose **Single Object** or **Parameter**.
6. Specify the target object or parameter.

7. To specify a target object, perform the following tasks:
   a. Click **Select** and choose a target object. You can select an existing target object or create a new target object at runtime and specify the object name.



   You must specify the target table name.
   b. To create a target object at runtime, select **Create New at Runtime**.
   c. Enter the name of the target table that you want to create name in the **Object Name** field.
   d. In the **Path** field, specify the target table name and schema in the following format: `<Schema-Name>/<TableType>`, where the mandatory value for TableType is *TABLE*.

      For example, *private/TABLE*

      In the example, the table is created in the schema named "private" in the database server. If you do not specify a value for the path, the Secure Agent considers the schema name you specified in the connection. If you did not specify a schema name in the connection, the Secure Agent creates the table in the default schema.
   e. Click **OK**.
8. Specify the advanced properties for the target, if required.

Rules and guidelines for creating a target at runtime

When you configure a mapping with the **Create New at Runtime** option, consider the following rules:

- Don't edit the metadata in the target object. If you edit the metadata, the changes are not reflected at runtime.
- When a target table exists, the Secure Agent uses the same target table.
- When you specify the schema name, Data Integration honors the attribute in the following order of precedence:
  1. The **Schema Name** advanced property in the Target transformation.
  2. The schema provided in the **Path** property in the **Create New at Runtime** option.
  3. The **Schema Name** advanced property in the JDBC V2 connection.
  4. The default schema of the database.
- When you specify the table name, Data Integration honors the attribute in the following order of precedence:
  1. The **Table Name** advanced property in the Target transformation.
  2. The **Object Name** property in the **Create New at Runtime** option.

JDBC V2 lookups in mappings

In a mapping, you can configure a Lookup transformation to represent a JDBC V2 object.

Specify the name and description of the JDBC V2 lookup.

You can parameterize the JDBC V2 lookup connection and lookup object with values specified in a parameter file when you configure a mapping in advanced mode.

You can create the following lookups when you configure field mappings in a mapping task:

- Connected lookup
- Unconnected lookup

Note: You can't configure a Lookup transformation in a data transfer task.

For more information about the Lookup transformation, see *Transformations*.

The following table describes the JDBC V2 lookup properties that you can configure in a Lookup transformation:

Property	Description
Connection Name	Name of the lookup connection.
Source Type	Source type. Select **Single Object** or **Parameter**.
Parameter	A parameter file where you define values that you want to update without having to edit the task. Select an existing parameter for the lookup object or click **New Parameter** to define a new parameter for the lookup object. The **Parameter** property appears only if you select parameter as the lookup type. If you want to overwrite the parameter at runtime, select the **Allow parameter to be overridden at run time** option. When the task runs, the Secure Agent uses the parameters from the file that you specify in the advanced session properties.
Lookup Object	Name of the lookup object for the mapping.
Multiple Matches	Behavior when the lookup condition returns multiple matches. Select from the following options: - Return any row - Return all rows - Report error
Filter	Not applicable.
Sort	Not applicable.

The following table describes the JDBC V2 lookup advanced properties that you can configure in a Lookup transformation:

Advanced Source Property	Description
Pre SQL	The SQL query that the Secure Agent runs before reading data from the source.
Post SQL[1]	The SQL query that the Secure Agent runs after reading data from the source.

Advanced Source Property	Description
Fetch Size	The number of rows that the Secure Agent fetches from the database in a single call.
Table Name	Overrides the table name used in the metadata import with the table name that you specify.
Schema Name	Overrides the schema name of the source object. If you specify the schema name both in the connection and the source properties, the Secure Agent uses the schema name specified in the source properties.
SQL Override	The SQL statement to override the default query and the object name that is used to read data from the JDBC V2 source.
[1]Doesn't apply to mappings in advanced mode.	

Mappings in advanced mode example

You work for a multi-national hospital that maintains medical records of patient emergencies for more than 50 specialties in their database across the globe. The hospital has more than 10,000 units spread across 500 locations.

Medical investigators from the hospital want to analyze the medical data of the treatment performance of specific inpatient hospital events within the hospitals. The management wants to use this analysis to provide better care for patients and help achieve health equity.


To avoid low performance and high-cost challenges, the hospital plans to port its entire data from all the hospital branches spread globally to Aurora PostgreSQL within a short span of time. Create a mapping in advanced mode to read data from the hospital branches and write data to the Aurora PostgreSQL target.

1. In Data Integration, click **New** > **Mappings** > **Mapping**.

   The **New Mapping** dialog box appears.

2. In the Mapping Designer, click **Switch to Advanced**.

   The following image shows the **Switch to Advanced** button in the Mapping Designer:



3. In the **Switch to Advanced** dialog box, click **Switch to Advanced**.

   The Mapping Designer updates the mapping canvas to display the transformations and functions that are available in advanced mode.
4. Enter a name, location, and description for the mapping.
5. Add a Source transformation, and specify a name and description in the general properties.
6. On the **Source** tab, perform the following steps to provide the source details to read data from the source:
   a. In the **Connection** field, select the required source connection.
   b. In the **Source Type** field, select the type of the source.
   c. In the **Object** field, select the required object.
   d. In the **Advanced Properties** section, provide the appropriate values.
7. Add a Target transformation, and specify a name and description in the general properties.
8. On the **Target** tab, perform the following steps to provide the target details to write data to the Amazon S3 target:
   a. In the **Connection** field, select the JDBC V2 target connection.
   b. In the **Target Type** field, select the type of the target.
   c. In the **Object** field, select the required object.
   d. In the **Operation** field, select the required operation.
   e. In the **Advanced Properties** section, provide appropriate values for the advanced target properties.
9. Click **Save** > **Run** the mapping.

   In Monitor, you can monitor the status of the logs after you run the mapping.

Partitioning for mappings in advanced mode

When you configure a JDBC V2 mapping in advanced mode to read from or write data to a database that supports the Type 4 JDBC driver, you can configure partitioning for the JDBC V2 source or target to optimize the mapping in advanced mode performance at run time. The partition type controls how the advanced cluster distributes data among partitions at partition points.

The advanced cluster distributes rows of data based on the partition key you define. Before you configure a partition, ensure that you select the partition key in the **Fields** tab of the Source or Target transformation in a JDBC V2 mapping. If the imported table already has a primary key defined, the cluster application considers that as the default partition key. Before you import, ensure that the table has only one partition key.

After you import, you can change the partition key on the **Fields** tab. From the **Options** list, select **Edit Metadata** and then select the partition key. Ensure that you do not define more than one partition key for the source or target.

The default number of partitions is 1. If the number of partitions you specified for the target is 1, the cluster application considers the same number of partitions you specified for the source as the target partition number.

JDBC V2 data types supported for partitioning

The following table lists the JDBC V2 data types supported as partition keys:

Data types	Supported
Smallint	Yes
Integer	Yes
Bigint	Yes
Decimal	Yes
Numeric	Yes
Real	Yes
Double	Yes
Smallserial	Yes
Serial	Yes
Bigserial	Yes
Char	-
Charn	-
Varchar	-
Varcharn	-
Text	-
Bytes	-
Boolean	-
Date	-
Time	-
Timestamp	-
Bit	-

Rules and guidelines for JDBC V2 objects in mappings

Consider the following rules and guidelines for JDBC V2 objects used as sources and targets in mappings:

Schema names and table names

- When you specify the schema name and table name in the advanced properties or object properties, Data Integration honors the attributes in the following order of precedence:
  1. **SQL override**. The SQL statement to override the default query generated from the specified source type in the Source or Lookup transformation in a mapping.
  2. **Custom query**. The SQL statement to reduce the number of columns to query in the Source or Lookup transformation in a mapping.
  3. **Runtime advanced attributes**. The advanced properties such as schema name and table name in the Source, Target, or Lookup transformation in a mapping.
  4. **Connection attributes**. The schema attribute in the connection properties.
  5. **Object metadata**. The object type selected in the Source, Target, or Lookup transformation in a mapping.
- If you change the schema name in the connection, the updated schema name does not reflect in the user interface in the existing mapping object. However, the updated schema reflects at runtime.
- The mapping fails when the target table name contains double quotes.

Import objects

When you import a JDBC V2 object and search for special characters, the search results do not display the objects.

Multiple objects

- You can't parameterize multiple JDBC V2 source objects.
- When you join multiple Azure SQL Database tables, the schemas must have different table names.

Data types

- When you preview the data for time(4), time(5) and time(6) data types, the data is truncated beyond precision 3.
- Do not specify a filter in a mapping for the Azure SQL Database source that contains the Datetime data type.
- When you read or write data that contains time(4), time(5), and time(6) data types, the data is truncated beyond precision 3.
- When you write data that contains the Timestamp data type to a PostgreSQL or Azure SQL Database target using the **Create New at Runtime** option, the Timestamp data type value is appended with the time zone.
- When you create a new Azure SQL or PostgreSQL Database target at runtime and the source data contains the Time data type, the Secure Agent writes the date time value until microseconds.

Partitioning

You can't configure partitioning in a mapping.

Salesforce Data Cloud read

- When you read data from Salesforce Data Cloud and the source contains Date or Datetime data type, the mapping stops responding. To resolve the issue, change the Date or Datetime datatype fields to String in the source object and in the corresponding field mapping.

SQL query

- Ensure that the list of selected columns, the data types, and the order of the columns that appear in the query matches the columns, data types, and order in which they appear in the source object.
- You can't use an SQL query to read data from a Salesforce data lake.

Oracle synonym

You can't read from or write to a synonym of an Oracle synonym.

Rules and guidelines for JDBC V2 objects in mappings configured in advanced mode

Consider the following rules and guidelines for JDBC V2 objects for mappings configured in advanced mode:

Unicode and special characters

- When you import multiple source objects, ensure that the table and column names do not contain Unicode characters.
- Ensure that the source or target table names and field names do not contain special characters.
- When you import a JDBC V2 object and search for special characters, the search results do not display the objects.
- The mapping fails when the target table name contains double quotes.

Schema names and table names

- If you change the schema name in the connection, the updated schema name does not reflect in the user interface in the existing mapping object. However, the updated schema reflects at runtime.
- When you join multiple Azure SQL Database tables, the schemas must have different table names.

Data types

- When you preview the data for time(4), time(5) and time(6) data types, the data is truncated beyond precision 3.
- Do not specify a filter in a mapping for the Azure SQL Database source that contains the Datetime data type.
- When you read or write data that contains time(4), time(5), and time(6) data types, the data is truncated beyond precision 3.
- When you write data that contains the Timestamp data type to a PostgreSQL or Azure SQL Database target using the **Create New at Runtime** option, the Timestamp data type value is appended with the time zone.
- When you create a new Azure SQL or PostgreSQL Database target at runtime and the source data contains the Time data type, the Secure Agent writes the date time value until microseconds.
- When you read from or write to an Oracle table that contains the Number data type, even though the precision does not exceed the maximum allowed value of 38, the mapping adds additional digits to the data. To avoid issues with the Number data type precision, select the **Apply Custom Schema** advanced property in the Source or Target transformations, based on the operation that you configure.

Parameterization

- When you configure the field mapping and the source or target object is parameterized, set the field mapping to **Automap**. If you set the field mapping to **Manual**, the mapping does not run in advance mode.
- You can't parameterize multiple JDBC V2 source objects.

Target operations

- When you perform an update, upsert, delete, or data driven operation, ensure that the following conditions are met:
  - All fields are mapped in the **Field Mapping** tab in the Target transformation.
  - The source and target schemas are identical to avoid mismatches and runtime errors.
- You must specify a column in the **Update Columns** field, even if the target table has a defined primary key.
- If the target table doesn't have a defined primary key and multiple rows match the update condition, the mapping might insert records alongside updating and upserting, which can lead to duplicate records in the target table.
- You can't use multiple PostgreSQL sources in a mapping when you perform an update, upsert, delete, or data driven operation on the target.
- You can't perform an update, upsert, delete, or data driven operation on Oracle synonyms.
- To perform a data driven operation on the target, ensure that the column selected in the **Update Columns** field doesn't contain duplicate or null values.
- When you run a mapping with an upsert or data driven target operation, the number of processed and failed rows for the target operation is not displayed on the **Individual Task Results** page.
- Consider the following guidelines for the **Truncate Target** option:
  - If you don't select the **Truncate Target** option, the mapping might drop and recreate the target table, which doesn't retain table constraints such as primary keys, indexes, and foreign keys. To retain existing table constraints, you must select the **Truncate Target** option while configuring the target object.
  - If you select the **Truncate Target** option when performing an update, upsert, delete, or data driven operation, and a user error occurs, such as a primary key violation, you might encounter data loss.

Partitioning

When you configure partitioning for the source or target object that contains an Oracle synonym and the synonym contains a primary key, select the partition key in the **Fields** tab of the Source or Target transformation based on the operation that you configure.

Oracle synonym

You can't read from or write to a synonym of an Oracle synonym.

CHAPTER 4

Migrating a mapping

You can configure a connection and mapping in one environment, then migrate and run the mapping in another environment.

Data Integration uses the configured runtime attributes from the earlier environment and runs the mapping successfully in the new environment.

You can also migrate mappings configured in advanced mode. After the migration, you can change the connection properties from the Administrator service, but you don't need to modify the mapping.

Consider a scenario where you develop a mapping in the development organization (Org 1) and then you migrate and run the mapping in the production organization (Org 2). After you migrate, you might want to use the same or a different connection endpoint or object path in Org 2. Based on your requirement, follow the guidelines in this section before you plan the migration.

Use the same object path for the migrated mapping

If you want the migrated mapping to use the same object path as in the earlier environment, you need to maintain the same schema and table in the JDBC V2 connection for both the earlier and the new environments.

For example, if you have two different connections, Connection1 used for Org 1 and Connection2 used for Org 2, the object path for the schema and table name needs to be the same in both connections.

Connection1: SCHEMA1/TABLE1

Connection2: SCHEMA1/TABLE1

In this scenario, you don't need to override the schema and table in the advanced properties.

Use a different object path for the migrated mapping

After you migrate the mapping, you can use a different object path to run the mapping from the new environment.

Before you migrate the mapping, you can change the object metadata or the runtime attributes to reflect the object path in the migrated environment. You don't have to edit or update the mapping in the new environment.

As a rule, when you specify the schema and table in the advanced properties or object properties, Data Integration honors the attributes in the following order of precedence:

1. **SQL override**. The SQL statement to override the default query generated from the specified source type in the Source or Lookup transformation in a mapping.
2. **Custom query**. The SQL statement to reduce the number of columns to query in the Source or Lookup transformation in a mapping.
3. **Runtime advanced attributes**. The advanced properties such as schema name and table name in the Source, Target, or Lookup transformation in a mapping.
4. **Connection attributes**. The schema attribute in the connection properties.
5. **Object metadata**. The object type selected in the Source, Target, or Lookup transformation in a mapping.

Migration options

When you migrate, you can choose one of the following options to update the object path:

Option 1. Update the connection properties to reference the new object

When you import the mapping to the new environment, you can change the existing connection in the **Review Connections** section to one that has access to the specified schema and table in the new environment.

Option 2. Override the properties from the advanced properties

Before the migration, specify the required schema and table name for the object from the new environment in the advanced properties of the mapping in the earlier environment. After the migration, when you run the mapping, the Secure Agent uses the configured advanced parameters to override the object specified in the mapping imported from the earlier environment.

Option 3. Parameterize the properties in the mapping

You can choose to parameterize the advanced attributes, such as the schema and table name before the migration. You can configure input parameters, in-out parameters, and parameter files in the mapping.

If you have used in-out parameters, you can change the schema and table attributes using the parameter file so that the changes are applied when the task runs.

You can't override the input parameters from the parameter file in the advanced properties. You need to use the in-out parameter to override the value from the parameter file.

Parameterizing only the advanced properties, but not the object in the mapping

If you want to parameterize only the advanced properties and use them at run time, select a placeholder object in the object properties within the mapping, and then specify an override for this placeholder object in the advanced properties.

Ensure that the placeholder object contains the same metadata as the corresponding table that you specify as an override. When you run the mapping, the value specified in the advanced property overrides the placeholder object.

Parameterizing both the object and the advanced properties

If you want to keep both the JDBC V2 object type and the advanced fields parameterized, you need to leave the **Allow parameter to be overridden at runtime** option cleared in the input parameter window while adding the parameters, and then select the required object at the task level. When you run the task, the values specified in the advanced properties take precedence.

Rules and guidelines for migrating a mapping

Consider the following rules and guidelines when you use the same or a different object path for the migrated mapping:

- The following table lists the transformation, object type, and the fields in the advanced properties of a mapping that you can retain when you migrate to the new environment:

Transformations	Object Type	Advanced Fields
Source	Single object	Schema and table name
Lookup	Single object **Note:** Applicable for unconnected and connected, cached and uncached.	
Target	Single object	

- You can't dynamically refresh the data object schema at run time. You need to maintain the same metadata for the table selected in the Source, Target, or Lookup transformation and the corresponding advanced field overrides, as schema change handling is not applicable.
- You can't migrate a mapping that uses the Hosted Agent as the runtime environment.
- If the mapping contains an advanced filter for the object in the **Query Options** section and an override of the object in the advanced properties, you need to use the object specified as an override in the advanced properties to define the condition.
- If the mapping contains multiple objects, you can't override the schema and table name from the advanced properties.

APPENDIX A

JDBC V2 data type reference

Data Integration uses the JDBC type 4 driver to read data. The Secure Agent converts the JDBC data type to the transformation data type, and uses the transformation data type to move data across platforms.

When Data Integration writes to a JDBC V2 target, the Secure Agent converts the transformation data type to the corresponding JDBC V2 data type.

The following table compares the JDBC V2 data types that Data Integration supports to the transformation data types:

Aurora PostgreSQL Data Type	Transformation Data Type	Description
integer	integer	-2147483648 to 2147483647, precision 10, scale 0
smallint	integer	-32768 to 32767, precision 10, scale 0
bigint	bigint	-9223372036854775808 to 9223372036854775807, precision 19, scale 0
real	double	Precision 15
float	double	Precision 15
double_precision	double	Precision 15
decimal	decimal	Precision 1 to 38, scale 0 to 38
numeric	decimal	Precision 1 to 38, scale 0 to 38
boolean	string	Precision 6
char	string	1 to 10485760 characters
varchar	string	1 to 10485760 characters
date	date/time	January 1, 0001, through December 31, 9999
time	date/time	00:00:00.000 through 23:59:59.999

Aurora PostgreSQL Data Type	Transformation Data Type	Description
timestamp	date/time	Date range: January 1, 0001, through December 31, 9999 time range: 00:00:00 through 23:59:59.997
nchar	string	1 to 10485760 characters

JDBC V2 and transformation data types for Create New at Runtime option

The following table lists the transformation data types that Data Integration supports and the corresponding Aurora PostgreSQL data types when you use the **Create New at Runtime** option:

Transformation Data Type	PostgreSQL Data Type
double	float
varbinary	bytea
binary	bytea
tinyint	integer
time	timestamp
smallint	integer
numeric	numeric
real	float
float	float
char	varchar
nchar	varchar
varchar	varchar
nvarchar	varchar
timestamp	timestamp
boolean	varchar
decimal	numeric

Transformation Data Type	PostgreSQL Data Type
bigint	integer
integer	integer

The following table lists the transformation data types that Data Integration supports and the corresponding Azure SQL Database data types when you use the **Create New at Runtime** option:

Transformation Data Type	Azure SQL Database Data Type
date	datetime2(7)
binary	varbinary
tinyint	int
time	datetime2(7)
smallint	int
numeric	decimal
char	nvarchar
nchar	nvarchar
varchar	nvarchar
nvarchar	nvarchar
real	float
float	float
timestamp	datetime2(7)
boolean	varchar
decimal	decimal
bigint	bigint
integer	int

Rules and guidelines for data types

Consider the following rules when you import data types:

- When you import data from Aurora PostgreSQL that contains the varchar data type and the data size is less than 100 MB, the original precision of the Varchar data type is retained. However, if the data size is more than 100 MB, the Secure Agent imports the Varchar data type with a default precision of 4000.
- Consider the following rules when you use the **Create New at Runtime** option to write to an Azure SQL Database target:
  - When the precision of the char(n), nchar(n), varchar(n), and nvarchar(n) data types is more than 4000, the Secure Agent writes these data types as ntext. If the precision is less than 4000, the Secure Agent writes these data types as nvarchar.
  - When the precision of the binary(n) and varbinary(n)) data types is more than 8000, the Secure Agent writes these data types as images. If the precision is less than 8000, the Secure Agent writes these data types as varbinary.

INDEX

A

advanced source properties 15
advanced target properties 18

C

Cloud Application Integration community
  URL 5
Cloud Developer community
  URL 5
commit interval
  default 18
connections
  JDBC V2 9
Create target
  rules and guidelines 20

D

Data Integration community
  URL 5
data types 31
databases 7

E

error file directory 18

I

Informatica Global Customer Support
  contact information 6
Informatica Intelligent Data Management Cloud
  web site 5

J

JDBC data type 31
JDBC type 4 driver 7
JDBC V2
  connection properties 9
JDBC V2 connector
  rules and guidelines 24, 26
JDBC V2 Connector
  assets 7
JDBC V2 objects
  lookups 21

L

lookups
  Mappings 21

M

maintenance outages 6
mappings
  source properties 15
  target properties 18
Mappings in advanced mode
  example 22

N

number of rows to be fetched 15

P

page size 15

S

source properties 15
status
  IDMC 6
success file directory 18
system status 6

T

target properties 18
transformation data type 31
trust site
  description 6

U

upgrade notifications 6

W

web site 5