Informatica® Cloud Data Integration

Salesforce Data 360 Connector

Informatica Cloud Data Integration Salesforce Data 360 Connector
October 2026

© Copyright Informatica LLC 2024, 2026

This software and documentation are provided only under a separate license agreement containing restrictions on use and disclosure. No part of this document may be reproduced or transmitted in any form, by any means (electronic, photocopying, recording or otherwise) without prior consent of Informatica LLC.

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation is subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License.

Informatica, the Informatica logo, Informatica Cloud, and PowerCenter are trademarks or registered trademarks of Informatica LLC in the United States and many jurisdictions throughout the world. A current list of Informatica trademarks is available on the web at https://www.informatica.com/trademarks.html. Other company and product names may be trade names or trademarks of their respective owners.

Portions of this software and/or documentation are subject to copyright held by third parties. Required third party notices are included with the product.

See patents at https://www.informatica.com/legal/patents.html.

DISCLAIMER: Informatica LLC provides this documentation "as is" without warranty of any kind, either express or implied, including, but not limited to, the implied warranties of noninfringement, merchantability, or use for a particular purpose. Informatica LLC does not warrant that this software or documentation is error free. The information provided in this software or documentation may include technical inaccuracies or typographical errors. The information in this software and documentation is subject to change at any time without notice.

NOTICES

This Informatica product (the "Software") includes certain drivers (the "DataDirect Drivers") from DataDirect Technologies, an operating company of Progress Software Corporation ("DataDirect") which are subject to the following terms and conditions:

1. THE DATADIRECT DRIVERS ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT.
2. IN NO EVENT WILL DATADIRECT OR ITS THIRD PARTY SUPPLIERS BE LIABLE TO THE END-USER CUSTOMER FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, CONSEQUENTIAL OR OTHER DAMAGES ARISING OUT OF THE USE OF THE ODBC DRIVERS, WHETHER OR NOT INFORMED OF THE POSSIBILITIES OF DAMAGES IN ADVANCE. THESE LIMITATIONS APPLY TO ALL CAUSES OF ACTION, INCLUDING, WITHOUT LIMITATION, BREACH OF CONTRACT, BREACH OF WARRANTY, NEGLIGENCE, STRICT LIABILITY, MISREPRESENTATION AND OTHER TORTS.

The information in this documentation is subject to change without notice. If you find any problems in this documentation, report them to us at infa_documentation@informatica.com.

Informatica products are warranted according to the terms and conditions of the agreements under which they are provided. INFORMATICA PROVIDES THE INFORMATION IN THIS DOCUMENT "AS IS" WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING WITHOUT ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND ANY WARRANTY OR CONDITION OF NON-INFRINGEMENT.

Publication Date: 2026-10-15

Table of Contents

Preface 4

Informatica Resources 4

- Informatica Documentation 4
- IDMC web site 4
- IDMC Communities 4
- IDMC Marketplace 4
- Data Integration connector documentation 5
- Informatica Knowledge Base 5
- IDMC Trust Center 5
- IDMC Pulse Dashboard 5
- Informatica Global Customer Support 5

Chapter 1: Introduction to Salesforce Data 360 Connector 6

Salesforce Data 360 Connector assets 6

Chapter 2: Salesforce Data 360 connections 7

Connect to Salesforce Data 360 7

- Before you begin 7
- Connection details 8
- Advanced settings 9

Chapter 3: Mapping and mapping tasks with Salesforce Data 360 Connector 11

Salesforce Data 360 sources in mappings 11

Salesforce Data 360 targets in mappings 12

- Create a target at run time 13

Enabling Bulk API ingestion mode 14

Rules and guidelines for mappings 15

Chapter 4: Data type reference 16

Salesforce Data 360 and transformation data types 16

Chapter 5: Troubleshooting 18

Troubleshooting Salesforce Data 360 Connector 18

Index 19

Preface

Use *Salesforce Data 360* to learn how to read from and write to Salesforce Data 360. Learn to create a Salesforce Data 360 connection, develop and run mappings and mapping tasks in Cloud Data Integration.

Informatica Resources

Informatica provides you with a range of product resources through the Informatica Network and other online portals. Use the resources to get the most from your Informatica products and solutions and to learn from other Informatica users and subject matter experts.

Informatica Documentation

Use the Informatica Documentation Portal to explore an extensive library of documentation for current and recent product releases. To explore the Documentation Portal, visit https://docs.informatica.com.

If you have questions, comments, or ideas about the product documentation, contact the Informatica Documentation team at infa_documentation@informatica.com.

IDMC web site

You can access the Informatica® Intelligent Data Management Cloud™ (IDMC) web site at http://www.informatica.com/cloud.

IDMC Communities

Use the IDMC Community to discuss and resolve technical issues. You can also find technical tips, documentation updates, and answers to frequently asked questions.

Access the IDMC Community at:

https://network.informatica.com/community/informatica-network/products/cloud-integration

Developers can learn more and share tips at the Cloud Developer community:

https://network.informatica.com/community/informatica-network/products/cloud-integration/cloud-developers

IDMC Marketplace

Visit the Informatica Marketplace to try and buy Data Integration Connectors, templates, and mapplets:

https://marketplace.informatica.com/

Data Integration connector documentation

You can access documentation for Data Integration Connectors at the Documentation Portal. To explore the Documentation Portal, visit https://docs.informatica.com.

Informatica Knowledge Base

Use the Informatica Knowledge Base to find product resources such as how-to articles, best practices, video tutorials, and answers to frequently asked questions.

To search the Knowledge Base, visit https://search.informatica.com. If you have questions, comments, or ideas about the Knowledge Base, contact the Informatica Knowledge Base team at KB_Feedback@informatica.com.

IDMC Trust Center

The IDMC Trust Center provides information about Informatica security, compliance, and privacy practices.

You can access the trust center at https://trust.informatica.com/.

IDMC Pulse Dashboard

The IDMC Pulse Dashboard provides system status and upgrade information for all PODs and services across IDMC.

Follow the services you use and subscribe to alerts to receive notifications about upgrades, maintenance, production incidents, and upcoming releases. The IDMC Pulse Dashboard displays the production status of all the IDMC products. All maintenance updates are posted to this page, and during an outage, it will have the most current information. To ensure you are notified of updates and outages, you can subscribe to receive updates for a single service or all IDMC services. Subscribing to all services is the best way to be certain you never miss an update.

For more information, see the Service Status and Communications guide.

Informatica Global Customer Support

You can contact a Global Support Center through the Informatica Network or by telephone.

To find online support resources on the Informatica Network, click **Contact Support** in the IDMC Help menu to go to the **Cloud Support** page. The **Cloud Support** page includes system status information and community discussions. Log in to Informatica Network and click **Need Help** to find additional resources and to contact Informatica Global Customer Support through email.

The telephone numbers for Informatica Global Customer Support are available from the Informatica web site at https://www.informatica.com/services-and-training/support-services/contact-us.html.

CHAPTER 1

Introduction to Salesforce Data 360 Connector

You can use Salesforce Data 360 Connector to securely read data from data lake objects and data model objects, and write data to data lake objects in Salesforce Data 360.

Use a Salesforce Data 360 connection in Source and Target transformations in mappings and mapping tasks to read data from and write data to Salesforce Data 360.

Salesforce Data 360 Connector assets

Create assets in Data Integration to integrate data using Salesforce Data 360 Connector.

When you use Salesforce Data 360 Connector, you can include the following Data Integration assets:

- Mapping
- Mapping task

For more information about configuring assets and transformations, see *Mappings*, *Transformations*, and *Tasks* in the Data Integration documentation.

CHAPTER 2

Salesforce Data 360 connections

Create a Salesforce Data 360 connection to securely read data from and write data to Salesforce Data 360.

Before you create a connection, enable the connector for the runtime environment. For more information about enabling connectors, see *Service and connector assignment* in the Administrator help.

You can use a Salesforce Data 360 connection to specify sources and targets in mappings and mapping tasks.

Connect to Salesforce Data 360

Let's configure the Salesforce Data 360 connection properties to connect to Salesforce Data 360.

Before you begin

Before you get started, make sure that you complete the following prerequisites:

- Create an external client app in Salesforce Data 360, and assign at least the following scopes to the app:
  - Manage user data via APIs (api)
  - Manage Data 360 Ingestion API data (cdp_ingest_api)
  - Perform ANSI SQL queries on Data Cloud data (cdp_query_api)

  For more information about configuring your external client app, see Salesforce Data 360 Quick Start.
- Get the consumer key and consumer secret from the external client app to generate the access token.
- Create an Ingestion API data stream to load data to an existing target.
  For more information about Ingestion API data stream, see Ingestion API.

Connection details

The following table describes the basic connection properties:

Property	Description
Connection Name	Name of the connection. Each connection name must be unique within the organization. Connection names can contain alphanumeric characters, spaces, and the following special characters: _ . + -, Maximum length is 255 characters.
Description	Description of the connection. Maximum length is 4000 characters.
Use Secret Vault	This property appears only if secrets manager is set up for your organization. However, this property doesn't apply to a Salesforce Data 360 connection.
Runtime Environment	The name of the runtime environment where you want to run tasks. Select a Secure Agent, Hosted Agent, or elastic runtime environment. For more information about runtime environments, see *Runtime Environments* in the Administrator help.
Authentication Type	The authentication method to connect to Salesforce Data 360. Default is OAuth 2.0 client credentials.
Access Token URL	The endpoint where OAuth 2.0 requests are sent to obtain an access token to connect to the Salesforce Data 360 instance. Specify the URL in the following format: `https://<Salesforce Data 360 organization ID>.salesforce.com/services/oauth2/token`
Client ID	Client ID of your application to connect to Salesforce Data 360.
Client Secret	The client secret associated with the client ID.
Access Token	The access token value. Click **Generate Access Token** to populate the access token value.

Advanced settings

The following table describes the advanced connection properties:

Property	Description
Retry Count	The total number of retries to get the response from the Salesforce Data 360 endpoint based on the HTTP status codes. Enter a positive integer. Default is 3.
Retry Interval	The wait time in milliseconds before the Salesforce Data 360 connection makes another attempt to receive a response. Enter a positive integer. Default is 5000 milliseconds.

Additional Properties	Additional properties that you can configure in the Salesforce Data 360 connection, such as specifying a custom data space, defining properties for connections and data streams.
	You can specify multiple properties, separated by an ampersand and colon (&:), in the following format:
	`<key1>=<value>&:<key2>=<value>&:<key3>=<value>`
	For example, you can specify a custom data space when you choose query as your source object:
	`customQueryDataSpace=My_Dataspace`
	For the list of properties that you can configure, see Configure additional properties.

Configure additional properties

You can use the additional properties field in the advanced settings to customize and set any additional properties in a Salesforce Data 360 connection.

Specify a custom data space.

- **customQueryDataSpace.** A custom data space that you can use when you choose query as your source object.
  For example, `customQueryDataSpace=My_Dataspace`

  If you do not specify a data space, the default data space of your organization is considered.

Configure status codes and timeout properties.

- **okhttp.retryStatusCodes.** A list of HTTP status codes that indicate transient errors for which a request should be retried.
  Default codes are 429,500,502,503,504.
- **okhttp.connectTimeout.** The maximum wait time in seconds that the Salesforce Data 360 connection waits for a response from the server.
  Default is 30 seconds.
- **okhttp.readTimeout.** The maximum wait time in seconds when an attempt is made to read a file from the server.
  Default is 30 seconds.
- **okhttp.writeTimeout.** The maximum wait time in seconds when an attempt is made to write a file to the server.
  Default is 30 seconds.

Configure data stream ingestion properties.

- **dataStreamIngestReadyInitialPollIntervalSeconds.** The initial poll interval duration in seconds that the Salesforce Data 360 Connector waits before making the first attempt to fetch the refresh date and time for the data stream.
  Default is 120 seconds.
- **dataStreamIngestReadyMaxWaitTimeSeconds.** The maximum wait time in seconds that the Salesforce Data 360 Connector will wait for the data stream to become ready to accept incoming data during the initial data load into the data lake object.
  Default is 1200 seconds.

Configure data stream active time properties.

- **dataStreamActiveInitialPollIntervalSeconds.**The initial poll interval duration in seconds that the Connector waits before making the first attempt to fetch the data stream status.
  Default is 1 second.
- **dataStreamActiveMaxWaitTimeSeconds.**The maximum wait time in seconds for the data stream status to transition to Active after successful creation.
  Default is 60 seconds.

For example,

```
okhttp.retryStatusCodes=429,500,502,503,504&:okhttp.connectTimeout=30&:dataStreamActiveMaxWai
tTimeSeconds=60&:dataStreamActiveInitialPollIntervalSeconds=1
```

CHAPTER 3

Mapping and mapping tasks with Salesforce Data 360 Connector

Use the Data Integration Mapping Designer to create a mapping. When you create a mapping, you configure a source or target to represent a Salesforce Data 360 object.

Salesforce Data 360 sources in mappings

To read data from Salesforce Data 360, configure a Salesforce Data 360 object as a source in a mapping.

The following table describes the Salesforce Data 360 source properties that you can configure in a Source transformation:

Property	Description
Connection	Name of the source connection.
Object Type	Type of the source object. Select one of the following object types: - Single Object - Query - Parameter Default is Single Object.
Object	Name of the source object. Select a source object from a data space. If you want to query an object from a custom data space, see "Configure additional properties" on page 9.
Parameter	This property appears only if you select parameter as the object type. A placeholder to dynamically assign values for the source object at run time without the requirement to edit the task. Select an existing parameter for the source object or click **New Parameter** to define a new parameter for the source object. To overwrite the parameter at run time, select the **Allow parameter to be overridden at run time** option.

Property	Description
Filter	Filters records based on the filter condition. You can specify one of the following filter conditions: - Not parameterized. Uses a basic filter to specify the object, field, operator, and value to select specific records. - Completely parameterized. Uses a parameter to represent the field mapping. - Advanced. Uses an advanced filter to define a more complex filter condition. Default is Not parameterized. **Note:** Contains, Starts With, and Ends With filter operations apply only to the Advanced filter condition.
Sort	Does not apply to a Salesforce Data 360 connection.

Salesforce Data 360 targets in mappings

To write data to Salesforce Data 360, configure a Salesforce Data 360 object as a target in a mapping.

The following table describes the target properties that you can configure for a Salesforce Data 360 target

Property	Description
Connection	Name of the Salesforce Data 360 source connection. You can select an existing connection or create a new connection. You can also click **New Parameter** to define a parameter for the target connection.
Target Type	Type of the target object. Select one of the following options: - Single Object - Parameter
Object	Name of the target object. You can select an existing object or create a new target at run time. To write data to an existing object, select an object from the Ingestion API connectors.
Operation	Type of the target operation. Select from one of the following operations: - Insert - Upsert - Delete **Note:** In Salesforce Data 360, the insert operation performs the same function as the upsert operation.

The following table describes the Salesforce Data 360 advanced target properties:

Property	Description
Ingestion Mode	The ingestion mode to write data into Salesforce Data 360. Select one of the following modes based on the data volume, processing speed, and near real-time requirements: - **Streaming API.** Select to process near-real-time micro-batch datasets. - **Bulk API.** Select to load large datasets. Before you use the Bulk API ingestion mode, you need to enable a property for the Secure Agent. For more information, see "Enabling Bulk API ingestion mode" on page 14.
Ingestion API Connector Name	Required when you don't choose an object from Ingestion API connectors. The name of the Ingestion API connector used for data ingestion into Salesforce Data 360. This API specifies the structure and format of the payload data to ensure compatibility and efficient processing. For example, in the URL, `https://{instance_url}/api/v1/ingest/sources/EmpOrder/Order`, the ingestion API connector name is `EmpOrder`.
Object Name	Required when you don't choose an object from Ingestion API connectors. Name of the Salesforce data lake object where you want to write the data. For example, in the URL, `https://{instance_url}/api/v1/ingest/sources/EmpOrder/Order`, the object name is `Order`. **Note:** When you configure an incorrect object name, the Salesforce Data 360 streaming API returns a success response, but you cannot read the data. This is a Salesforce Data 360 limitation.

Create a target at run time

You can use an existing target or create a target to hold the results of a mapping. If you choose to create the target, the agent creates the target if it does not exist already when you run the task.

Before you create a target at runtime, ensure that the fields from the source or upstream transformations meet the necessary schema file requirements. For more information, see Requirements for Ingestion API Schema File.

To specify the target properties, perform the following tasks:

1. Select the Target transformation in the mapping.
2. To specify the target, click the **Target** tab.
3. Select the target connection.
4. For the target type, choose **Single Object** or **Parameter**.
5. Specify the target object or parameter.
6. To specify a target object, perform the following tasks:
   a. Click **Select** and choose a target object. You can select an existing target object or create a new target object at run time.
   b. To create a target object at runtime, select **Create New at Runtime**.

c. Configure the following target properties:

Property	Description
Object Name	The name of the target object.
Data Space	The name of the data space to organize your data. If left empty, the default data space of your organization is considered.
Primary Key	The primary key or unique identifier of your source object that is required to create a data stream in Salesforce Data 360. If the source object does not have a primary key, specify a field that uniquely identifies each record.
Category	The type of data used in the data stream. You can define the following types of data: - Engagement. Select this if your dataset is time-series oriented. You must specify the event time using the **Event Time** Field. - Profile. Select this if your dataset consists of entities, such as individuals, businesses, employees, or devices with unique identifiers that you want to segment, unify, or enrich. - Other. Select this if your dataset serves as reference data with descriptive attributes for profile or engagement records.
Record Modified Field	This field applies to Profile and Other categories. The name of the field that captures the date or timestamp when the record was last modified. serves as a reference point for when the incoming record was last modified.
Event Time Field	This field is required if you select the Engagement category. The name of the field that captures when an event occurred.
Path	Required. The folder path of the target object. Specify the path in the following format: `/Ingestion API Connectors/<name of the ingestion API connector>`

7. Click **OK**.

Enabling Bulk API ingestion mode

Before you use the Bulk API ingestion mode to load large data sets to Salesforce Data 360, set the INFA_DTM_STAGING_ENABLED_CONNECTORS property for the Secure Agent.

Perform the following tasks to set the property:

1. In Administrator, click **Runtime Environments**.
   The Runtime Environments page appears.
2. Select the Secure Agent for which you want to set the custom configuration property.
3. Click the **Edit Secure Agent** icon corresponding to the Secure Agent that you want to edit in **Actions**.
   The Edit Secure Agent page appears.
4. In the **System Configuration Details** section, select the **Service** as **Data Integration Server** and the Type as **Tomcat**.

5. Set the value of the `INFA_DTM_STAGING_ENABLED_CONNECTORS` property to the plugin ID of the Salesforce Data 360 Connector.
   The plugin ID for Salesforce Data 360 is 645402.

   The following image shows the `INFA_DTM_STAGING_ENABLED_CONNECTORS` property set for the Secure Agent:

6. Click **Save**.

Before running the tasks, ensure that the new version of the service is available.

Rules and guidelines for mappings

Consider the following rules and guidelines for Salesforce Data 360 objects used as targets in mappings:

- You can't preview data in a Target transformation.
- You can perform read and write operations on an object within a single active job at a time. Ensure that no multiple jobs are running concurrently on the same object, either within or outside Intelligent Data Management Cloud services.
- Field names in Salesforce Data 360 display with suffix __c. In the mapping, the names of the target fields are the Field API Name without the suffix __c.
- The streaming API job completes after it reads the data from source and pushes it to the target. However, the data is not loaded in the target immediately. It might take a few minutes.
- The job statistics displays the number of rows that the mapping successfully reads from the source. It does not display the success and rejected records from Salesforce Data 360.
- When you delete data using bulk API in Salesforce Data 360, ensure that you map only the primary key from your source in the mapping to the corresponding primary key of the target Salesforce records that you want to delete.
- When you create a new target using an Ingestion API Connection, use the Bulk API ingestion mode to avoid a delay in loading data into the data stream. For subsequent runs of the mapping, you can use the Streaming API.
- NULL values in the primary key field are inserted into the target object without generating an error. This is a Salesforce Data 360 limitation.

CHAPTER 4

Data type reference

Data Integration uses the following data types in mappings and mapping tasks with Salesforce Data 360:

Salesforce Data 360 native data types: Salesforce Data 360 data types appear in the fields tab for Target transformations when you choose to edit metadata for the fields.

Transformation data types: These data types are set of data types that appear in the remaining transformations. They are internal data types based on ANSI SQL92 generic data types, which Informatica Cloud uses to move data across platforms. Transformation data types appear in all transformations in a mapping.

When Data Integration reads source data, it converts the native data types to the comparable transformation data types before transforming the data. When Data Integration writes to a target, it converts the transformation data types to the comparable native data types.

Salesforce Data 360 and transformation data types

The following table describes the Salesforce Data 360 data types that Data Integration supports and the corresponding transformation data types:

Salesforce Data 360 Data Type	Transformation Data Type	Range and Description
Boolean	String	1 to 5 characters.
Date	Date/Time	January 1,0001 to December 31,9999.
Datetime	Date/Time	0001-01-01T00:00:00.000Z to 9999-12-31T23:59:59.999Z
Email	String	1 to 31,072 characters.
Number	Decimal	Precision 1 to 28, scale 18.
Currency	Decimal	Precision 1 to 28, scale 18.
Percent	Decimal	Precision 1 to 28, scale 18.
Phone	String	1 to 31,072 characters.

Salesforce Data 360 Data Type	Transformation Data Type	Range and Description
Text	String	1 to 104,857,600 characters.
URL	String	1 to 31,072 characters.

CHAPTER 5

Troubleshooting

Use the following sections to troubleshoot errors in Salesforce Data 360 Connector.

Troubleshooting Salesforce Data 360 Connector

Cannot create the target due to the following reason: [timeout]

When creating a new target at run time, the data stream creation API response might be delayed due to intermittent network issues or timeouts.

Workaround: Increase the retry count and retry interval values in the advanced connection properties to keep the session active and continue retrying the API response.

Error occurred while fetching the Data Lake Objects. Error Code: [400]

When you create a new target at run time, data stream creation might fail with a 400 bad request error code.

Workaround: Run the mapping again to reinitiate the data stream creation process.

INDEX

C

Cloud Application Integration community
  URL 4
Cloud Developer community
  URL 4
connections
  Salesforce Data 360 7

D

Data Integration community
  URL 4

I

Informatica Global Customer Support
  contact information 5
Informatica Intelligent Data Management Cloud
  web site 4

M

maintenance outages 5

S

Salesforce Data 360
  connection properties 7
Salesforce Data 360 Connector
  connector overview 6
  tasks and object types 6
Salesforce Data 360 data types
  overview 16
status
  IDMC 5
system status 5

T

trust site
  description 5

U

upgrade notifications 5

W

web site 4